
# McIDAS-MVS

Man computer Interactive Data Access System for IBM mainframes running MVS-SP, MVS-XA or MVS-ESA

# Users Guide

Issued April 1993
Revised 1996





Space Science and Engineering Center University of Wisconsin - Madison 1225 West Dayton Street Madison, WI 53706 Telephone (608)262-2455 Fax (608) 263-6738

# Copyright<sup>©</sup> 1996 Space Science and Engineering Center (SSEC) University of Wisconsin - Madison All Rights Reserved

Permission is granted to make and distribute verbatim copies of this manual, provided the copyright notice and this permission are preserved on all copies.

SSEC makes no warranty of any kind with regard to the software or accompanying documentation, including but not limited to the implied warranties of merchantability and fitness for a particular purpose. SSEC does not indemnify any infringement of copyright, patent, or trademark through use or modification of this software.

Mention of any commercial company or product in this document does not constitute an endorsement by SSEC. Many of the designations used by manufacturers and sellers to distinguish their products are claimed as trademarks. Where those designations appear in this manual, and SSEC was aware of the trademark claim, the designations are printed in caps or initial caps.

The information in this manual is subject to change without notice. Considerable effort has been expended to make this document accurate and complete, but SSEC cannot assume responsibility for inaccuracies, omissions, manufacturers' claims or their representations.

# **Preface**

The purpose of this manual is to assist meteorologists in the structure of McIDAS user commands. The user of this manual is assumed to have a prior working knowledge of McIDAS. This manual contains several hundred user level commands. Each command includes a description of its usage, a breakdown of all positional parameters and keywords, and practical examples.

# Table of Contents

Chapter 1. System Startup and Utilities
Chapter 2. Graphics Applications
Chapter 3. String Tables
Chapter 4. Areas
Chapter 5. Derived Image Products
Chapter 6. Frame Analysis
Chapter 7. MD Files
Chapter 8. Gridded Data Files
Chapter 9. Weather Analysis
Chapter 10. TOVS and VAS Retrievals
Chapter 11. Cloud Drift Winds
Chapter 12. Command Schedulers
Chapter 13. System Navigation
Chapter 14. Appendices
Chapter 15. Index

# **Command Conventions**

The conventions used in documenting the commands in this manual are described below.

# Bold and Italicized Terms

Actual keyboard entries appear in BOLD type. You will type these entries exactly as they appear. Command names, some parameters, all keywords and examples are bolded. For example,

#### IGG MAKE 2 SUB 1

Variable entries, such as parameters, appear in italics. For example,

HELP command

If you wanted to list the online documentation for command CUR, you would type:

#### HELP CUR

Use capital letters and leave a space between each term or number in a command line.

#### Concatenating Commands

You can concatenate commands with semicolons. For example,

#### SF 3; EG 3; DF 101 3 EC MSN; MAP

Commands using quote fields can only be concatenated if the quote field is substituted with curly brackets ({}). For example, ZA 3 15 {MCIDAS}; LA 100 110.

Entering ZA 3 15 "MCIDAS; LA 100 110 won't work; it displays "MCIDAS; LA 100 110 as the text string.

#### Alt Key Entries

When you see an Alt entry, it means you will press two keys simultaneously. The Alt key is like the Shift key in that you hold it down while typing another key. For example,

Press: Alt C

means you should hold down the Alt key and press the C key.

#### **Screen Prompts**

System prompts and responses look like this:

Boxed text displayed in this typestyle indicates a screen message.

# Day and Time Standards

Many McIDAS commands ask for the time of day, satellite identifications and/or latitude and longitude locations. Only the standards below are accepted in McIDAS command formats. Parentheses indicate optional identification.

Sensor Source/Year/Day	Time	Latitude/Longitude		
SSYYDDD YYDDD	HH:MM:SS HH:MM	(-)DDD:MM:SS (-)DDD:MM		
YY/MM/DD MM/DD (SS)YY// SS///	HH: HH.fraction HH	(-)DDD: (-)DDD.fraction (-)		
where: SS sensor source YY year MM month DD day of month DDD Julian day	where: HH hours (GMT) MM minutes fraction fractional degree SS seconds : uses the current time	where: DDD degrees (West is positive) MM minutes SS seconds fraction fractional degree		

#### **Global Keywords**

Any McIDAS-MVS command can utilize the global keywords below.

- · ALSO=
- DEV=
- DTERM=
- VIRT=

#### **ALSO**

This keyword writes graphics to your workstation and the workstation number you designate. For example, ALSO=10 writes graphics on workstation 10 and your workstation. Keyword ALSO works only on workstations with identical configurations as the source workstation.

#### DEV

This keyword specifies the destination device of any output generated by a command.

DEV= C	sends all output to the text screen
P	sends all output to the printer
N	discards all output
F file A	appends the output to a specified LW file
F file R	replaces the output in a specified LW file
S	sends the output to the system line printer at SSEC
U	causes the current setting to remain unchanged

For example, LA 100 120 DEV=P runs the LA command and routes the output to the printer.

#### DTERM

This keyword writes graphics on the designated workstation. For example, DTERM=22 writes the graphics on workstation 22. Keyword DTERM works only on workstations with identical configurations as the source workstation.

#### VIRT

This keyword specifies a virtual graphics number. It applies only to commands that generate graphics. Use DMAP VIRT to list your files.

> simultaneously draws graphics on a graphics frame VIRT=number and stores them in the designated virtual graphic number; the range is 1 to 1024

For example, MAP USA VIRT=1 draws a USA map on the graphics frame and writes the output to the file VIRT0001. To restore it, use command SVG.

Command Information Most commands have Format, Parameter, Keyword, Remark and Example sections. However, some commands have only a Remarks section. To better understand the information in each of these sections, see the sample command description on the next page.

## **Command Name**

This line gives a brief description of the command's function.

#### **Format**

The format contains the command name along with any positional parameters and/or keywords it needs to perform its function. Commands can have several formats. Enter BOLDED terms exactly as they appear in the command format. *Italicized* terms are variables. You must enter a value or option in place of them in the command. If a format is too long to fit on one line, the second line is indented.

#### **Parameters**

Parameters are numbers or letters that provide information to a McIDAS-MVS command. To the right of each parameter is an explanation of its function. Enter parameters in the exact order specified in the command format. It is not always necessary to use every parameter. Enter BOLDED parameters exactly as they appear in the text. If a parameter is *italicized*, insert the appropriate number or letter in the command format. A quotation mark (quote field) is sometimes used to delineate a text string. The text string can be used as input to search a file, or to provide descriptive text to a command or database.

#### Keywords

Keywords further clarify a command function; they are optional. Keywords are from 1 to 6 characters, followed by an equals sign (or comma) and a value, e.g., COLOR=3 LAT=20 40 UNIT=A can be entered as COLOR,3 LAT,20 40 UNIT,A. Type text values exactly as they are listed with the keyword. Use as many keywords as you like in a single command format. Although keywords are listed alphabetically in the documentation, their order in the command line is not important. Just be sure they come after the parameters. To the right of each keyword is an explanation of its function. Most keywords may be truncated to three characters. For example, you can enter COL instead of COLOR, or UNI in place of UNIT.

#### Remarks

Additional information about the command is contained here.

#### See Also

Mentioned here are other related commands to reference.

#### **Examples**

One or more examples are provided for each command. If an example takes more than one line, the second line is indented. Directly below each bolded command line is an explanation of what the entry does.

# **Reader Response**

We would like your comments on our manual. Please take a moment to fill out this self-mailing form and return it to SSEC - McIDAS User Services and Documentation. Thank you.

Manual name (from the title page)									
On a day-to-day basis, do you actually need this manual in order to use the system?									
Have you fou	nd spe	ecific in	formation	onal use	es for thi	s manual? Please explain.			
Did you find	errors	or omis	ssions ir	n the ma	anual? I	Please be very specific.			
Please rate the	his ma	nual or	the fol	lowing	items fro	m 1 to 5, with 1 as low and 5 as high.			
Text	1	2	3	4	5				
Graphics	1		3	4	5				
Ease-of-use	1	$\overline{2}$	3	4	5				
Overall	1	2	3	4	5				
What is the b	est fe	ature of	this m	anual?					
					and-	Blail			
What is the v	worst f	eature (	of this r	nanual	?				
Your name a	nd titl	e							
Date									
McIDAS site			100316	C UIT	an infat	тик саныя воше			
		nor <del>t de</del>							
Address		-		PROPERTY.	Television of the least	remonth to WARD P			
Telephone	4	_				Madiscri, W. Sarce			
1		-							

Check here if you would like a written reply.

F	ol	d	H	er	е			

Fold Here

Space Science and Engineering Center
McIDAS User Services and Documentation, Room 611
University of Wisconsin - Madison
1225 West Dayton Street
Madison, WI 53706

# **Chapter 1. System Startup and Utilities**

Integer arithmetic utility	1-1
Lists country codes	1-2
Converts temperatures and computes wind chill	1-3
Converts units	1-4
Defines the cursor size, type and color	1-6
Copies the contents of an edit member into an LW file	1-8
Lists the name and size of McIDAS LW files	1-9
Lists the McIDAS command formats	1-10
Calculates the disk space needed for areas, MD files and grid files	1-12
Converts a Julian date to or from a Gregorian date	1-15
Lists the position of a polar orbiting satellite	1-16
Ends a McIDAS-MVS session	1-17
Begins a McIDAS-MVS session	1-18
Lists the 10 closest stations to the cursor position	1-21
Lists LW file space usage	1-22
Copies the contents of an LW file into an edit member	1-24
LW file utility	1-25
Mails messages to users, terminals or project numbers	1-27
Lists the international master weather station list	1-30
Defines a user logon password	1-32
Lists the time an orbiting sensor source views a ground point	1-33
Lists LW file text	1-34
Sends a mainframe LW file to a remote host or workstation	1-35
Lists text from source code files	1-37
Lists McIDAS-MVS command status	1-38
Lists McIDAS-MVS command status and terminal usage	1-39
Lists terminals and users logged on to McIDAS-MVS	1-40
Lists the sunrise and sunset for a date and location	1-41
Lists the logged on project number	1-42
Displays the McIDAS-MVS software version number	1-43
Sends a text message to the system operator	1-44
Recalls a previously entered command	1-45
Lists the next 20 source code lines	1-46
Lists the previous 20 source code lines	1-47
Lists McIDAS-MVS command status	1-48
Terminates a command	1-49
	Converts temperatures and computes wind chill Converts units Defines the cursor size, type and color Copies the contents of an edit member into an LW file Lists the name and size of McIDAS LW files Lists the McIDAS command formats Calculates the disk space needed for areas, MD files and grid files Converts a Julian date to or from a Gregorian date Lists the position of a polar orbiting satellite Ends a McIDAS-MVS session Begins a McIDAS-MVS session Lists the 10 closest stations to the cursor position Lists LW file space usage Copies the contents of an LW file into an edit member LW file utility Mails messages to users, terminals or project numbers Lists the international master weather station list Defines a user logon password Lists the time an orbiting sensor source views a ground point Lists LW file text Sends a mainframe LW file to a remote host or workstation Lists text from source code files Lists McIDAS-MVS command status Lists McIDAS-MVS command status Lists the sunrise and sunset for a date and location Lists the sunrise and sunset for a date and location Lists the logged on project number Displays the McIDAS-MVS software version number Sends a text message to the system operator Recalls a previously entered command Lists the next 20 source code lines Lists McIDAS-MVS command status

Issued 4/93

ii

Issued 4/93

### CALC

Integer arithmetic utility.

#### **Formats**

CALC value

CALC "expression

#### **Parameters**

value

decimal numbers (123, 909, -33, etc.), alphabetic characters (maximum of 4) or hexadecimal values

"expression

arithmetic expression containing the values in decimal, hexadecimal, characters and operators; the operators are:

- + addition
- subtraction
- \* multiplication
- / division
- \$ mod function
- exponentiation

#### Remarks

CALC works on integers only. If no parentheses are used, the normal hierarchy is observed. The output is in decimal, hexadecimal and character values.

Hexadecimal values must be preceded by a Z and evaluated as an expression.

#### **Examples**

#### CALC D

This entry lists the values below.

DEC: -1002422208 HEX: C4404040 CHAR: D

#### CALC "ZC4404040

This entry evaluates the hexadecimal value and displays the same results as shown above.

#### CALC "(365/52)\*24

This entry lists the values below.

DEC: 168 HEX: A8 CHAR: Y

# **CCODE**

Lists country codes.

**Format** 

CCODE country

**Parameter** 

country

country to list (default=ALL)

Remarks

If *country* is two characters, CCODE looks for the one country whose code matches it. If only one character or more than two characters are specified, all string matches are found.

**Examples** 

CCODE

This entry lists all country codes.

CCODE UK

This entry lists the country with UK as its country code.

CCODE FRANCE

This entry lists the country code for France.

CCODE ISLAND

This entry lists all countries that have the word ISLAND in them.

CCODE Z

This entry lists all country codes and countries that contain the letter Z.

# CT

Converts temperatures and computes wind chill.

**Format** 

CT centigrade mps fahrenheit kts

**Parameters** 

centigrade Centigrade temperature

mps

wind speed in mps

fahrenheit

Fahrenheit temperature

kts

wind speed in knots

Remarks

CT converts temperatures from Centigrade to Fahrenheit or Fahrenheit to Centigrade, and computes wind chill factor.

**Examples** 

CT 13

This entry converts 13°C to °F.

CT X X 45

This entry converts 45°F to °C.

CT -9 20

This entry calculates the wind chill factor for -9°C with a 20 mps wind.

CT X 14 -8

This entry calculates the wind chill factor for -8°F with a 14 mps wind.

# CU

#### Converts units.

#### **Formats**

CU LIST

CU value unit nunit

#### **Parameters**

LIST

lists the available units and their abbreviations

value

value to be converted

unit

current unit taken from LIST

nunit

new unit taken from LIST

#### Remarks

CU converts a value from its current unit to a new unit. Enter the units in the abbreviated form shown below.

Abbreviation	Unit	Abbreviation	Unit
ACRE	acre	KPH	kilometers/hr
C	Celsius	L	liter
CM	centimeter	LB	pound
DAY	day	M	meter
DEG	degree of latitude	MB	millibar
F Total III	Fahrenheit	MI	mile
FATH	fathom	MM	millimeter
FPMIN	feet/minute	MIN	minute
FPS	feet/second	MPH	miles/hour
FT	foot	MPS	meters/second
HR	hour	NMI	nautical miles
IN	inch	OZ	ounce
K	Kelvin	RD	rod
KG	kilogram	SEC	second
KM	kilometer	YD	yard
KT	knot		

To square or cube a unit, append 2 or 3, e.g., square inch=IN2.

#### **Examples**

CU LIST

This entry lists the units that can be used.

CU 24 IN FT

This entry converts 24 inches to feet.

CU 25 MPH MPS

This entry converts 25 miles per hour to meters per second.

CU 67.3 FT3 M3

This entry converts 67.3 cubic feet to cubic meters.

CU 1 M3 FT3

This entry converts 1 cubic meter to cubic feet.

**CU 11 M FT** 

This entry converts 11 meters to feet.

## CUR

Defines the cursor size, type and color.

#### **Formats**

CUR height width type color

CUR height width type blue green red

CUR height width type number

CUR option

#### **Parameters**

height cursor height in pixels; even size is rounded up to odd size; if entered as X, the size does not change (default=31)

width cursor width in pixels; even size is rounded up to odd size (default=height)

type BOX box cursor

XHAIR crosshair cursor (default)
XBOX crosshair inside box cursor

SOLID solid box cursor (not available on VGA

workstations)

BULL external crosshair with bullseye cursor

(not available on VGA or McIDAS-X

workstations)

color color name from the color palette (default=RED)

blue blue color intensity; the range is 0 to 255 (default=0)

green green color intensity; the range is 0 to 255 (default=0)

red color intensity; the range is 0 to 255 (default=255)

number VGA color level; the range is 0 to 15 (default=2)

option ON makes the cursor visible (default)

OFF makes the cursor invisible

#### Remarks

To list VGA workstation color levels, enter: GU TABLE. To list palette colors and red, green and blue intensities for other workstations, enter: GU COLORS.

The CUR command is reflected back to the workstation for execution even when preceded by a period. CUR can be executed on the mainframe via mainframe macros.

The color default only applies when entering CUR with no positional parameters. For all other command formats, the default is the current color.

#### **Examples**

#### CUR

This entry displays a 31 by 31 red crosshair cursor.

#### **CUR 21**

This entry makes the cursor 21 by 21 pixels.

#### CUR X X 5

This entry makes the current cursor a bullseye cursor.

#### **CUR 40 30 XBOX BLUE**

This entry makes a 41 by 31 pixel, blue, crosshair inside box cursor.

#### CUR 31 21 BOX 45 15 25

This entry makes a 31 by 21 box cursor colored by the intensities for blue, green and red as 45, 15 and 25, respectively.

#### CUR X 53 4

This entry makes a solid cursor with a width of 53 pixels; the height and color do not change.

#### CUR 100 X X YELLOW

This entry makes a 101 by "X" yellow cursor, where "X" is the last dimension. The type does not change.

#### CUR OFF

This entry turns off the cursor making it invisible.

# **DATOLW**

Copies the contents of an edit member into an LW file.

**Format** 

DATOLW member file R [keyword]

**Parameters** 

member edit member name

file

LW file name

R

replaces the contents of the LW file

Keyword

CLEAN= Y cleans up bad characters in the data making them blanks; also blanks columns 73 through 80

N does not clean up the data (default)

See Also

Use command LWTODA to copy an LW file into an edit member. Use command SEE to list the LW file and SHOWME to list the edit member.

Example

DATOLW DATEMP TEMP

This entry copies the contents of edit member DATEMP into an LW file called TEMP, but does not clean up the data.

# **DMAP**

Lists the name and size of McIDAS LW files.

**Format** 

DMAP bfile efile

**Parameters** 

bfile beginning LW file to list (default=lists usage space)

efile ending LW file to list for a range of files (default=bfile)

Remarks

If no file is specified, available LW file free space is listed. To list all files beginning with a given letter, enter the letter in place of *bfile* and *efile*.

DMAP also lists LW file protection by including a (W) or (D) after the creation project number. (D) indicates the file can be deleted only by the creator project; (W) indicates the file can be written to or deleted only by the creator project.

**Examples** 

DMAP

This entry lists LW file available space.

DMAP MDX

This entry lists all MD files.

DMAP A D

This entry lists the LW files beginning with letters A, B, C and D.

DMAP A 9

This entry lists all LW files on the host.

## **HELP**

#### Lists the McIDAS command formats.

#### **Formats**

HELP command abbr [keyword]
HELP X abbr [keyword] "member

HELP 'McBASI command

HELP chapter

#### **Parameters**

command

McIDAS-MVS command name

abbr

any keyboard letter to list an abbreviated help; all help lines that begin with the command name are listed (default=entire help)

"member

source member name with prefix, e.g., ML, MR

'McBASI command

McBASI command name preceded by a single

quote

chapter

McIDAS-MVS Users Guide chapter number;

the range is 1 to 13

#### Keyword

LIB= CORE

specifies the help for the command's MCIDAS.CORE.SOURCE version

TEST

specifies the help for the command's

MCIDAS.TEST.SOURCE version specifies the help for the command's

USER

specifies the help for the command's MCIDAS.USER.SOURCE version

(default=searches CORE first followed by USER; if the command begins with a Y,

searches USER version first)

#### **Examples**

HELP

This entry lists the McIDAS-MVS Users Guide chapter names and numbers.

#### HELP 3

This entry lists all the commands in Chapter 3 and gives a brief description of each.

#### HELP LA DEV=P

This entry lists the user documentation for command LA on the line printer.

#### HELP WHO

This entry lists the help for the McBASI program WHO.

#### HELP SKU S

This entry lists the command syntax for SKU.

#### HELP YSKU

This entry lists the help for the USER library version of the SKU command.

#### HELP DF LIB=USER

This entry lists the help of the USER source member DF.

#### HELP LIB=USER "MLDF

This entry lists the help of the USER source member MLDF.

#### HELP YDF

This entry lists the help of the USER source member DF.

#### HELP X D LIB=USER "MLDF

This entry lists the abbreviated help for the USER source member DF.

## **HOWBIG**

Calculates the disk space needed for areas, MD files and grid files.

**Formats** 

HOWBIG AREA barea earea

HOWBIG AREA SIZE Isize esize zsize zres prefix [keyword]

HOWBIG GRID bgfile egfile HOWBIG MD bfile efile

HOWBIG MD SIZE schema version rows columns

**Parameters** 

AREA calculates the bytes used by the specified areas

SIZE calculates the number of tracks needed for the specified

area characteristics or the number of pages needed for the

specified MD file characteristics

GRID calculates the bytes used by the specified grid file

MD calculates the bytes used by the specified MD file

barea beginning area number

earea ending area number (default=barea)

lsize line size of the area

esize element size of the area

zsize number of bytes per element (default=1)

zres number of bands (default=1)

prefix size of the line prefix (multiple of 4); value of the total

length in LA area FORM=ALL

bgfile beginning grid file number

egfile ending grid file number (default=bgfile)

bfile beginning MD file number

efile ending MD file number (default=bfile)

schema schema name of the MD file

version version number of the MD file schema (default=current)

rows number of rows in the MD file (default=schema default)

columns number of columns in the MD file (default=schema default)

Keyword

VOL= volume number of the area; use with the SIZE option (default=0)

Remarks

Use HOWBIG to determine the number of disk tracks and bytes your areas, MD files and grid files are using.

HOWBIG also shows the protection associated with each file. If a (P) is listed after the file, it is protected and only the assigned owners are authorized to alter it.

MD files and grid files can have LW protection in addition to WQP protection. It is indicated by a (W) or (D) after the creation project number. (D) means the creation project number only may delete the file; (W) means the creation project number only may write to or delete the file.

HOWBIG MD and HOWBIG GRID use the program DMAP to produce the MD and grid space usage. The actual size of an MD file on the mainframe may be less depending on the number of stations reporting data.

HOWBIG MD SIZE is useful for calculating the destination size of an MD file when using SENMD2. This option calculates the maximum size, ±5%, of an MD file.

The parameters AREA, MD, GRID and SIZE can be shortened to single letters. See the examples below.

Examples

#### HOWBIG AREA 6512 6514

This entry calculates the number of tracks and bytes used by areas 6512 to 6514.

#### **HOWBIG AREA SIZE 1000 1250**

This entry calculates the number of tracks and bytes used by an area 1000 lines by 1250 elements.

#### HOWBIG MD SIZE ISFC

This entry calculates the number of bytes needed by an MD file of schema ISFC.

1-13

#### **HOWBIG GRID 6512 6515**

This entry calculates the number of bytes used by grid files 6512 to 6515.

#### HOWBIG A 101

This entry calculates the number of tracks and bytes used by area 101.

#### HOWBIG A S 3000 2048 2 5 244

This entry calculates the number of tracks and bytes needed for an area that is 3000 lines by 2048 elements, has 5 bands of 2-byte data and a prefix length of 244 bytes. This is an example for a 3000-line full resolution HRPT or LAC area.

#### **HOWBIG M 1002**

This entry calculates the bytes and pages used by MD file 1002.

### LISDAY

Converts a Julian date to or from a Gregorian date.

**Format** 

LISDAY date

**Parameter** 

date

year and day, YYDDD or YYMMDD (default=current)

Remarks

The range available is April 1, 1960 (the launch of TIROS) to December 31, 1999. The maximum month and day are 12 and 31.

**Examples** 

LISDAY

This entry lists the current day in two formats, YYDDD and YYMMDD.

**LISDAY 92205** 

This entry converts day 205, 1992 into the Gregorian date (920723).

LISDAY 911204

This entry converts December 4, 1991 into the Julian date.

# **LOCATE**

Lists the position of a polar orbiting satellite.

**Format** 

LOCATE ss date time

**Parameters** 

ss sensor source number (no default)

date

date of the orbit, YY/MM/DD or YYDDD (default=current)

time

time of the orbit, HH:MM:SS (default=current)

**Example** 

LOCATE 60 92121 12

This entry lists sensor source 60's position for day 92121 at 12Z.

## **LOGOFF**

Ends a McIDAS-MVS session.

Remarks

When you complete your McIDAS-MVS session,

Type: LOGOFF
Press: Enter

McIDAS-MVS echoes the message:

--- WORKSTATION IDLE ---

# LOGON

#### Begins a McIDAS-MVS session.

#### **Formats**

LOGON initials project I password LOGON initials project . password LOGON initials project string password

#### **Parameters**

your initials; 3 or 4 alphanumeric characters initials project your 4-digit project number initializes the workstation I

> initializes the workstation; the string table named initials becomes your current string table; any string in that table beginning with initials is immediately executed

name of the string table and string to execute; if logging string

on from a blank 3270-connected terminal, the string name must be preceded by a TAB or at least 4 spaces;

the string name is suppressed as it is entered

your password (changed with command PASS); if password

logging on from a McIDAS-OS2 or -X workstation, each

character of the password is suppressed with a dash (-)

#### Remarks

When you log on to McIDAS, your workstation is initialized and the following information is listed.

- a communications connection message
- your workstation identification
- message of the day from McIDAS-MVS operations
- +LOGON COMPLETE+ message
- MAIL WAITING message, when applicable

To view the LOGON message during a workstation session,

Type: SEE LOGON

Press: Enter

LOGON commands cannot be scheduled on the -MVS scheduler.

McIDAS-OS2 and -X workstations suppress your password with a series of dashes. Passwords entered from a blank screen of a 3270-connected terminal are completely suppressed.

McIDAS-MVX has four LOGON procedures. Review the examples below and select one that is suitable for you.

#### See Also

Use the PASS command to set or change a password. See the McIDAS-OS2 or McIDAS-X Users Guide for more information on logging on to -X and -OS2 workstations.

#### **Examples**

#### LOGON ABC 1234 I CBA\$ABC

This entry initializes your McIDAS-MVS session as follows:

- clears the string table
- · does not set the current MD file number
- · sets the current grid file number to your terminal number
- · displays the first image and graphics frames
- sets image frame loop bounds from one to one-half the total number of image frames on your terminal
- · connects image frame looping
- sets graphics frame loop bounds to one and the total number of graphics frames on your terminal
- disconnects graphics frame looping
- sets image and graphics frame dwell rates to 9/15 second for the first frame and 6/15 second for remaining frames
- sets the graphics line width to one pixel
- initializes graphics color levels
- displays a red 31 by 31 pixel crosshair cursor; on VGA workstations, the crosshair cursor is cyan
- unlocks cursor control
- turns off the pictel interlace switch (N key)

#### LOGON ABC 1234 X CBA\$ABC

This entry leaves McIDAS-MVS in its current state and sets the image and graphics frames to the lowest loop bound frame.

#### LOGON ABC 1234 . CBA\$ABC

This entry initializes the McIDAS-MVS workstation. The string table named ABC becomes the current string table. Any string in that table beginning with ABC is executed.

#### LOGON ABC 1234 STR CBA\$ABC

This entry initializes the McIDAS-MVS workstation. The string table named STR becomes the current string table. Any string in that table beginning with STR (e.g., STRCOLOR, STRERASE) is executed.

### LTEN

Lists the 10 closest stations to the cursor position.

**Format** 

LTEN type

**Parameters** 

type ISFC lists the 10 closest ISFC stations (default)
SVCA lists the 10 closest SVCA stations
RAOB lists the 10 closest RAOB stations
FOUS lists the 10 closest FOUS stations
IRAB lists the 10 closest IRAB stations

Remarks

The station identification, latitude and longitude are listed.

When the video image is on, the calculation is based on the satellite image. When the image is off, the calculation is based on the graphical analysis.

Position the cursor and type another period (.) after you enter LTEN. You may continue moving the cursor and typing periods to collect more station lists. Type two periods to exit the program.

**Examples** 

LTEN

This entry lists the 10 closest ISFC stations to the cursor position.

LTEN FOUS

This entry lists the 10 closest FOUS stations to the cursor position.

## **LWS**

#### Lists LW file space usage.

#### **Formats**

LWS user project

LWS user project LIST

#### **Parameters**

user

user initials (default=all)

project

project number (default=all)

LIST

lists all files found

#### Remarks

LWS is useful for maintaining LW file space usage within sitespecified limits.

The LIST parameter lists the names of all files associated with the user and project number specified.

The data used by LWS is generated by background job MBLW2. Run LWS after MBLW2.

#### **Examples**

#### LWS

This entry lists LW file space usage for all users and project numbers, in bytes.

#### **LWS AMW 7000**

This entry lists LW file space usage for user AMW, project number 7000.

#### **LWS LAR 2000**

This entry lists the total LW file space usage by user LAR under project 2000. The output is shown below.

LWS -- TOTAL2000LAR = 36.4M

LWS TAS X LIST

of ELEWORE has all W.I self to alestico off work of Electronic to

This entry lists the name and size of each LW file created by user TAS. The output is shown below.

FILENAME	PROJ	USER	SIZE	
BASICVV67	2000	TAS	16K	
GRID5728	3000	TAS	40K	
GRID5730	2000	TAS	43.6M	
GRID5738	4650	TAS	164K	
LWS TOTAL	TAS=		43.8M	

# **LWTODA**

Copies the contents of an LW file into an edit member.

Format LWTODA file member R [keywords]

Parameters file LW file name

member edit member name

R replaces the contents of member (default=does not

replace)

Keywords BEGIN= number of the first line to copy (default=1)

NCARDS= number of lines to copy (default=all)

Remarks LWTODA cannot be executed on a remote CPU; that is, it cannot be

executed via XMT.

See Also Command DATOLW copies an edit member into an LW file. Use

command SEE to view the contents of the LW file and SHOWME to

view the contents of the edit member.

**Example** LWTODA TEMP DATEMP

This entry copies the contents of an LW file called TEMP into the edit

member DATEMP.

## LWU

#### LW file utility.

#### **Formats**

LWU DEL file LWU MAKE file LWU INFO file

LWU LIST file bword eword

LWU COPY sfile dfile LWU COMP file1 file2 LWU RENAME sfile dfile LWU POKE file value word

LWU PROT file state

#### **Parameters**

DEL deletes a file

MAKE generates a file

**INFO** lists the file size in pages

LIST lists the words in the LW file

COPY copies a file

COMP compares file1 and file2

RENAME renames an LW file

POKE pokes a value into an LW file

PROT protection value

name of the file file

source file name sfile

dfile destination file name

bword beginning word number to list; the range is 0 to 8

million (default=0)

ending word number to list; the range is 0 to 8 million eword

(default=39)

file1,2LW file names to compare value value poked into the LW file word

word number of the LW file word

state 0 unprotected (default)

1 delete protected2 write protected

#### Remarks

Do not use a period (.) in an LW file name. Use only alphanumeric (A-Z, 0-9) characters. A period in an LW file name indicates a partitioned data set.

#### **Examples**

#### LWU INFO

This entry lists the total number of pages free and pages used for each disk volume allocated to LW space.

#### LWU MAKE CLOUDS

This entry creates an LW file named CLOUDS.

#### LWU INFO CLOUDS

This entry lists the size of the LW file CLOUDS.

#### LWU COPY CLOUDS NEWONE

This entry copies the LW file CLOUDS into NEWONE.

#### LWU DEL CLOUDS

This entry deletes the file CLOUDS.

#### LWU LIST LWTXT 10 20

This entry lists words 10 to 20 of the LW file LWTXT.

### MAIL

Mails messages to users, terminals or project numbers.

**Formats** 

MAIL LIST recipient

MAIL DELETE number

MAIL SENT

MAIL recipient pending [keyword] "message

**Parameters** 

LIST

chronologically lists the messages sent to your initials,

terminal or project number (default)

DELETE

deletes messages sent to you or by you

SENT

chronologically lists messages you sent

recipient

the recipient's initials, terminal number or project

number

site.initials

name of a remote McIDAS site followed by the user initials or terminal number;

site names are CCFF, EADS, JSC, SSEC

and VDUC

pending

NO message is not pending after it is listed once by

the recipient (default)

YES

message is pending every time the recipient logs on to McIDAS; use keyword DAY to set

the number of pending days

number

number preceding a message used to delete that

message

"message

message to send; the maximum length is the text screen

width; the pound sign (#) is invalid in a MAIL message

Keywords

DAY=

number of days before the message is purged; maximum

is 14 days (default=1)

LOG=

YES

does not send a message if the receiving

terminal is logged off (default)

NO

sends the message even if the receiving terminal

is logged off

SAVE= YES

saves messages for terminals logged off when

the message is sent

NO

doesn't save messages for terminals logged off

(default)

#### Remarks

If you are logged on to a video terminal, it makes a bell sound when mail is sent to you.

If the message recipient is not logged on to McIDAS at the time of the message transmission, the message is saved for a maximum of two weeks or until the recipient lists the message. If the recipient has not listed the message within this two-week period, it is purged from McIDAS. All listed messages are purged on their expiration dates, either 24 hours after the message is sent or as specified by keyword DAY.

If you have pending mail, a MAIL WAITING message is listed on your text screen following the logon message.

To send a message to a user or terminal on a networked system, use the form *site.initials*, e.g., SSEC.AMW.

The LOG= keyword only applies when sending mail to a specified terminal.

#### **Examples**

#### MAIL

This entry chronologically lists all mail sent to your initials, terminal or project number.

#### MAIL LIST 7000

This entry chronologically lists all mail sent to project 7000.

#### MAIL 11 'HELLO TERMINAL 11

This entry sends the message HELLO TERMINAL 11 to terminal 11.

### MAIL ABC Y DAY=5 "IMPORTANT MESSAGE

This entry sends the message IMPORTANT MESSAGE to user ABC. Notification of this message appears every time user ABC logs onto McIDAS during a 5-day period.

#### MAIL DELETE 6

This entry deletes message number 6.

#### MAIL SENT

This entry chronologically lists all mail that you have sent.

#### MAIL SSEC.AMW 'RESPONSE REQUESTED

This entry sends the message RESPONSE REQUESTED to SSEC, user AMW.

#### MAIL 67 LOG=NO "THIS IS A TEST

This entry sends the message THIS IS A TEST to terminal 67, even if the terminal is logged off.

### MSL

#### Lists the international master weather station list.

Formats	MSL station MSL [keywor	[keywords] rds] "matchstring
Parameters	station	3- or 4-character station ID 5- or 6-digit station ID
	"matchstring	an alphanumeric string to match; maximum of 20 characters
Keywords	CO=	2-letter country code
	LAT=	min max latitude bounds to search
	LON=	min max longitude bounds to search
	ST=	2-letter state (Post Office abbreviation) or international regional code to match
	TYPE=	RADAR lists radar stations RAOB lists RAOB stations SURF lists surface hourly stations SYNOP lists synoptic stations

#### Remarks

MSL searches the international master weather station list for station identifications, latitude, longitude, station elevation, type of station and regional areas. Station and runway elevations are given in meters.

The codes under DATA TYPES in the output from MSL are:

	_
TAF forecast	
coastal/SMARS	
short-range terminal forecast	
radar	
3-hourly synoptic	
PLATF forecast	
6-hourly synoptic	
off-hour synoptic	
	coastal/SMARS short-range terminal forecast radar 3-hourly synoptic PLATF forecast 6-hourly synoptic

Code	Definition
0	AERO
P	PIBAL
R	RAOB
T	METAR
W	service airways (surface hourly)

#### See Also

Command CCODE lists the country codes.

#### **Examples**

#### MSL TAP

This entry lists the location information for Tapachula, Mexico.

#### MSL ST=WI

This entry lists all stations in Wisconsin.

#### MSL ST=WI TYPE=RADAR

This entry lists all radar stations in Wisconsin.

#### MSL "AFB

This entry lists all Air Force bases.

#### MSL CO=US "AFB

This entry lists all Air Force bases in the United States.

#### MSL LAT=-40 -10 LON=-160 -110 TYPE=RAOB

This entry lists all RAOB stations between 40°S and 10°S latitude, and 160°E and 110°E longitude, i.e., the Australian continent.

#### MSL CO=SP "AIRPORT

This entry lists all airport stations in Spain.

## **PASS**

Defines a user logon password.

**Format** 

PASS password

**Parameter** 

password

new or changed user password required for logon authorization; can be any string from 6 to 12 alphanumeric characters; all new passwords must contain one of these special symbols:

@\$%&\*+-<>?\!

Remarks

Check with an operator at your site to determine if your system is using passwords.

When you log on to a system that utilizes password security, a message tells you that you must create a new password with the PASS command. If you don't create a new password before logging off, you won't be able to log on again without assistance from an operator.

The password is the fourth parameter for the LOGON command. All passwords are suppressed by the system; they are not echoed or repeated.

Passwords are not kept by operations. Therefore, if you forget your password, operations must reinitialize it for you.

You can change your password at any time by entering the PASS command with a new password.

Example

PASS \$CYCLONE

This entry defines \$CYCLONE as your logon password. You must enter it as the fourth parameter in LOGON when logging on to McIDAS.

## **PASSBY**

Lists the time an orbiting sensor source views a ground point.

**Format** PASSBY ss day lat lon **Parameters** SS sensor source number (no default) YYMMDDD or YYDDD default=current) daylat latitude (default=43.08°) longitude (default=89.43°) lon Remarks PASSBY also displays the angle of elevation from a horizontal plane, the angle the sensor source makes from an easterly direction, and whether the sensor source is in ascending or descending mode. test output line

Example PASSBY 62 #Y 43 89

> This entry lists the times that NOAA-12 scans normal to 43° N and 89° W for the current day.

> > SEE MYFFILE HEGIN=15

## SEE

Lists LW file text.

The ADDE command READ may be used in place of SEE.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

SEE file nchars [keywords]

**Parameters** 

file

name of an LW file or partitioned text file to list

nchars

number of characters per line (default=80)

**Keywords** 

BEGIN=

first line number to list; if negative, number of the first

word to list

EOF=

N

suppresses the \*\*\*EOF\*\*\* text output line

Y shows the \*\*\*EOF\*\*\* text output line (default)

LAST=

number of lines from the end of the file to list

NLINES=

number of lines to list (default=500)

ALL lists all lines

STEP=

number of lines skipped between the lines listed;

if negative, it steps backwards

**Examples** 

#### SEE LOGON

This entry lists the message seen when logging on to McIDAS.

#### SEE MYFILE BEGIN=25

This entry lists the text in LW file MYFILE beginning with line 25.

#### SEE MYFILE NLINES=25 STEP=-1 DEV=P

This entry lists the text in MYFILE beginning with line 1, stepping backwards, listing 25 lines, and sends the output to the line printer.

#### SEE SCHEMA BEGIN=99 NLINES=15 STEP=-1

This entry lists file SCHEMA starting at line 99 and stepping backwards by 1 line for 15 lines.

#### SEE JCL

This entry lists the partitioned text file directory. Use SEE JCL.file to list individual files.

## **SENLW**

Sends a mainframe LW file to a remote host or workstation.

**Format** 

SENLW sfile dfile [keywords]

**Parameters** 

sfile source LW file name

dfile

destination LW file name on the remote host or workstation; 12 characters maximum including drive and path (default=sfile)

Keywords

BEGIN= begins writing word 0 of *sfile* at the specified word in *dfile*; do not use this option with the RANGE or PAGE options

FLIP= NO does not flip bytes (default)
YES flips bytes of 32-bit words

PAGE = NO sends missing pages (default)

YES suppresses the sending of missing pages from the LW file; use this option for host-to-host communication only

RANGE= beg end dest

beginning and ending pages to send, and the destination page of the beginning page in *dfile*; you must use LW file page numbers, 1024 words per page (default for *dest*=0)

TRANS= A translates from EBCDIC to ASCII; the source LW file must contain EBCDIC characters only

F translates from mainframe format floating point values to McIDAS-OS2 format floating point values

T sends text to the workstation (implies A option)

Remarks

To send an LW file to a drive other than C on a McIDAS-OS2 workstation, precede the destination LW file name with the destination drive letter and a colon (e.g., A:dfile). Necessary drive extensions should follow the destination file name, separated by a period (e.g., dfile.ET). When transferring enhancements to a McIDAS-OS2 workstation, always add the file extension .ET to the destination file name. The total number of characters for dfile is twelve, including drive names, file extensions, colons and periods.

#### **Examples**

#### SENLW LWTXT

This entry sends the LW file LWTXT to a workstation LW file named LWTXT in the current McIDAS directory.

#### SENLW MSTATS A:PCSTAT

This entry sends source LW file MSTATS to destination LW file PCSTAT and copies it to the diskette in drive A.

#### WAVI.SENI.W MDXX4570 MDX13696 PAGE=Y

This entry transfers MD file 4570, on the WAV1 system, to your host MD file 13696. PAGE=Y deletes blank pages and should be used for host-to-host file transfers.

## **SHOWME**

Lists text from source code files.

Format SHOWME file page ALL [keywords]

Parameters file name of the McIDAS source code member

page page number (default=first 20 lines of file)

ALL lists the entire file

Keywords NUM= N suppresses line numbers when using the ALL option

PREF= any valid two-letter file prefix

Remarks If you enter a file name without a two-letter prefix, SHOWME will

locate the first occurrence of the file name in DATABLE. The user

library is searched before the core library.

See Also Use command > or < to page forward or backward one page.

Examples SHOWME MYFILE

This entry lists the first 20 lines of MYFILE.

SHOWME PLOT ALL PREF=DN DEV=P

This entry lists the entire file PLOT on the printer.

## SS

#### Lists McIDAS-MVS command status.

#### Remarks

The SS command lists all commands currently running on McIDAS-MVS.

A sample SS output is shown below.

SSEC	STATUS		
WRK#	Terminal ID	CPU Prog	ram Command(s)
WRK00	114 OS2SRV	0.1 SS	?
WRK03	3 639	0.1 WTOR	WTOR "CHANGE TEMP/HUMIDITY CHART
WRK05	9 248D	3.9 IGTV	#HGTTOFOR
WRK06	62 QC-B	5.7 TIRC	AL MULTIR 828
WRK07	9 248D	0.5 MAP	#HGTTHRTSX

Each column in the output is defined below.

Column	Definition
WRK#	the letters WRK followed by the worker number; most systems have 15 workers where four may
	be used by a single workstation at one time
Terminal ID	workstation number and its location
CPU	executing command's total CPU cycles, in
	seconds
Program	program name executing
Command(s)	command entered

To stop your program, type a slash (/) followed by a space and the worker number. You cannot abort a program running on another workstation.

#### See Also

The question mark (?) command is a shorter form of command SS.

#### Example

/ 5

This entry terminates the program running on worker 5 and restarts worker 5.

# SST

Lists McIDAS-MVS command status and terminal usage.

#### Remarks

The output format of SST is a combination of the SS and ST commands, as shown below.

SSE	EC	S	тат	US	R E P	ORT	17	Dec 92	9235	2 19:	24:21	В
WRK	(# 	Term	inal :	ID	CPU	Program	Cor	nmand(s)				
WRK	(03	114	OS2SF	٧V	0.1	SS	SS	r				
WRK	(04	52	248C	- WW	2.9	DF	DF	11126 2	3 IU	16500	-275	BAND, 6
0	OPCC	M	6999	OPER	34.6		1	QC-A	6999	OPER	0.4	V570
4	243		3332	THA	0.1	DOWN	6	JSC	7000	HOST	0.2	
12	248A	4	3305	AJS	0.5	V570	14	UNIREC	2360	RCD	4.9	V550
17	235-	TA	3340	THA	0.0	DOWN	18	CCFF	7000	HOST	0.0	
22	LOOF	PER	7000	LOOP	27.3	V560	25	601	6999	DEEW	3.6	V570

#### See Also

For more information, see commands SS and ST.

# ST

Lists terminals and users logged on to McIDAS-MVS.

#### **Remarks**

The output format of ST is shown below.

0	OPCOM	6999	OPER	34.6		1	QC-A	6999	OPER	0.4 V570
4	243	3332	THA	0.1	DOWN	6	JSC	7000	HOST	0.2
12	248A	3305	AJS	0.5	V570	14	UNIREC	2360	RCD	4.9 V550
17	235-TA	3340	THA	0.0	DOWN	18	CCFF	7000	HOST	0.0
22	LOOPER	7000	LOOP	27.3	V560	25	601	6999	DEEW	3.6 V570
27	MSFC	3378	HOST	10.9		32	TOAST	2233	STW	0.0 V163

Each column in the output is defined below.

Column	Definition
100	terminal number
2	terminal location or name
3	user project number
4	user initials
5	total minutes of CPU cycles of your current terminal session, in seconds
6	McIDAS workstation version number or terminal communication status

#### See Also

Use command SS or SST to list the program being executed.

## **SUNLIT**

Lists the sunrise and sunset for a date and location.

**Formats** 

SUNLIT TODAY lat lon

SUNLIT date lat lon

**Parameters** 

TODAY uses today's date for sunrise and sunset; after 18 CST

today, it lists tomorrow's times; times are given in UTC

date

date of sunrise and sunset, YYDDD

lat

latitude for sunrise and sunset (default=43:04:48)

lon

longitude of sunrise and sunset (default=89:25:48)

**Examples** 

SUNLIT

This entry lists today's sunrise, sunset, latitude and longitude for

Madison, WI.

SUNLIT TODAY 36 90

This entry lists sunrise and sunset for today at 36°N and 90°W.

SUNLIT 92233 38:42:05 96:22

This entry lists sunrise and sunset for day 92233 at 38°42'05" N and

96°22'W.

## U

Lists the logged on project number.

#### Remarks

To list the logged on project numbers,

Type: U Press: Enter

A sample screen output is shown below.

						1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1		
92338	3	DEC	92	195548	ABC	7000	T#=60	

#### Each field is defined below.

Output	Definition	
92338	year, Julian day (YYDDD)	
3 DEC 92	day, month, year	
195548	time (GMT), HHMMSS	
ABC	user's initials	
7000	user's project number	
T#=60	terminal number	

# **VER**

Displays the McIDAS-MVS software version number.

#### Remarks

VER displays the current McIDAS-MVS software version number and the date of the most recent upgrade in the format YYDDD.

Below is a sample output.

\*\*MCIDAS SOFTWARE VERSION 92289

\*\*15 October 1992

# **WTOR**

Sends a text message to the system operator.

**Format** 

WTOR "text

**Parameter** 

"text

the text message; must be less than 46 characters

Remarks

The operator must reply to the text message. Use this command with

discretion.

Example

WTOR "HELLO, HAS TAPE SS1441 BEEN READ IN?

This entry displays the message HELLO, HAS TAPE SS1441 BEEN

READ IN? on the operator's text screen.

# & (Ampersand)

Recalls a previously entered command.

#### Remarks

The ampersand command displays a previously entered command on the text screen. You can then press the carriage return key to execute the command, or change characters and then execute it. >

Lists the next 20 source code lines.

Remarks

When listing source code with command SHOWME, press > to view the next 20 lines. Press < to page backwards 20 lines.

See Also

Use command SHOWME to list text from source code files.

<

Lists the previous 20 source code lines.

Remark

When listing source code with command SHOWME, press < to view the previous 20 lines. Press > to page forward 20 lines.

See Also

Use command SHOWME to list text from source code files.

# ? (Question Mark)

Lists McIDAS-MVS command status.

#### Remarks

The question mark (?) command lists all commands currently running on McIDAS-MVS.

A sample output is shown below.

SSEC WRK#	S T A T U S Terminal ID	R E P O R T CPU Program	17 Dec 92 92352 15:04:09 Command(s)
WRK00	114 OS2SRV	0.1 SS	?
WRK03	3 639	0.1 WTOR	WTOR "CHANGE TEMP/HUMIDITY CHART
WRK05	9 248D	3.9 IGTV	#HGTTOFOR
WRK06	62 QC-B	5.7 TIRCAL	MULTIR 828
WRK07	9 248D	0.5 MAP	#HGTTHRTSX

Each column in the output is defined below.

Column	Definition	
WRK#	the letters WRK followed by the worker number; most systems have 15 workers where four may	
	be used by a single workstation at one time	
Terminal ID	workstation number and its location	
CPU	executing command's total CPU cycles, in	
	seconds	
Program	program name executing	
Command(s)	command entered	

To stop your program, type a slash (/) followed by a space and the worker number. You cannot abort a program running on another workstation.

#### See Also

Use the slash (/) command to stop a program. Command SS also lists McIDAS-MVS command status.

# / (Slash)

#### Terminates a command.

#### Remarks

To terminate a command, type a slash followed by a space and the worker number. If you don't know the worker number, use the question mark (?) command to list it.

To determine the worker number,

Type: ?

Then,

Type: / worker number

Press: Enter

#### **Example**

/7

This entry terminates the program running on worker 7 and restarts worker 7.

# **Chapter 2. Graphics Applications**

CLOCK	Displays a clock on the graphics
CW	Fills or erases the graphics within the cursor 2-2
DYOG	Displays your own graph
EG	Erases a graphics frame 2-5
EVG	Erases virtual graphics
GD	Defines graphics display parameters 2-7
LG	Lists the graphics frame directory 2-8
LVG	Lists virtual graphics directory entries 2-9
MAPORB	Displays polar orbital tracks on a Mercator map 2-10
SENVG	Sends a virtual graphic from the mainframe to a workstation 2-12
SVG	Displays virtual graphics 2-13
SVS	Displays and manipulates virtual graphics 2-14
TG	Displays text from an LW file on a graphics frame 2-16
TGW	Displays text on a graphics frame with word wrap 2-17
USAORB	Displays polar orbiting satellite tracks over North America 2-18
ZA	Displays annotations on the graphics frame at the cursor position 2-19

Despite the destroy of the state of the stat

Issued 4/93

## **CLOCK**

time

ccolor

tint

Displays a clock on the graphics.

**Format** 

CLOCK time wcolor ccolor tint tlength

**Parameters** 

time for the wedge to cover, in minutes; the range is 0 to 60

(default=0)

wcolor graphics color level of the wedge (default=1)

graphics color level of the clock (default=3)

interval between tic marks, in minutes (default=no marks)

tlength length of the tic mark, in pixels (default=3)

Remarks

The clock is drawn at the current cursor location. Its diameter is the smallest dimension of the cursor or 30 pixels, whichever is larger.

**Examples** 

CLOCK 10

This entry displays a clock centered at the cursor position. The wedge is graphics color level 1; the clock is level 3. The wedge is from 0 to 10.

CLOCK 10 4 X 5

This entry displays a clock in graphics color level 3 at the current cursor position. The wedge, in graphics color level 4, is from 0 to 10. Tic marks are 3 pixels long, every 5 minutes.

### CW

Fills or erases the graphics within the cursor.

**Format** 

CW level frame height width

**Parameters** 

graphics color level; the range is zero to the maximum available for the display type (default=0 to erase

graphics within the cursor)

frame

level

graphics frame number (default=current)

height

height of the area to erase, in pixels (default=cursor height)

width

width of the area to erase, in pixels (default=cursor width)

See Also

Use command EG to erase the entire graphics frame.

**Examples** 

**CW** 

This entry erases the graphics within the cursor.

CW 1 3

This entry fills the cursor with graphics color level 1 on graphics frame 3.

CW 6 2 50 30

This entry fills a box 50 by 30 centered at the cursor with graphics color level 6 on graphics frame 2.

# DYOG

# Displays your own graph.

Format	DYOG xl	DYOG xlen xtic xbeg xinc xcolor ylen ytic ybeg yinc ycolor [keywords]		
Parameters	xlen	length of the x-axis in pixels, maximum length is 450 (default=450)		
	xtic	number of evenly spaced tic marks on the x-axis (default=10)		
	xbeg	beginning value of the x-axis tic marks		
	xinc	increment of the xtic labels		
	xcolor	graphics color level of the x-axis tics and labels (default=2)		
	ylen	length of the y-axis in pixels, maximum length is 380 (default=380)		
	ytic	number of evenly spaced tic marks on the y-axis (default=10)		
	ybeg	beginning value of the y-axis tic marks		
	yinc	increment of the ytic labels		
	ycolor	graphics color level of the y-axis tics and labels (default=3)		
Keywords	XLAB=	x-axis label, maximum of 48 characters		
	YLAB=	y-axis label, maximum of 48 characters		
Remarks	DYOG w	DYOG will display the x and y axes with labels and tic marks.		
See Also	Use command ZA to insert data points.			

#### **Examples**

#### DYOG X X O 2 X X X O 2 X

This entry displays an x-axis 450 pixels long with 10 tic marks beginning at 0, incrementing by 2, in graphics color level 2. The y-axis is 380 pixels long with 10 tic marks beginning at 0, incrementing by 2, in graphics color level 3.

# DYOG 400 12 0 2 4 350 20 -10 10 6 XLAB=TIME YLAB=TEMP

This entry displays an x-axis 400 pixels long with 12 tics beginning at 0, incrementing by 2, in graphics color level 4 and labels it TIME. The y-axis is 350 pixels long with 20 tics beginning at -10, incrementing by 10, in graphics color level 6 and labels it TEMP.

### **EG**

Erases a graphics frame.

**Formats** 

EG ALL

EG bframe eframe

**Parameters** 

ALL

erases all graphics frames

bframe

beginning graphics frame number to erase

(default=current)

eframe

ending graphics frame number to erase (default=bframe)

See Also

Use command CW to erase small portions of the graphics frame.

**Examples** 

EG

This entry erases the current graphics frame.

EG 6 12

This entry erases graphics frames 6 through 12.

EG ALL

This entry erases all graphics frames on your terminal.

## **EVG**

Erases virtual graphics.

**Format** 

EVG buirt evirt

**Parameters** 

bvirt

beginning virtual graphics number to erase; the range is 1

to 1024

evirt

ending virtual graphics number to erase (default=bvirt)

Remarks

EVG will not erase the graphics displayed on the frame, only those stored in the virtual graphics. You cannot erase individual graphics

scenes.

**Examples** 

**EVG 22** 

This entry erases virtual graphics 22.

EVG 10 30

This entry erases virtual graphics 10 through 30.

### GD

### Defines graphics display parameters.

#### **Format**

GD width display flip dlength gcolor glength

#### **Parameters**

width graphics line width, in pixels; the range is 1 to 64 (default=1)

display ON draws graphics

OFF does not draw graphics (default=current mode)

flip ON flips the graphics display left to right; valid for tower displays only

OFF does not flip the graphics display (default)

dlength length of the dashes in a line; the range is 0 to 64

(default=5)

gcolor graphics color levels of the gaps in a dashed line

(default=255, transparent)

glength length of the gaps in a dashed line; the range is 0 to 64

(default=5)

#### Remarks

Use the *display* OFF option when creating virtual graphics on a nonvideo workstation. Use the *flip* option with tower workstations only.

#### **Examples**

#### GD

This entry lists the current graphics status.

#### GD 4

This entry defines the graphics width as 4 pixels.

#### GD X OFF

This entry turns off the graphics display.

#### GD 1 X X 20 0

This entry defines the dash length as 20 pixels on the current display.

#### GD 1 X X 10 1 10

This entry defines the dash and gap lengths as 10 pixels and the gap color as graphics color level 1 on the current workstation.

### LG

Lists the graphics frame directory.

**Format** 

LG scene [keywords]

**Parameter** 

scene

graphics scene number (default=all scenes on the frame)

Keywords

FORM= STN standard list (default)

ALL expanded list; you must specify the scene

FRAME= graphics frame number (default=current)

TERM= terminal number (default=current)

Remarks

Scene numbers increase from 1 to n, where n is the total number of graphics scenes drawn on a frame since the last erase (command EG).

To select keyword FORM=ALL, you must specify scene.

A scene is one element of a virtual graphics display, for example a map outline or temperature plot.

**Examples** 

LG

This entry lists the graphics frame directory for all scenes on the current graphics frame.

LG 2 FRAME=6

This entry lists the graphics frame directory for scene number 2, graphics frame 6.

### LVG

Lists virtual graphics directory entries.

Format LVG buirt evirt scene [keywords]

**Parameters** 

beginning virtual graphics number to list; the range is buirt

1 to 1024

evirt

ending virtual graphics number to list (default=bvirt)

scene

graphics scene number stored in the virtual graphics

(default=all scenes)

**Keywords** 

FORM= expanded list; you must specify a scene number

(default=standard 1-line list)

terminal number with virtual graphics (default=current)

**Examples** 

LVG 250

This entry lists the information for virtual graphic 250.

LVG 100 200 5

This entry lists all virtual graphics from 100 to 200, scene 5 only.

LVG 10 30 TERM=67

This entry lists the virtual graphics between 10 and 30 stored on

terminal 67.

## **MAPORB**

Displays polar orbital tracks on a Mercator map.

**Format** 

MAPORB ss date ulat ulon llat llon LALO clalo [keywords]

**Parameters** 

sensor source number (POES satellites)

date date, YYDDD (default=current)

ulat upper-left latitude (no default)

ulon upper-left longitude (no default)

llat lower-right latitude (no default)

llon lower-right longitude (no default)

LALO displays latitude/longitude lines with a map

(default=does not draw lines)

clalo graphics color level for the latitude/longitude lines

(default=3)

**Keywords** 

COLOR= graphics color level of the map (default=1)

GRA= graphics frame number to draw on (default=current)

INT= lat lon intervals for latitude and longitude lines (default is computed)

LINEC= orbit line color level (default=2)

Remarks

When specifying latitude and longitude, positive numbers are degrees North and degrees West respectively, while negative numbers are degrees South and degrees East respectively.

See Also

See Appendix B for a list of satellite sensor numbers.

#### **Examples**

MAPORB 60 92100 42 115 23 81 LALO 3 COLOR=5 This entry draws orbital tracks for sensor source 60, day 92100, from 42° North, 115° West to 23° North, 81° West in graphics color level 5 with latitude/longitude lines drawn in graphics color level 3.

MAPORB 61 91300 80 100 -10 -10 LALO 7 LINEC=5 GRA=5 This entry draws orbital tracks on graphics frame 5 for sensor source 61, day 91300, from 80° North, 100° West to 10° South, 10° East with the latitude/longitude lines drawn in graphics color level 7 and the orbital tracks in graphics color level 5.

Issued 4/93 2-11

### **SENVG**

Sends a virtual graphic from the mainframe to a workstation.

Format SENVG svirt dvirt frame [keywords]

Parameters source virtual graphic number; the range is 1 to 1024

(no default)

dvirt destination virtual graphic number (default=svirt)

frame graphics frame number to display (default=does not display

the virtual graphic)

Keywords ALSO= t1...tn list of additional McIDAS-OS2 workstations to

receive and display the virtual graphic

COORD= ON sends Z dimension coordinates

OFF does not send Z dimension coordinates (default)

TERM= McIDAS-MVS terminal number of the source virtual

graphic (default=current)

Remarks 1024 virtual graphics numbers are reserved for each McIDAS-MVS

workstation connection.

See Also To list a saved virtual graphic, use command LVG.

Examples SENVG 5

This entry copies virtual graphic 5 from the mainframe to the current

workstation, but does not display it.

SENVG 21 22 3 TERM=11

This entry copies virtual graphic 21 from terminal 11 as virtual graphic 22 onto the current workstation and displays it on graphics

frame 3.

SENVG 2 X 1 ALSO=11 13

This entry copies virtual graphic 2 saved on the current terminal as virtual graphic 2 and displays it on graphics frame 1 on the current

workstation and also workstation numbers 11 and 13.

### **SVG**

### Displays virtual graphics.

**Format** 

SVG virt frame [keywords]

**Parameters** 

virt virtual graphics number; the range is 1 to 1024

frame

graphics frame number to display the virtual graphic

(default=current)

Keywords

TERM=

McIDAS-MVS terminal number where the virtual

graphic is stored (default=current)

TOTERM=

destination terminal number usually assigned by the computer operators; use TOTERM when you plan to write virtual graphics to tape and need protection from accidental deletion by other users; numbers are greater than 1000, usually 1000 + terminal number; call your computer operators for more information

SCALE=

NO

does not scale the graphic for a VGA display

YES scales the graphic for a VGA display

Remarks

Virtual graphics are deleted at SSEC with the monthly purge. To store virtual graphics, append keyword VIRT to any graphics

command.

On a VGA workstation, use the SCALE=NO option to accurately display graphics that are navigated (MAP, SP, SC, etc.). Use SCALE=YES on VGA workstations to display graphics that are not navigated (MG, STUVE, ZA, etc.).

See Also

Use command DMAP VIRT to find the available TOTERM numbers.

**Examples** 

SVG 250

This entry displays virtual graphic 250 on the current graphics frame.

SVG 800 5 TERM=23

This entry displays virtual graphic 800 stored on terminal 23 on graphics frame 5.

### **SVS**

Displays and manipulates virtual graphics.

**Format** 

SVS virt frame [keywords]

**Parameters** 

virt

virtual graphics number; the range is 1 to 1024

frame

graphics frame number (default=current)

**Keywords** 

ANGLE=

angle to rotate the scene, in degrees

BLOW=

line ele

multiplies the line and element coordinates

differentially before rotating the scene

(default=1,line)

BOX=

0 use keyword CURFLG to select the scene's output

saves all or part of the scene within the cursor as a virtual graphic; output is centered on the graphics

frame

CURFLG=

o if BOX=0 and SHR=-1, the scene is replotted and adjusted to fit inside the cursor; if BOX=0 and SHR=some real number, the scene is shrunk

according to SHR=

1 if BOX=0 the scene remains unaltered when

replotted (default)

POSX=

TV center line of the scene

POSY=

TV center element of the scene

SCENE=

scene numbers to display (default=all)

SHRINK=

draws the scene inside the cursor; its size is changed according to the real number entered (i.e., if SHR=.5 the scene is plotted ½ its original size); use SHR with

keywords BOX=0 and CURFLG=0

-1 110

-1 fits the scene to the cursor size

SIZEX=

TV line dimension of the scene

SIZEY=

TV element dimension of the scene

TERM=

terminal number where the virtual graphic is stored

(default=current)

Remarks

Use SVS to display virtual graphics. Scenes can be rotated, blown up,

blown down or repositioned.

**Examples** 

SVS 100

This entry displays virtual graphic 100 on the current graphics frame.

SVS 50 4 SCENE=3 4 6

This entry displays virtual graphic 50 scenes 3, 4 and 6 on graphics

frame 4.

SVS 50 SCENE=1 BOX=0 CURFLG=0 SHR=-1

This entry displays virtual graphic 50 scene 1 on the current graphics frame inside the cursor.

### TG

Displays text from an LW file on a graphics frame.

**Format** 

TG file nlines raster pictel color height bline [keywords]

**Parameters** 

file name of the LW file containing the text

nlines number of text lines to display on the graphics; maximum

number of lines is based on the height of the characters

(default=maximum)

raster TV raster to begin text on (default=15)

pictel TV pictel to begin text on (default=15)

color graphics color level (default=1)

height height of the letters in pixels; minimum for legibility

is 5 (default=8)

bline beginning line of text to print (default=1)

Keywords

GRA= graphics frame number (default=current)

WID= width of the graphics, in pixels (default=1)

Remarks

The LW file must be in 80-character card image format.

See Also

Use command DATOLW to copy an edit member into an LW file and command LWTODA to copy an LW file into an edit member. Use command SEE to view the contents of the LW file and command SHOWME to view the contents of the edit member.

**Examples** 

TG SFCPLT

This entry displays the first 32 lines of text from the LW file SFCPLT. The characters are magenta, 8 pixels high.

TG WXDAT 10 X X X 6 4

This entry displays 10 lines of text from the file WXDAT starting at line 4. The text starts at TV coordinates (15,15). The characters are 6 pixels high and drawn in magenta.

### **TGW**

Displays text on a graphics frame with word wrap.

**Format** 

TGW file height raster pictel color bline [keyword]

**Parameters** 

file name of the LW file containing the text

height height of the letters, in pixels; the minimum for legibility

is 5 (default=8)

raster TV raster to begin writing text on (default=15)

pictel TV pictel to begin writing text on (default=15)

color graphics color level (default=1)

bline beginning line of text to plot (default=1)

Keyword

GRA= graphics frame number (default=current)

Remarks

A % in the first column of the LW file starts a new line instead of filling the current line.

See Also

Use command DATOLW to copy an edit member into an LW file; use LWTODA to copy an LW file into an edit member. Use command SEE to view the contents of the LW file; use command SHOWME to view the contents of the edit member.

**Examples** 

TGW LWTXT

This entry displays text from the LW file LWTXT. The characters are 8 pixels high in graphics color level 1.

TGW FPWI 10 200 X 3 4

This entry displays text from the LW file FPWI, starting at line 4. The text wraps around so each line is filled. The characters are 10 pixels high, in graphics color level 3, starting on TV raster 200, TV pictel 15.

### **USAORB**

Displays polar orbiting satellite tracks over North America.

**Format** 

USAORB ss yyddd map [keyword]

**Parameters** 

sensor source number (POES satellites); if the sensor source number is negative, antenna circles are drawn

yyddd

date of the tracks (default=current)

map

doesn't display a map 0

displays a map without state boundaries (default) 1

displays a map with state boundaries

**Keyword** 

GRA=

graphics frame number (default=current)

See Also

See Appendix B for a list of sensor source numbers.

**Examples** 

**USAORB 60 92300 2** 

This entry displays orbital paths for sensor source 60 on day 92300

and includes state boundaries on the map.

USAORB 61 GRA=10

This entry displays today's orbital paths over North America for sensor source 61 onto graphics frame 10.

## ZA

Displays annotations on the current graphics frame at the cursor position.

Format	ZA color	height justify [keyu	ord] "text		
Parameters	color	graphics color level (default=1)			
	height	letter height, in pix	cels (default	t=10)	
	justify	<ul><li>R right justificati</li><li>C centered</li><li>L left justification</li><li>V vertical</li></ul>		ZATE This on th	
	"text			ame; you can use up ouble quote is mand	
	"\$text	dollar sign (\$) plus	any of the f	vs on the graphics; e following alphanume nding weather symb	eric
		T= thunderstorm	K	H= haze	$\infty$
		W=rain shower	Ŷ	Z= freezing rain	00
		X= snow shower	*	0= 1	
		R= rain	0	1= 💭	
		S= snow	*	2= 🖒	
		F= fog	=	3= ∑	
		C= clear	$\bigcirc$	4= 🞝	
		Q= partly cloudy	$\bigcap$	5=	
		B= mostly cloudy	$\widetilde{\mathbb{D}}$	6= 🖒	
		O= overcast	$\Theta$	7= 💢	
		D= drizzle	•	<b>\$= \$</b>	

Keyword

GRA= graphics frame number (default=current)

Remarks

To write lowercase letters, unlock the capital letters with the alpha lock key located on the left side of the keyboard. Remember to switch back to uppercase again to type in your next commands. McIDAS-MVS does not accept lowercase input for any other command.

See Also

Use command CW to erase graphics inside the cursor.

**Examples** 

#### ZA 3 15 "MCIDAS IBM

This entry writes MCIDAS IBM in graphics color level 3, 15 pixels high on the current graphics frame.

#### ZA 2 20 "streamlines

This entry writes streamlines in graphics color level 2, 20 pixels high on the current graphics frame.

#### ZA 4 25 GRA=6 "Upper air data

This entry writes upper air data in graphics color level 4, 25 pixels high on graphics frame 6.

#### ZA 3 20 "\$T

This entry plots a thunderstorm symbol on the current graphics frame.

#### ZA 3 10 C "TEST

This entry writes the word TEST in graphics color level 3, 10 pixels high on the current graphics frame, centering it at the cursor location.

#### ZA "Wisconsin

This entry writes the word Wisconsin 10 pixels high on the current graphics frame in graphics color level 1.

# **Chapter 3. String Tables**

DUO	Repeats a command
PROMPT	Prompts the next linefeed using a string table
SENST	Sends a string table from the mainframe to a workstation 3-4
TC	Stores an arithmetic calculation in a string table 3-5
TD	Deletes string(s) from the current string table
TE	Enters or edits a string in a string table
TL	Lists the strings in a string table 3-10
TU	String table utility

### DUO

### Repeats a command.

#### **Format**

DUO string start TO end BY inc start BY inc ... start BY inc [keyword]

#### **Parameters**

string string name or prefix from the string table containing the command(s) to execute; 1 to 12 characters; all strings matching the prefix are executed

start starting parameter value

end ending parameter value

inc values to increment the parameter by the execution of DUO

TO mandatory parameter indicating the range between start

and end

BY mandatory parameter indicating the increment between

start and end

#### Keyword

MAXN= maximum number of commands to execute (default=200)

#### Remarks

Before executing DUO, set up your string table using a !number for each parameter to be incremented during execution; number must begin at 1 and increment by 1.

DUO only executes mainframe commands; use command REPEAT to execute workstation commands.

#### **Examples**

#### DUO PSEUDO 1 TO 1

This entry executes each command shown in the string table entries below one time. The commands are executed but no values are incremented.

PSEUDOA:=EL 10 20 0 0 35 45 20 50

PSEUDOB:=EL 25 45 50 50

PSEUDOC:=EL 46 63 0 0 0 30 63

OUR is nothing a suit y

#### DUO ERASE 1 TO 10 BY 2

This entry executes the string ERASE on every second frame from frames 1 to 10. The entry in the string table is:

ERASE:=EG!1

#### DUO TV 101 TO 103 BY 1 1 BY 1 105 BY 1 11 BY 1

This entry executes strings TVLOAD and TVMES three times each; the execution stops when area 103 is displayed. The string table entries are shown below.

A:=EC 36 90
B:=-4
TVLOAD:=DF !1 !2 #A #B;DF !3 !4 #A
TVMES:=MAIL 21 "TV LOADS STARTED

The following DF commands are executed.

DF 101 1 EC 36 90 -4
DF 102 2 EC 36 90 -4
DF 103 3 EC 36 90 -4
DF 105 11 EC 36 90
DF 106 12 EC 36 90
DF 107 13 EC 36 90
MAIL 21 "TV LOADS STARTED

### **PROMPT**

Prompts the next linefeed using a string table.

**Formats** 

TE string 'PROMPT

TE string "PROMPT "command

**Parameters** 

"PROMPT executes a linefeed

string

string name

"command

part or all of an executable command

Remarks

When PROMPT is part of an executable command, the text screen responds with a linefeed. If a command follows PROMPT, the cursor waits at the end of the line for you to type a carriage return. You can edit this line before typing the carriage return.

3270 terminals must have one keystroke made before typing a carriage return or all blanks are entered in spite of the command line listed.

Example

TE LIST "PROMPT "LA 101

Entering command ##LIST echoes command LA 101 and the cursor pauses after the 101. You can modify the LA command before typing the carriage return.

### **SENST**

Sends a string table from the mainframe to a workstation.

**Format** 

SENST PC table initials

**Parameters** 

PC

string table destination; you must enter PC (no default)

table

string table name on the mainframe

initials

author's initials (default=current initials)

Remarks

The table name is assigned the initials of the user logged on to the workstation unless otherwise specified.

See Also

Enter command TU SAVE in the local mode to save the transferred string table.

Enter command SENST in the local mode to send string tables to the mainframe.

**Examples** 

SENST PC MYTABLE

This entry sends the string table named MYTABLE from the mainframe to the workstation, assigning the user's initials to the table.

SENST PC TVLOAD DLX

This entry sends the mainframe table TVLOAD to the workstation and assigns the initials DLX to it.

### TC

Stores an arithmetic calculation in a string table.

#### **Format**

TC number operator number operator . . . [keyword]

#### **Parameters**

number a decimal integer, hex value prefixed by Z, or any sequence of 4 characters whose left adjusted EBCDIC

value is an integer

operator

+ arithmetic addition operator

- arithmetic subtraction operator

\* arithmetic multiplication operator

/ arithmetic division operator

\$ arithmetic mod function operator

arithmetic exponentiation operator

#### Keyword

ANS=

stores the result of the calculation in the string table

entry (default=X)

#### Remarks

The new string is listed and stored in your local string table under the name specified with ANS=. Parentheses are permitted to modify the calculation sequence.

Numbers, operators and parentheses are individual parameters and must be surrounded with blanks.

#### **Examples**

#### TC #Y + 1 ANS=TOMORROW

This entry, if run on 92218, assigns the string TOMORROW the value 92219, which is used to create O&A data for 1992, day 219.

TC 8 \* Z4F - 2

This entry stores the answer 630 in string X.

TC 8 \* ( Z4F - 2 )

This entry stores the answer 616 in string X.

### TD

Deletes string(s) from the current string table.

#### **Formats**

TD name

TD PREFIX prefix

TD ALL

TD ALL GLOB

#### **Parameters**

name

a single string name to delete

prefix

deletes all strings that begin with this prefix

PREFIX searches for the string prefix

ALL

deletes all strings except for global strings

**GLOB** 

deletes all strings including global strings

#### Remarks

A string name whose first character is a question mark (?) is defined as global. Global strings remain in the table unless you delete them by entering: TD ALL GLOB.

#### See Also

Use command TL or TE to list or edit strings. Use command TU to save the current string table.

#### **Examples**

#### TD 9

This entry deletes the string named 9.

#### TD PREFIX CH

This entry deletes all strings that begin with CH.

#### TD ALL

This entry deletes all strings except those preceded by a question mark (?).

#### TD ALL GLOB

This entry deletes all strings including those preceded with a question mark.

### TΕ

Enters or edits a string in a string table.

#### **Formats**

TE string "text

TE string val1 val2...valn

#### **Parameters**

string

an alphanumeric string name, 1 to 12 letters; only the

first character may be numeric

"text

the value, command or text defining string

val1...n

values to edit in a string's parameter position

a period will not change a parameter; at least one period must appear in each edit command

deletes the parameter from the string

valn

inserts additional parameters into the string

Note:

To enter keywords (keyword=value), each keyword is broken down into two parameters,

the keyword= and the value.

#### Remarks

To execute a command entered under a string name on a 3270 terminal or from a macro, type: #string. If #string1 is included within another string, such as #string2, the value of #string1 is used when #string2 is executed. Enter an extra pound sign if the command is entered from a workstation. The command line interpreter drops one pound sign before execution.

You cannot use the letter X as a string name since McIDAS interprets X as a place holder for default values. Likewise, if you have a series of strings beginning with X (e.g., XMAP, XSOUND, XSEL) you cannot delete them with TD PREFIX X nor execute them with DUO X 1 TO 1.

A string name whose first character is a question mark (?) is called a global string. To delete a global string, use: TD ALL GLOB.

#### See Also

Use command TL to list strings and TD to delete strings. TU is the string table utility.

#### **Examples**

#### TE BLANK

This entry assigns blanks to the string named BLANK.

## TE NOTE "MAP OF NORTH AMERICA IN SATELLITE PROJECTION

This entry stores the text MAP OF NORTH AMERICA IN SATELLITE PROJECTION under the string name NOTE.

#### TE MAPS "MAP NA

This entry stores the command MAP NA under the string name MAPS. To execute the MAP NA command from your workstation, type: ##MAPS.

#### TE MAPS . SAT

This entry changes NA in the above example to SAT. The new string looks like this: MAPS:=MAP SAT.

#### TE MAPS . . 5

This entry adds a third parameter (5) to the string which now looks like this: MAPS:=MAP SAT 5.

#### TE MAPS . DEF LAT=20 40 LON=90 120

This entry changes SAT to DEF and adds new parameters to the end of the string which now looks like this:

MAPS:=MAP DEF LAT=20 40 LON=90 120.

#### TE MAPS . MID X X X X X X X

This entry changes DEF to MID and deletes the remaining parameters. The new string looks like this: MAPS:=MAP MID

In the compound string example below, remember to define the string that replaces the ##value before defining the string that uses it. This example is entered from a workstation, not a 3270 terminal.

#### TE A "120

The replacement string is ##A.

#### TE LIST "LA 100 ##A

The actual string stored under LIST is LIST:=LA 100 120.

To vary the value in ##A, insert four # signs in string LIST:

#### TE LIST 'LA 100 ####A

The actual string stored is LIST=LA 100 #A.

If you change string A now, the new value will be used when LIST is executed. For example, if you enter the following change:

TE A "150

The system will use LA 100 150 the next time ##LIST is executed.

Assume the following string commands exist on the system.
TE LIST "LA 100 120;####TVLOAD
TE TVLOAD "DF 101 1 EC MSN

When ##LIST is executed from a workstation, the following commands are executed.

LA 100 120 DF 101 1 EC MSN

### Lists the strings in a string table.

**Formats** 

TL ALL

TL OUT

TL [keyword]

TL prefix [keyword]

**Parameters** 

ALL

lists the strings that begin with 0-9 and A-Z; the maximum

is 256

OUT

lists all strings, including global strings

prefix

lists the strings beginning with this prefix

**Keywords** 

NUM=

number of strings to list (default=20)

TERM=

terminal number to list string table from (default=current)

Remarks

Strings are stored alphabetically with numbers 0 to 9 at the end of the table. A string whose first character is a question mark (?) is called a global string. It is listed with TL OUT or TL ?. To list other strings that do not begin with 0-9 or A-Z, use TL OUT.

See Also

Use commands TD and TE to delete and enter strings. TU is the

string table utility.

**Examples** 

TL

This entry lists the first 20 strings from the current string table.

TL NUM=10

This entry lists the first 10 strings in the string table.

TL ALL

This entry lists all strings; the maximum is 256.

TL TEMP NUM=15

This entry lists up to 15 strings starting with TEMP.

### String table utility.

#### **Formats**

TU SAVE name [keywords] TU DEL name [keywords] TU LIST initials [keywords]

TU REST name initials [keywords]

#### **Parameters**

SAVE saves the string table

DEL deletes the string table

LIST lists string table directories (default=string tables

saved under the logged on initials)

REST restores a string table to your terminal and makes it

the current string table

1- to 12-character name identifying the string table name

initials 1- to 4-character name identifying your string table file;

this file name may contain numerous string tables

(default=initials used at log on)

ALL lists all string tables stored on McIDAS

#### **Keywords**

ALL= YES saves or restores all strings including global

NO saves or restores only the alphanumeric strings

(default)

SAVEFILE = LW file name to store the table in or restore it from; should only be used when you plan to write a file to tape; the LW file is deleted during the monthly purge at SSEC; use LWU LIST to list the contents of the file; command SEE, normally used to list LW files, does not work on the string table format

#### Remarks

If you do not specify initials with the LIST option, only entries saved under the logged on initials are listed. You may restore any string table as long as the correct name and initials are entered. You cannot save over or delete another user's string table.

The maximum number of tables you can save is 512.

A string name whose first character is a question mark (?) is global and remains after each restore.

#### See Also

Use commands TD, TE, and TL to delete, enter and list strings.

#### **Examples**

#### TU

This entry lists the string tables saved under your initials.

#### TU LIST ABC

This entry lists all the string tables stored under the initials ABC.

#### TU SAVE CLOUDS

This entry saves the current string table under the logged on initials and the name CLOUDS.

#### TU REST CLOUDS KJB

This entry restores the string table named CLOUDS stored under initials KJB.

#### TU DEL CLOUDS

This entry deletes the string table CLOUDS. The logged on initials must match the saved initials.

#### TU SAVE MYTABLE SAVEFILE=TEMPFILE

This entry stores table MYTABLE in the LW file TEMPFILE. This is not a permanently saved file and is deleted monthly. TEMPFILE can be written to tape and restored at a later date. To restore TEMPFILE on your terminal, use: TU REST name SAVEFILE=LWfile

# Chapter 4. Areas

AA	Copies and displays an area	4-1
ARCLST	Lists the GOES/GVAR satellite archive inventory	4-4
BU	Blows an image up or down	4-8
CA	Modifies the area directory	4-9
DF	Displays an area on an image frame	4-11
DFASAP	Displays an actively ingested area on multiple WWWs	4-15
DFC	Displays a radar area on a graphics frame	4-17
DFLOOP	Automates displaying images in real time on tower workstations	4-19
GA	Generates an area	4-21
GOLOOP	Sets the image and graphics frame parameters for DFLOOP	4-22
IS	Generates GOES IR stretch tables	4-23
LA	Lists an area directory	4-25
LOAD	Displays real-time satellite images using loop numbers	4-26
LOOP	Defines real-time satellite image loop control parameters	4-28
MOVIT	Copies areas and updates an image frame loop	4-30
PAA	Displays and scales an area to its display head size	4-33
POESAA	Sends fully calibrated POES areas to a workstation	4-35
QA	Deletes areas	4-37
ROTIRO	Rotates a POES image 180°	4-38
SECTOR	Uses the cursor to outline image sector extents	4-39
SENAA	Sends areas from the mainframe to a workstation	4-40
SEP	Sends the most recent image to a workstation or remote host	4-42
SEQ	Updates an image frame loop	4-46
SEQG	Updates an image and graphics frame loop	4-49
SETLUP	Defines frame bounds from loop parameters	4-51
SVGA	Generates an area from virtual graphics	4-52
TIRCAL	Calibrates POES images	4-53
TPREP		4-54

Revised 6/95

ii Revised 6/95

### AA

Copies and displays an area.

The ADDE command IMGCOPY may be used in place of AA.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

#### **Formats**

AA sarea darea frame locate station mag line ele [keywords]
AA sarea darea frame locate y-coord x-coord mag line ele [keywords]

#### **Parameters**

sarea source area number of the data

darea destination area number; must be different than sarea

frame image frame number for display; the data in darea is displayed on the frame (default=does not display darea)

OPP displays the image on the frame opposite the current image frame

locate

coordinate type for loading images (default=AU, meaning the area coordinates are displayed with the upper-left corner line and element); use one of these coordinate systems:

A area

E earth

I image

T TV

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

station station ID, e.g., MSN, DSM, 2C2; it must be preceded by

EU, EC or ED

y-coord y-axis coordinate (default=upper-left corner of the area)

x-coord x-axis coordinate (default=upper-left corner of the area)

mag image blowup or blowdown factor; positive numbers blow up; negative numbers blow down; blowups repeat data

values; blowdowns sample data (default=1)

line number dimensioning darea (default=500)

ele element number dimensioning darea (default=640)

Keywords	ASIZE=	ALL	copies the entire area including all bands; specify only sarea and darea with ASIZE=ALL; do not use any other keywords with this option; you can designate a frame number, but it is not necessary		
		SAME		s the original area size; overrides the lt <i>line</i> and <i>ele</i>	
	BAND=	will list entered	bands hig	nove; the range is 1 to 32; command LA ther than 9 as A, B, C, etc.; they must be r, that is, A=10, B=11, etc. (default=8	
				bands if subsecting a multibanded area	
	DOC=	YES NO		e image documentation section (default) nove the image documentation section	
	EMAG=	element	t only blow	rup or blowdown factor	
	0.202	repeat	inc start	adds a grayscale bar to the bottom of the image	
			repeat	brightness repetition factor (default=10)	
			inc	if greater than 0, it increments black to white, if less than 0, it increments white	
			start	to black (default=1) starting brightness value; the range is 0 to 63 (default=increment dependent)	

IR= 1 moves the image documentation section

LMAG= line only blowup or blowdown factor

#### Remarks

You cannot run this command from a remote mainframe. Also, you cannot specify keyword ASIZE and parameter *locate* in the same command line.

The coordinates for displaying images are listed below.

Y-coordinate	X-coordinate	Format
line	element	0 to 5 digits
latitude	longitude	DDD:MM:SS,
		DDD.fraction or
		station ID
line	element	0 to 5 digits
raster	pictel	0 to 3 digits
	line latitude	line element latitude longitude line element

## **Examples**

### AA 102 4000

This entry copies area 102 into area 4000, which is 500 lines by 640 elements, but does not display the image.

### AA 101 2000 1 EC 38 90 -4

This entry copies area 101 to area 2000 and displays the image on image frame 1, earth centering it at 38° N and 90° W. It has a blowdown factor of 4. Area 2000 is 500 lines by 640 elements, regardless of the size of area 101.

## AA 101 2000 1 ASIZE=ALL

This entry copies area 101 plus all bands into area 2000 and displays the image on image frame 1.

## AA 104 2000 10 EC 36 90 2

This entry copies area 104 into area 2000 and displays the image on image frame 10. It is centered on earth coordinates 36° N and 90° W. The brightness values are replicated to make a two times blowup.

## AA 101 3000 OPP IU 5000 6000

This entry copies area 101 into area 3000 and displays it on the image frame opposite the displayed frame. The area is moved and displayed by upper-left corner image coordinates 5000 and 6000.

## **AA 110 5000 OPP EC MSN**

This entry copies area 110 into area 5000 and displays the area on the opposite image frame, centering it on Madison, Wisconsin.

### AA 105 6512 ASIZE=ALL

This entry copies area 105 plus all bands to area 6512, but does not display the image.

Revised 6/95 4-3

## **ARCLST**

Lists the GOES/GVAR satellite archive inventory.

Format

ARCLST ss bday eday opt1 opt2 opt3 opt4 [keywords]

**Parameters** 

sensor source number, or enter one of the following

locations:

WEST GOES/GVAR West satellites
EAST GOES/GVAR East satellites

PRIME GOES Prime satellites; used when the satellite

is not located at the typical EAST or WEST

longitude (75°W or 135°W)

IND GOES satellite over the Indian Ocean, 60°E VAS GOES satellites sending Mode-AA VAS data

(1980-1981)

Prefix the ss number with a 2 for satellites sending Mode-AA VAS data (1980-1981). Also use a 2 for VAS satellites when three GOES satellites were simultaneously operational (e.g., 228).

bday beginning day, YYDDD or YY/MM/DD

eday ending day, YYDDD or YY/MM/DD (default=bday)

opt1..4 listing options, use one or more of the following in any order:

ACT image time, type and activity description

COM comments about image quality and exceptions

to the intended schedule

SKD operational schedules and associated times

TAP archive tape numbers and time of data on each

tape (default=ACT COM SKD)

**Keywords** 

FILE= name of the inventory database file to search (default=file

name in the table for the specified sensor source)

FORM= ALL lists an expanded version of the catalog comment

names and explanations for schedule exceptions; to see the entire comment explanation, direct

output to a printer

GEN= ACT lists tapes for active generation

ALL lists all tape generations

MATCH= lists the activities under the column heading Image Names

containing the specified substring

MCHSKD=	lists the schedules matching the specified substring		
RANGE=	btime etime	time range to list; lists all times between btime on bday and etime on eday, HH:MM:SS (if only btime is specified, etime defaults to btime)	
TIME=	btime etime	time range for each day to list, HH:MM:SS (if only btime is specified, etime defaults to btime)	
TYPE=	IMAGER	lists standard VISSR images and MSI imagery	
	SOUNDER	lists all Mode-AA, AAA, and GVAR block 11 dwell soundings	
	ALL	lists Imager and Sounder (default)	

## Remarks

ARCLST lists schedules, schedule times, schedule activities, schedule exceptions, comment names and their explanations, tapes and tape times for a specified day of the GARS (METEOSAT-3, GOES/GVAR) online inventory. Presently, this inventory exists only on the SSEC and GARS systems.

When using the default options ACT, COM and SKD, only comments for existing images are listed. To see a complete listing of all comments for all scheduled image times, enter COM for the options parameter.

If the values for keywords TIME and RANGE are both specified, TIME is used and RANGE is ignored. If neither TIME nor RANGE is specified, the listing includes all times for all days requested.

If the FORM=ALL option is listed, the comment explanations for the schedule exceptions may be truncated. To see the complete comment name and explanation, direct the output to a printer.

When listing comments and/or activities, all time periods of data loss are listed. The data loss comments are also listed regardless of the value of keyword MATCH.

The ARCLST output for the GVAR satellites (GOES-8 and GOES-9) reflects the flexible scanning capabilities of these satellites. Since they can scan extremely small earth sectors, the coverage listed by this command is defined by parameters that create geographical boundaries. The R used in the W-ELON parameters indicates the radius from earth center, which can be either + or -. When R is greater than .5, that corner of the geographical coverage is actually in space.

The ARCLST output parameters for the GVAR satellites are shown in the sample output below and defined in the table that follows.

IMAGE TIMES	IMAGE NAMES	IMAGE DESCRIPTIONS	
2:02	CONUS	CVRAGE= 375 816 9249 17752	
		CLAT=31 NLAT=58 W-ELON=6R 4	17
		CLON=86 SLAT=13 W-ELON=111 6	52
		BAND=12345	
2:09 SHS		CVRAGE= 1258 1570 8173 22020	
		CLAT=-34 NLAT=-21 W-ELON=123 3	32
		CLON=77 SLAT=-54 W-ELON=8R .7	7R
		BAND=12345	

Parameter	Definition
CVRAGE	image scan coordinates (www xxx yyy zzz); where, www = beginning image scan line number
	xxx = ending image scan line number
	yyy = beginning image element number
	zzz = ending image element number
CLAT	center latitude
NLAT	north latitude
W-ELON	(first entry) longitude of the upper left and right corners
CLON	center longitude
SLAT	south latitude
W-ELON	(second entry) longitude of the lower left and right corner

In the CONUS output, the center latitude of the image is 31° N; the center longitude is 86° W; the northern latitude is 58° N; the southern latitude is 13° N. The upper-left longitude of the image is -.6R (out in space); the upper-right longitude is 47° W; the lower-left longitude is 111° W; the lower-right longitude is 62° W.

In the SHS output, the center latitude of the image is 34° N; the center longitude is 77° W; the northern latitude is 21° S; the southern latitude is 54° S. The upper-left longitude is 123° W; the upper-right longitude is 32° W; the lower-left longitude is -.8R (in space); the lower-right longitude equals .7R (in space).

## **Examples**

## ARCLST 32 90010 X RANGE=00:01 06:01 MATCH=MSI

This entry lists all schedule times, activities and exceptions that contain the substring MSI for sensor source 32, from 00:01 through 06:01 images on day 90010.

## ARCLST WEST 90010 X RANGE=1 6 MATCH=MSI

This entry lists the schedule times, activities and exceptions that contain the substring MSI for any GOES West satellite, from 01:00 through 06:00 images on day 90010. The listing will not contain data for the 6 UTC image, which is transmitted at 06:01 UTC.

## ARCLST 228 81160 81160 ACT

This entry lists the activities on Julian day 81160 for sensor source 228.

### ARCLST VAS 81160 81160 ACT

This entry lists the same information as the previous example, except it uses the more broad descriptor VAS instead of the specific sensor source number. If other operational satellites were classified as VAS satellites for this period, an activity list for those satellites is also generated.

## ARCLST 32 90010 90012 TIME=00:01 06:01

This entry lists the schedule times, activities and exceptions that occurred for sensor source 32 from 00:01 through 06:01 for days 90010 through 90012.

#### ARCLST 32 90010 X COM FORM=ALL

This entry lists only comments and comment explanations for schedule exceptions, for sensor source 32 on day 90010. The output is in an expanded screen format.

#### ARCLST 32 90010 X COM SKD TAP FORM=ALL

This entry lists the comment names and explanations for schedule exceptions, schedules and their times, and tape IDs and times for sensor source 32 on day 90010. The output is in an expanded screen format.

#### ARCLST 32 90010 X ACT

This entry lists only schedule activities for sensor source 32 on day 90010.

## ARCLST 32 90152 90243 SKD MCHSKD=RISOP

This entry lists the schedule times from June 1 to August 31, 1990, on days that a RISOP schedule was in effect.

## ARCLST 54 93010 ACT

This entry lists the activities for METEOSAT-3, sensor source 54, for day 93010.

## BU

frame

emag

area

## Blows an image up or down.

**Format** 

BU frame lmag emag area

**Parameters** 

OPP displays the blowup on the opposite image frame
TV frame number for the image load (default=current)

lmag line magnification factor (default=1)

element magnification factor (default=lmag)

area number containing the data (default=current frame's

area number)

Remarks

Magnification factors are relative to the area resolution. If line and element magnifications are less than zero, the image is blown down. The image is center loaded using the coordinates of the cursor center.

**Examples** 

BU 2 -3

This entry blows down the currently displayed image three times and displays it on image frame 2.

BU 1 4 X 10

This entry blows up area 10 four times and displays it on image frame 1. Because X means use the default value, this example can also be entered as:  $BU\ 1\ 4\ 4\ 10$ .

# CA

# Modifies the area directory.

Format	CA area parm1parm11 [keywords] "text		
		t sear cooper serva so vote	
Parameters	area	area number of the directory to be changed	
	parm111	new directory values; insert X to indicate no change	
	"text	text to replace the memo portion of the area directory as seen by typing the command line:  LA area FORM=EXP; quotes are mandatory	
Keywords	BAND=	replaces the band sequence; the range is 1 to 32  NA means not applicable	
	CAL=	changes the length of the calibration section of the prefix; must be a multiple of 4	
	CODE=	changes the validity code	
	CTYPE=	changes the calibration type	
	DOC=	changes the length of the documentation section of the prefix; must be a multiple of 4	
	LEV=	changes the length of the level section of the prefix; must be a multiple of 4	
	NAV=	pri sec changes the primary and secondary codicil navigation pointers; for system navigation enter: NAV=0 10	
	PFX=	changes the total length of the line prefix; must be the sum of the fields that can be changed with the keywords CAL=, DOC= and LEV=; add 4 if the validity code is present	
	STYPE=	changes the source type	
Remarks	Parameters er	ntered with CA replace the area directory and current	

values listed by typing: LA area.

Revised 6/95

## **Examples**

To change the line and element coordinates from 1698 and 2830 to 1700 and 2800, first list area 1100.

Type: LA 1100

The following information is displayed on the screen.

AREA SS YYDDD HHMMSS LCOR ECOR LR ER ZR LSIZ ESIZ Z BANDS 1100 28 83199 190000 1698 2830 1 1 0 2880 5948 1 NA

To change the line and element coordinates,

Type: CA 1100 X X X 1700 2800 BAND=1 3 8

The area directory's LCOR and ECOR are changed to 1700 and 2800. The information below is displayed on the screen.

AREA SS YYDDD HHMMSS LCOR ECOR LR ER ZR LSIZ ESIZ Z BANDS

1100 28 83199 190000 1700 2800 1 1 0 2880 5948 1 1.3...8

PROJ: 0 CREATED: 85113 165702 MEMO:

TYPE: AREA VALCOD: 0 IMAGE ID:

NAVIGATION CODICIL: PRIMARY= 0 SECONDARY=300

ZCOR: 0 Y-Z PREFIX: 0

## DF

Displays an area on an image frame.

The ADDE command IMGDISP may be used in place of DF.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

### **Formats**

DF area frame locate y-coord x-coord mag repeat [keywords]
DF area frame locate station mag repeat [keywords]

## **Parameters**

area number of the data to display

frame image frame number to display

OPP displays the image on the frame opposite the current frame

locate

coordinate type for loading images (default=AU, meaning the area coordinates are displayed with the upper-left corner line and element); use one of these coordinate systems:

A area

E earth

I image

 $\mathbf{T}$  TV

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

optionally followed by:

R uses the current load enhancement table set up by command IS, table 0; only works on tower workstations

0 to 8 uses this load enhancement table number set up by command IS; only works on tower workstations

y-coord y-axis coordinate (default=upper-left corner of the area)

x-coord x-axis coordinate (default=upper-left corner of the area)

station station ID, e.g., MSN, DSM, 2C2; must be preceded by EU, EC or ED

mag image blowup or blowdown factor (default=1)

repeat number of consecutive frames to load from consecutive areas; see keyword INC below for an incremental load (default=1)

Keywords

ANN= bkgrd char

grayscale values for the annotation line's background and characters located at the bottom of the screen (default=32 192 for WIDE WORD and McIDAS-X workstations; 32 160 for tower and SDA workstations; 0 255 for VGAs)

AREA= destination area number; the area is sent via command SENAA to WIDE WORD and SDA workstations connected asynchronously (default=frame number)

BAND= area band number; the range is 1 to 32; command LA will list bands higher than 9 as A, B, C, etc.; they must be entered as integer, that is, A=10, B=11, etc. (default=8 for GOES IR, 4 for POES)

CAL= QTIR calibration module name; use QTIR for a fast POES load (default=from the area directory); the first calibration is used for the entire image; the area is unaffected

EMAG= element only blowup or blowdown factor (default=1)

EU= name name of the enhancement table on the workstation to apply to the image

GRAY= NO does not display a grayscale bar (default)
YES adds a grayscale bar to the bottom of the image using the defaults below

repeat inc start line

repeat brightness repetition factor (default=10)
inc if greater than 0, increments black to white;
if less than 0, increments white to black
(default=1)

start starting brightness value (default=0)

start starting brightness value (default=0)
line starting TV line (default=-23, the bottom of
the image)

INC= ainc finc area and frame increments for repeat parameters (default=1 1)

LMAG= line only blowup or blowdown factor (default=1)

#### Remarks

The coordinates for displaying images are listed below.

Location	Y-coordinate	X-coordinate	Format	
A	line	element	0 to 5 digits	
E	latitude	longitude	DDD:MM:SS, DDD.fraction or station ID	
I T	line raster	element pictel	0 to 5 digits 0 to 3 digits	

DF displays images from areas up to 12,000 lines and elements in size.

If your workstation is on ProNET and has an VGA display, DF deletes the mainframe graphics directory corresponding to the destination frame number for the display so that coordinate transformations work correctly.

If you have a VGA workstation and want to adjust the gray scale, use command SENAA to transfer the data. Then display the image with DF's LEVELS= keyword on the workstation.

When using keyword EU, the name specified must be an enhancement saved on the workstation. Use the workstation command EU LIST to list the saved enhancements on your workstation.

SSEC does not recommend running the McIDAS-MVS version of DF on asychronously-connected WIDE WORD or SDA workstations. The preferred method is to send the area to the workstation with command SENAA and load the image with DF on McIDAS-OS2. If you DF an area to an asychronously-connected WIDE WORD or SDA workstation, the area is sent via SENAA and loaded with the McIDAS-OS2 DF. The data is sent to the area number equal to the frame number. If you designate a repeat factor, consecutive workstation area numbers are used. For a single DF, the area number can be overridden using the AREA keyword. The same area number is reused when using a repeat factor combined with the AREA keyword. Due to the limitations of SENAA, positive magnification values are not available.

Revised 6/95

## **Examples**

## DF 1 10 EC 36.5 90.5 -4 2 INC=3 -2

This entry loads areas 1 and 4 onto image frames 10 and 8, respectively. The images are centered at  $361/2^{\circ}$  North and  $901/2^{\circ}$  West with a 4-times blowdown.

## DF 4 2 ED MSN

ac 76 to minimize 2006-24 GLb Maintenand premiero per con sold D 122

This entry loads area 4 on image frame 2 with Madison, Wisconsin, positioned in the lower-right corner.

## DF 101 OPP

This entry loads area 101 on the image frame opposite the displayed frame. It loads from the upper-left corner of area 101.

## DF 7500 3 EC 75 -150 EU=POLAR.ET

This entry loads area 7500 on image frame 3. The image is centered at 75° N and 150° E. The saved enhancement POLAR.ET is applied when the image is loaded.

## **DFASAP**

Displays an actively ingested area on multiple WWWs.

**Formats** 

DFASAP area frame locate y-coord x-coord mag repeat [keywords] DFASAP area frame locate station mag repeat [keywords]

**Parameters** 

area number of the data for display

frame image frame number for display

locate coordinate type for loading images (default=AU, meaning the area coordinates are displayed with the upper-left corner line and element); use one of these coordinate systems:

A area
E earth

I image T TV

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

optionally followed by:

R uses the current load enhancement table set up by command IS, table 0

0 to 8 uses this load enhancement table number set up by command IS

y-coord y-axis coordinate (default=0)

x-coord x-axis coordinate (default=0)

station 3-letter station ID, e.g., MSN, DSM; must be preceded by EU, EC or ED

mag image blowup or blowdown factor (default=1)

repeat number of consecutive frames loaded from consecutive areas; only the area being ingested at the moment DFASAP is run is displayed line-by-line; all other areas are displayed as old data (default=1)

## Keywords

ALSO= t1 t2 t3 ...

terminal numbers of other WWWs on which the image will be displayed on the same image frame number (default=your WWW)

ANN= bkgrd char

grayscale values for the annotation line's background and characters located at the bottom of the screen (default=32 192)

BAND= specifies bands for soundings (default=8 for VAS, 4 for

AVHRR)

CAL= calibration module name; use QTIR for a quick POES load

(default=from the area directory)

**EMAG**= element only blowup or blowdown factor (default=1)

LMAG= line only blowup or blowdown factor (default=1)

#### Remarks

Use DFASAP on WIDE WORD workstations only. Currently, it only works correctly for GOES and GVAR data.

You can run DFASAP while data is being received. The DF command only displays data that currently resides in an area, whereas DFASAP displays data as each line is ingested.

DFASAP is recommended for large frames (greater than 1024 x 1024), even for non real-time data. Non real-time data with smaller frame sizes will be more efficient with DF.

Use keyword ALSO to display the same image on several WWWs.

## **Examples**

## DFASAP 200 5

This entry loads area 200 on image frame 5 using the upper-left corner area coordinates.

## DFASAP 102 1 EC MSN -2 3

This entry loads areas 102, 103 and 104 on image frames 1, 2 and 3 respectively, centered on MSN with a two times blowdown for each image. If area 102 is still collecting data, a worker is held until the satellite has scanned enough data to complete the area. Areas 103 and 104 will not be updated before they're displayed.

## DFASAP 202 12 ID 1000 1200 ALSO=67

This entry loads area 202 on image frame 12 with image line 1000 and image element 1200 located in the lower-right corner. The same image is also displayed on image frame 12 of terminal 67.

## **DFC**

## Displays a radar area on a graphics frame.

_			
Fo	rm	a	ts

DFC area frame locate y-coord x-coord mag repeat [keywords]

DFC area frame locate station mag repeat [keywords]

**Parameters** 

area

radar area number to display

frame

graphics frame number to display

locate

coordinate type used to load images, e.g., IC, EC, UC, etc. (default=AU, meaning the area coordinates are displayed with the upper-left corner line and element); use one of these coordinate systems:

A area

image I + I then the radius and I + I

and a composite relies much beginning to E earth

T TV (cursor)

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

optionally followed by:

R uses the current load enhancement table set up by command IS, table 0

0 to 8 loads this enhancement table number set up by

command IS

y-coord y-axis coordinate (default=0)

*x-coord* x-axis coordinate (default=0)

station three-letter station ID; must be preceded by EU, EC or ED

mag image blowup or blowdown factor (default=1)

repeat number of consecutive frames loaded from consecutive

areas (default=1)

## **Keywords**

BAND= band specifier for soundings (default=8 for VAS, 2 for

AVHRR)

CAL= most significant bit number for left or right shift

0 calibrates sounding data (default)

EMAG= element only blowup or blowdown factor

LMAG= line only blowup or blowdown factor

NAV= YES attaches the graphics frame navigation to the frame

directory

NO leaves the image frame as the source for navigation

(default)

## Remarks

Command DFC displays only radar images on graphics frames. It does not display satellite images.

To overlay a satellite image with a manually digitized radar (MDR) image, use command MDRIMG to create the radar image, then use command REMAP to convert the radar image from polar stereographic to satellite projection. Finally, use command DFC to display the radar area on a graphics frame that overlays the corresponding satellite image.

Selecting NAV=YES attaches the graphics frame navigation (which comes from the radar area) to the current frame directory. Therefore, running any navigation dependent command (e.g., MAP, E, PC) will result in that command using the navigation from the graphics frame instead of the image frame. This state will exist until another image is displayed on the image frame, resulting in its navigation being written to the frame directory, as usual.

## **Examples**

## DFC 1200 5

This entry displays radar image 1200 on graphics frame 5, with the upper-left corner of the area in the upper-left corner of the graphics frame.

## DFC 1001 2 EC 36 90

This entry displays radar image 1001 on graphics frame 2 centered at  $36^{\circ}$  N and  $90^{\circ}$  W.

## **DFLOOP**

Automates displaying images in real time on tower workstations.

**Formats** 

DFLOOP loop barea earea bframe eframe lat lon interval band res

irtype [keyword]

DFLOOP loop ON DFLOOP loop OFF

DFLOOP loop MOD lat lon

DFLOOP loop NEXT bframe

**Parameters** 

loop loop number; the range is 1 to 32 (no default)

ON enables a loop

OFF disables a loop

MOD changes the center point of a loop

NEXT displays the next frame in the loop (no default)

barea beginning area to display (no default)

earea ending area to display (no default)

bframe beginning frame to display (no default)

eframe ending frame to display (no default)

lat image center point latitude, adjusted by MOD

(no default)

lon image center point longitude, adjusted by MOD

(no default)

interval in minutes; not a time notation (default=30)

band number (default=0 for visible)

res image resolution; a positive number means blow up; a

negative number means blow down (default=1, blow up)

irtype IR table number from the IS command for data

modification; the range is 1 to 8 (default=0, none)

Keyword

TERM= terminal number (default=current)

Remarks

DFLOOP works only on tower workstations. WWWs should use DFASAP.

Use command DFLOOP to set real-time image display parameters (request DF commands) for your workstation.

The image displays are performed automatically by command MULMUL, which initiates the multiple TV loads and is run by the event scheduler. DFMUL is started by MULMUL to do individual TV loads. Neither MULMUL nor DFMUL should be entered by a user. See command GOLOOP for easy loop activation after TV loads occur.

The DFLOOP method of automatic image loading is more efficient than the older SEQ or LOOP/LOAD methods. However, this is true only if the resolution of the ingested data matches the resolution of the image load request. If you request a different resolution for the image load, DFLOOP provides only a slight performance advantage.

**Examples** 

**DFLOOP** 

This entry lists the previously entered loops.

**DFLOOP 1 OFF** 

This entry disables loop number 1.

DFLOOP 1 ON

This entry enables loop number 1.

DFLOOP 12 6000 6008 1 10 X X X 3 X 2

This entry sets real-time loop control parameters for loop 12, areas 6000 to 6008. It also loads frames 1 to 10, band number 3, IR table 2.

DFLOOP 2 0 0 0 0 0

This entry deletes loop 2 from the list.

## GA

## Generates an area.

**Format** 

GA area line ele zsize

**Parameters** 

area number to generate area

line

number of lines in the area (default=500)

ele number of elements in the area (default=640)

zsize

number of bytes per data element (default=1)

Remarks

The default area size is 500 by 640 by 1, which is the size of one

See Also

Use command AA to copy data into the new area.

**Examples** 

This entry generates area 2500 to be 500 lines by 640 elements.

GA 1007 1000 1500

This entry generates area 1007 to be 1000 lines by 1500 elements.

GA 3000 800 1000

This entry generates area 3000 to be 800 lines by 1000 elements.

## **GOLOOP**

Sets the image and graphics frame parameters for DFLOOP on tower workstations.

**Format** 

GOLOOP loop dwell cdwell

**Parameters** 

loop number from command DFLOOP; the range is

1 to 32 (default=1)

dwell

loop

dwell rate for all but the most current frame

(default=5/15 seconds)

cdwell

dwell rate for the current frame in seconds

(default=15/15 seconds)

Remarks

Command GOLOOP sets image and graphics frame bounds from the loop parameter set by command DFLOOP for McIDAS-OS2 and tower workstations. This activates a loop. In this way GOLOOP can run from a single keystroke string, allowing easy loop activation. Command DFLOOP sets real-time TV load parameters.

**Examples** 

**GOLOOP** 

This entry sets image and graphics frame bounds for the loop number in command DFLOOP. The loop number is 1; dwell rates are 15 for the current frame, 5 for all others.

## GOLOOP 10 X 10

This entry sets image and graphics frame bounds from DFLOOP parameter *loop* for loop 10; the dwell rate is 10/15 seconds for the current frame.

## IS

## Generates GOES IR stretch tables.

**Formats** 

IS CLE table

IS LIST table [keyword]

IS DEF table input1 output1 ... inputn outputn [keyword]

IS GRA table min max [keyword]

**Parameters** 

CLE

clears the table of existing values

LIST

lists the input and output values of the table

DEF

defines the table

GRA

graphs the interpolated data

table

table number; the range is 0 to 8

input1..n

input number; pixel range is 0 to 255; Kelvin range is

163 to 330; Celsius range is -110 to 57

output1..n

output number for the gray scale; the range is 0 to 63

min

minimum plotted value on the x-axis

max

maximum plotted value on the x-axis

Keyword

UNIT=

K Kelvin

P pixel brightness

C Celsius (default)

Remarks

Command IS only works on GOES IR imagery and on tower and WIDE

WORD workstations.

You can specify multiple pairs of input and output per command. Use the DF command to display a stretched image. Before generating a new stretch table (3), clear the table with: IS CLE 3.

The output range 0 to 63 is scaled from 0 to 255 during image enhancement on a WIDE WORD workstation.

## **Examples**

## 1. IS DEF 3 240 30 UNIT=K

This entry creates table 3. Temperatures of 240°K are now represented as brightness count 30, thereby stretching temperatures less than 240° over counts 30 to 63 which are scaled from 121 to 255 during image display.

## IS LIST 3 UNIT=K

This entry lists table 3 in Kelvin.

## DF 109 5 EC3 36 90

This entry applies table 3 to GOES IR area 109.

2. This example generates a new table 5.

## IS CLE 5

This entry clears table 5.

## IS DEF 5 -32 40 -34 42 -36 44 -38 46

This entry generates table 5 using multiple cutoffs. Values are linearly stretched between values; -32°C becomes brightness 40, -34°C becomes 42, etc.

#### DF 1001 5 AU5

This entry applies table 5 to area 1001.

## LA

Lists an area directory.

The ADDE command IMGLIST may be used in place of LA.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

LA barea earea [keywords]

**Parameters** 

barea

beginning area directory to list

earea

ending area directory to list (default=barea)

Keywords

DAY=

lists areas for the specified day and year only, YYDDD or

YY/MM/DD; if DDD=0, all days for YY are listed

FORM=

ALL

lists the entire area directory

AUDIT

lists the entire directory with its audit trail

**EXP** 

lists an expanded version of the area directory

SS=

ss1 ss2

lists the areas for up to two sensor sources

TIME=

lists the areas with this time only, HH:MM:SS

#### Remarks

If you use FORM=ALL with POES, be sure to check the MEMO line in the directory information. The signal will be HRPT (LAC or GAC). The product will be MULT (multiple) or SIG (single) band. The ground station will be Wallops Island (W) or Gilmore Creek/ Fairbanks (G). The A or D in the line represents Ascending or Descending pass. If D appears on the line, the image is upside down.

Type SHOWME DNBANDS for detailed information on the BANDS column.

## **Examples**

## LA 101 120 TIME=21:01

This entry lists the areas between 101 and 120 with time 2101 UTC.

#### LA 101

This entry lists the single line directory for area 101 only.

## LA 1000 1040 SS=32 55

This entry lists the areas between 1000 and 1040 for sensor sources 32 and 55.

## LOAD

Displays real-time satellite images using loop numbers.

**Formats** 

LOAD SCH DR=

LOAD ESCH SAT= DR= LOAD loop OPT=ALL DR=

**Parameters** 

SCH checks and displays satellite images for all loops associated

with the current terminal number; SCH is usually run from

the command scheduler; see the SKE command

ESCH checks and displays satellite images for all loops associated

with the current terminal number; ESCH is usually run

from the event scheduler; see the ESKE command

loop number of the loop to display; the range is 1 to 9

Keywords

days for YY are hared ...

DR= YES changes the dwell rate to 5 (default)

NO leaves the dwell rate at its current setting

OPT= ALL displays all images of a loop; if not specified,

only one image is displayed

SAT= EAST loads GOES EAST satellite images (default)

WEST loads GOES WEST satellite images

Remarks

The loop numbers are from the LOOP command. This command is

mainly used from the scheduler.

The dwell rate is in units of  $V_{15}$  second.

See Also

See the LOOP, SETLUP and SKE commands for more information.

**Examples** 

LOAD 4 OPT=ALL

If you type this entry interactively, the frames defined in loop 4 are displayed immediately. See Example 4 in the LOOP command for the definition of loop 4.

SKE 92200 18:00:00 999999 :05 "LOAD SCH

This entry defines a scheduler entry that is turned on at 18:00:00 UTC, day 200, 1992. All loops are checked every five minutes and applicable images are displayed.

bagining and ending image in an administration

ESKE "F22=2&(F27>550VF23=5VF23=8)&F5002=0
"LOAD ESCH SAT=EAST
ESKE "F22=2&(F27>550VF23=5VF23=8)&F5002=0
"SETF F5002 1

ESKE "F22=2&F23=1 "SETF F5002 0

This entry runs LOAD from the event scheduler when a new satellite image is ingested from image spool 2. For a description of the event flags, see DNEFLAGS. The character V represents the logical operator OR (V).

## LOOP

Defines real-time satellite image loop control parameters.

Format

LOOP loop option [keywords]

**Parameters** 

loop loop number; the range is 1 to 9

option ON

N turns the loop on

OFF turns the loop off
DEL deletes the loop

**Keywords** 

AREA= beg end beginning and ending real-time area numbers

to search

BAND= band number

DR= YES changes the dwell rate to 5 (default)

NO leaves the dwell rate at its current setting

FRA= beg end beginning and ending image frame numbers

defining the loop

INC= time increment between scheduled TV loads, in minutes

(default=30)

IS= IR stretching table number set by the IS command;

the range is 1 to 8; works only on tower workstations

LAT= latitude of the image center

LON= longitude of the image center

OPP= defines the loop opposite the currently defined loop

RES= image resolution, in km (default=4)

SAT= EAST data is from GOES East (default)

WEST data is from GOES West

**SEQ=**  $loop 1 \dots n$  ordered sequence of loop numbers loaded by

the scheduler (default=1 2 3 4 5 6 7 8 9)

TYP= IR infrared

VIS visible

WV water vapor, band 10

### Remarks

The parameters defined here are used by the LOAD command for the scheduled displaying of satellite loops.

If keywords SAT, FRA, LAT, LON, RES and INC are changed or the loop is turned OFF or DELeted, the opposite loop is removed.

The dwell rate is in units of  $V_{15}$  second.

## See Also

See the LOAD and SETLUP commands for more information.

## **Examples**

## LOOP

This entry lists all previously defined loops.

# LOOP 1 TYP=VIS SAT=EAST FRA=1 4 LAT=40 LON=90 RES=1 INC=15 AREA=101 104

This entry defines loop 1 using GOES East visible 1 km satellite data from areas 101 to 104. It loads the loop on frames 1 to 4, centered on 40° N, 90° W. The time interval between loop loads is 15 minutes.

## LOOP 3 OPP=1

This entry defines loop 3, which is the opposite of loop 1. All parameters are the same as loop 1 except the opposite type (IR) is used. FRA is opposite; AREA is the opposite data areas, (105-108); the IS table is 0.

## LOOP 4 TYP=VIS SAT=EAST FRA=5 6 LAT=30 LON=77 RES=4 AREA=113 114 IS=1

This entry defines loop 4 using GOES East visible 4 km resolution satellite data from areas 113 and 114. It loads frames 5 and 6, centered on 30° N, 77° W, using IS table 1.

## LOOP 6 OPP=4 SEQ=4 6 3 1

This entry defines loop 6, which is the opposite of loop 4, and sets the loading sequence so loop 4 is loaded first, then loop 6, etc.

## LOOP 1 OFF

This entry turns off loop 1. When the scheduler scans the loop, it will not be loaded. Also, loop 6 is no longer the opposite of loop 1.

## MOVIT

Copies areas and updates an image frame loop.

The ADDE command IMGCOPY may be used in place of MOVIT.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

### **Formats**

MOVIT bsarea esarea bdarea edarea bframe eframe locate y-coord x-coord mag line ele [keywords]

MOVIT bsarea esarea bdarea edarea bframe eframe locate station mag line ele [keywords]

## **Parameters**

bsarea beginning source area number

esarea ending source area number

bdarea beginning destination area number; must be different

than bsarea

edarea ending destination area number

bframe beginning image frame number (default=does not update

the image frame)

eframe ending image frame number (default=bframe)

locate coordinate type for loading images (default=AU, meaning

the area coordinates are displayed with the upper-left corner line and element); use one of these coordinate systems:

A area

E earth

I image

T TV

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

y-coord y-axis coordinate (default=upper-left corner)

x-coord x-axis coordinate (default=upper-left corner)

station 3- or 4-character station ID, e.g., MSN, DSM; must be

preceded by EU, EC or ED

	mag		resolution blowup (positive numbers) or blowdown ive numbers); blowups repeat data values while
		blowdo	wns sample data (default=1)
	line		umber dimension defining <i>bdarea</i> and <i>edarea</i> (t=500)
	ele		at number dimension defining $bdarea$ and $edarea$ $(t=640)$
Keywords	ASIZE=	ALL	moves an entire area including all bands
	BAND=	will lis	number to move, the range is 1 to 32; command LA t bands higher than 9 as A, B, C etc.; they must be d as integer, that is, A=10, B=11, etc. (default=8 ES IR, 1 for POES)
		ALL	moves all bands if subsecting a multibanded area
	IR=	1	moves image documentation (default=strips off line documentation section)
	MOVE=	ALL TEST	moves all areas lists the first AA command generated to update the sequence, but does not run it
	STYPE=	VISR	converts a 2-byte area to a 1-byte area
Remarks	MOVIT loc	cates the	e most recent area in the range bsarea to esarea and

## Remarks

MOVIT locates the most recent area in the range *bsarea* to *esarea* and copies it using the AA command into the area following the most recent area in the range *bdarea* to *edarea*. There is a limit of 200 areas in the *bdarea* to *edarea* range. To copy all areas in *bsarea* to *esarea* in time order (oldest to most recent), use keyword MOVE=ALL.

The coordinates for displaying images are listed below.

Location	Y-coordinate	X-coordinate	Format	
A	line	element	0 to 3 digits	
E	latitude	longitude	DDD:MM:SS,	
			DDD.fraction or	
			station ID	
I	line	element	0 to 5 digits	
$\mathbf{T}$	raster	pictel	0 to 3 digits	

## **Examples**

## MOVIT 1000 1010 3300 3310

This entry searches areas 1000 to 1010 for the most recent time and copies the most recent image into the area following the latest time in 3300 to 3310. It does not display the image.

## MOVIT 1000 1010 3300 3310 MOVE=TEST

This entry displays the first AA command for copying the area with the most recent time between the range of 3300 to 3310.

## MOVIT 1000 1010 3300 3310 10 20

This entry locates the most recent time in areas 1000 to 1010 and copies it into the area following the latest time in 3300 to 3310. It also displays the image after the latest image frame from 10 to 20.

# PAA

Displays and scales an area to its display head size.

Format	PAA area	device options bias MAP [keywords]	
Parameters	area	area number to read the data from; the entire area is read and scaled to the size of the display (no default)	
	device	CW text screen display, alphanumeric, 24 x 80 (default) 3 3278, alphanumeric, 20 x 80 PW 100 x 160 workstation display	
		<ul> <li>ZW 350 x 640 workstation display</li> <li>YW 200 x 320 workstation display</li> <li>AW Apple II computer</li> </ul>	
	options	A alphanumeric characters, 26 levels, use with any device (default)	
		G 16 gray levels, use with device P, Z, Y half tone, use with device P, Z, Y, A S squeezed half tones, use with device P, Z, Y, A quarter tone, use with device P, Z, Y extended alpha, 32 levels, use with any device	
	bias	value to subtract from each value prior to scaling and transmission (default=0)	
	MAP	includes a base map in the data (default=none)	
Keywords	AREA=	output destination area number; this is only valid on workstations running McIDAS-OS2 (default=does not store the data upon receipt)	
	BAND=	wavelength band chosen from a multibanded area (default=8 for multibanded data)	
	ELE=	number of elements of output on each line (default=defined by output device)	
		number of lines of output (default=defined by output device)	
	NAM=	name of the map base file; valid only when MAP is specified; use OUTLUSA, OUTLUSAL, OUTLWRLD, OUTLEURO, OUTLPOLI or OUTLAUST (default=OUTLUSA or OUTLUSAL depending on the geographic coverage of the area number)	

NAV= ON for polynomial coefficients

**COD** sends a navigation codicil with the data

(default=does not send navigation)

STR= min max stretches the original values between min and

max into the range 0 to 255 before any additional

scaling is performed (default=0 255)

TIME= if the value specified is greater than the time of the AREA

specified, nothing is sent; used for scheduling commands

(default=the time in AREA)

### Remarks

PAA stretches the data to fit the output device. Source area line/element extents should match the output device (e.g., 350 by 640 for VGA). Otherwise, navigation will not match the image.

If the *options* are not specified, the default is a form of character shading suitable for a quick look. For G/H/S output formats, the following information is provided on the header line:

TYPE NAVSTAT SSYYDDD HHMMSS IMGLINE IMGELE LINES ELES LINES ELERES LINESOUT ELESOUT

For all device types, using the letter W (e.g., ZW) fills the output packets and speeds up data transmission; otherwise, only one line is placed in a packet. For example, PAA 123 Z G.

## **Examples**

### **PAA 1001**

This entry scales area 1001 onto a 24x80 text screen. It produces 26 brightness levels shown with letters on the display.

### PAA 112 CW E 0 MAP

This entry scales area 112 onto a 24x80 text screen display, and produces 32 levels of brightness, shown with letters on the display. A base map of geography is imbedded in this display using the quote sign (").

## PAA 4321 ZW G 0 MAP NAME=OUTLUSA

This entry scales area 4321 onto a 350x640 VGA display, and converts the values into 16 gray levels. A map is imbedded in the data using the latitude/longitude coordinates in the OUTLUSA file. Several lines are packed into transmission packets.

## PAA 4332 Z Q 0 MAP STR=50 200 TIME=20:08

This entry does nothing if the time of the data in area 4332 is past 20:08. Otherwise, data is extracted from this area and values are stretched by mapping values from 50 to 200 into the range 0-255. This data is averaged to a 350x640 domain, and then converted into quarter-tones, suitable for an EGA display. Each line of data is contained in a separate communications packet for transmission (since the W option is omitted).

## POESAA

Sends fully calibrated POES areas to a workstation.

Formats

POESAA sarea darea locate y-coord x-coord mag line ele [keyword] POESAA sarea darea locate station mag line ele [keyword]

**Parameters** 

sarea source area number of the data (no default)

darea destination area number for the data (no default)

locate coordinate type used to transfer the area; use one of these

coordinate systems:

E earthI image

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

y-coord y-axis coordinate (default=first line)

x-coord x-axis coordinate (default=first element)

station station ID, e.g., MSN, DSM, 2C2; it must be preceded by

EU, EC or ED

mag this option has not been implemented; data must be full

resolution (default=1)

line number of lines in darea (default is workstation

dependent)

ele number of elements in darea (default is workstation

dependent)

Keyword BAND=

band number to move (default=4)

ALL moves all bands

Remarks

POESAA sends sectorized POES data to a McIDAS workstation. The

data is fully calibrated before it is sent to the workstation.

You must specify 1 as the magnification factor for the image. Only full

resolution POES data can be calibrated.

## **Examples**

## POESAA 710 1000 EC OMA 1 200 200 BAND=4

This entry sends band 4 of area 710 to workstation area 1000. The data is fully calibrated and centered on Omaha, Nebraska. The size of the destination area on the workstation is 200 lines by 200 elements.

## POESAA 829 1001 IU 91 1 BAND=ALL

This entry sends all bands of area 829 to workstation area 1001. The data is fully calibrated. The size of the destination area depends on the workstation.

4-36 Revised 6/95

## QA

Deletes areas.

The ADDE command IMGDEL may be used in place of QA.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

QA barea earea

**Parameters** 

barea

beginning area number to delete

earea

ending area number to delete (default=barea)

**Examples** 

QA 1101 1120

This entry deletes areas 1101 to 1120.

QA 1101

This entry deletes area 1101 only.

## **ROTIRO**

Rotates a POES image 180°.

**Format** 

ROTIRO sarea darea

**Parameters** 

sarea

source area number

darea

destination area number

Remarks

ROTIRO flips an entire POES real-time image  $180^{\circ}$  so that an image

scanned south to north can be viewed with north up.

Use this command only on an original AVHRR image area. If the image size is moved with AA, it will work only if the image is the same size as

the original.

**Example** 

**ROTIRO 5205 6000** 

This entry rotates POES area 5205 by 180° and writes the new area

into 6000.

## **SECTOR**

Uses the cursor to outline image sector extents.

Format

SECTOR mag line ele

**Parameters** 

mag magnification factor applied to the area, not the displayed image; no positive numbers more than half the resolution of the displayed image (default=1)

line number of lines in the image sector (default=480)

number of elements in the image sector (default=640)

Remarks

Use command SECTOR to specify the magnification and size of an area subset. The currently displayed image is used when indicating the coverage of the subset. The cursor size is changed in proportion to the parameters entered, illustrating the exact coverage.

When you use command SECTOR on a WIDE WORD workstation, the maximum size of the cursor is 256 x 256.

See Also

Use command DF to display the area on an image frame at the magnification established with command SECTOR.

**Examples** 

#### SECTOR

ele

This entry encloses the image sector on the displayed image with no change in resolution. The sector is based on the digital area's resolution, not the displayed area's resolution.

#### SECTOR -4

This entry changes the cursor size to represent a 4x blowdown of the area, not the displayed image.

### SENAA

Sends areas from the mainframe to a workstation.

The ADDE command IMGCOPY may be used in place of SENAA. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Formats** 

SENAA sarea darea locate y-coord x-coord mag line ele [keywords] SENAA sarea darea locate station mag line ele [keywords]

**Parameters** 

source area number of the data (no default) sarea

destination area number for the data (no default) darea

coordinate type for loading images; use one of these locate

coordinate systems (no default):

E earth

image

followed by one of these locations:

U upper-left corner

center C

D lower-right corner

y-coord y-axis coordinate (default=first line)

x-coord x-axis coordinate (default=first element)

station ID, e.g., MSN, DSM, 2C2, preceded by EU, EC or ED station

blowup or blowdown factor of the image (default=1) mag

line number of lines in darea (default is workstation dependent)

number of elements in darea (default is workstation dependent) ele

**Keywords** 

ASIZE= ALL moves the entire area including all bands and the documentation section; specify only sarea and darea when using ASIZE=ALL; do not use any other keywords with this option

BAND= band number, the range is 1 to 32; command LA lists bands higher than 9 as A, B, C, etc.; they must be entered as integer, i.e., A=10, B=11, etc. (default=8 for GOES IR, 4 for POES) ALL moves all bands if subsecting a multibanded area; do not use STYPE=VISR with this option

**EMAG**= element only blowup or blowdown factor (default=1)

LMAG= line only blowup or blowdown factor (default=1)

MODE= PACK sends data in compressed form

UNPACK sends data in uncompressed form

(default=PACK for asynchronous connections unless sending 2-byte data;

otherwise, default=UNPACK)

PAKSIZ= number of bits per pixel to send when packing data,

6 or 8; see the Remarks (default=8)

STYPE= VISR reduces two-byte data to one-byte data; see the

Remarks

#### Remarks

The Z column in the mainframe area directory is the number of bytes per pixel in the area. Visible data is usually 1-byte; most IR data is 2-byte. The 2-byte data is usually a raw value which can be operated on with calibration coefficients to convert the data to radiance, temperature or brightness. STYPE=VISR converts the original data to brightness data. Do not use STYPE=VISR with ASIZE=ALL or BAND=ALL.

SENAA can extract single bands from multibanded data and retain full calibration when the area is sent to the workstation. The workstation must be running version 5.0 or later. Mainframe to mainframe transfers require sending all bands (BAND=ALL) to retain the calibration. Multibyte data must be sent in uncompressed form.

When sending single-byte data, you can reduce the transmission time by specifying PAKSIZ=6. SENAA ignores the two bits that are not useful for image display. IR data requires all eight bits of data.

To retain the line header information stored in the documentation section of an area, you must copy the entire area with ASIZE=ALL.

#### **Examples**

#### SENAA 101 1 EC MSN

This entry transfers area 101 from the mainframe to workstation area 1. The image, with earth coordinates, is centered on Madison, Wisconsin.

#### SENAA 109 2 EC 43 89 X 350 640 STYPE=VISR

This entry transfers IR area 109 from the mainframe to workstation area 2. The image, with earth coordinates, is centered over Madison, Wisconsin, and is 350 lines by 640 elements. STYPE=VISR reduces the 2-byte data to 1-byte data. This speeds up the transfer, but the resulting area will not contain radiance information from the mainframe area.

### SEP

Sends the most recent image from the mainframe to a workstation or remote host via command SENAA.

The ADDE command IMGCOPY may be used in place of SEP.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

#### **Formats**

SEP barea earea darea locate y-coord x-coord mag line ele [keywords] SEP barea earea darea locate station mag line ele [keywords]

#### **Parameters**

barea beginning area number to search (no default)

earea ending area number to search (default=barea)

darea destination area number

locate coordinate type for loading images; use one of these

coordinate systems (no default):

A area

E earth

I image

T TV

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

optionally followed by:

S smooths data; this works on visible and IR data during a blowup of the image

y-coord y-axis coordinate (default=first element)

x-coord x-axis coordinate (default=first line)

station 3-letter station ID, e.g., MSN, DSM; must be preceded by

EU, EC or ED

mag blowup or blowdown factor of the image (default=1)

line number of lines in darea (default is workstation

dependent)

ele number of elements in darea (default is workstation dependent)

Keywords

ASIZE= ALL moves the entire area including all bands; specify

only barea and earea when using ASIZE=ALL; do not use any other keywords with this option

BAND= band number to move, the range is 1 to 32; command LA

will list bands higher than 9 as A, B, C, etc.; they must be entered as integer, that is, A=10, B=11, etc. (default=8

for GOES IR, 1 for POES)

ALL= moves all bands if subsecting a multibanded area;

do not use with keyword STYPE=VISR

CAL= calibration coefficient (default=1)

CYCLE= num inc places the selected area into a circular queue of

destination areas beginning with darea, consisting of the *num* number of areas (default *num*=0 meaning no queue; default *inc*=1:00

meaning a 1-hour increment when num is not

equal to zero)

DAY= selects areas on this day only, YYDDD

MODE= NONE moves a copy of the data to darea but doesn't

send it

PACK packed data

UNPACK unpacked data

AUTO packed data if remote or background, unpacked

if local (default)

PAKSIZ= data compaction resolution (default=8)

RTIME= beg end beginning and ending minute range (MM) for

selecting an area with the image time for the current hour; an area is selected if the image time falls between the minute range specified for the current hour; if multiple areas have image times falling within the range, the first area is selected; RTIME values override TIME

values

STYPE= VISR reduces 2-byte data to 1-byte; see the Remarks

TIME= beg end selects an area within the time window specified

above, HH:MM:SS

#### Remarks

Command SEP, like command SEQ, is most useful when used with the scheduler to transfer the most recent satellite data from a mainframe to another mainframe or workstation.

Use keyword CYCLE with the scheduler to copy the most recent McIDAS-MVS area to a loop of areas on the workstation. The beginning area in the loop is specified with *darea*; the number of areas in the loop is specified with keyword CYCLE.

When using keyword CYCLE, the following formula determines which area in the workstation's loop the most recent McIDAS-MVS area is copied to:

(modulus (time/inc, num)) + darea

where *time* is the image time of the area, *inc* and *num* are the values specified in keyword CYCLE, and *darea* is the value specified in the *darea* positional parameter.

For example, if the command:

#### SEP 101 104 1 EC DCA CYCLE=5 1:00

is scheduled to run once an hour, the 13:00 UTC McIDAS-MVS area is copied to workstation area 4, since time=13:0, inc=1.0, num=5, and darea=1 (13.0÷1.0=13; 13÷5=2, with a remainder 3; 3 + 1=4). The 14:00 UTC area is copied to area 5, the 15:00 UTC area is copied to area 1, etc.

If a similar SEP command is scheduled to run every half-hour, but CYCLE=6 00:30 and darea is 11, the 20:00 UTC McIDAS-MVS area is copied to workstation area 15, since time=20.0, inc=0.5, num=6 and darea=11 (20.0÷.5=40; 40÷6=6 with a remainder of 4, 4+11=15). The 20:30 UTC area is copied to area 16, the 21:00 UTC area is copied to area 11, etc.

Keywords TIME and RTIME identify an area to send. Use them to specify a time range that must be met for the area copy to occur. This is especially useful for choosing the desired area when new areas are received frequently, such as GOES images during a RISOP schedule. These keywords also allow you to spread out the scheduled area copies so scheduler activity is more evenly distributed throughout the hour.

Keyword STYPE=VISR converts original data to brightness (1-byte) data. Do not use STYPE=VISR with BAND=ALL.

See Also

See commands SENAA, AA and SEQ in this chapter.

#### **Examples**

#### SEP 101 104 968 ED

This entry sends the most recent data from areas 101 to 104 into area 968, positioned in the lower-right corner.

SEP 109 112 5000 EC MIA 2 CYCLE=10 00:30 RTIME=30 35 This entry searches areas 109 to 112 for an area with an image time falling between 30 and 35 minutes after the current hour. The first area that matches these criteria is sent (via SENAA) to the next available area within area range 5000 to 5010 that follows the 30-minute image time increment set with RTIME. It is centered at Miami, Florida, with a 2x blowup.

#### SEP 305 312 1 EC 43 75 X 480 640 CYCLE=7 X

This entry sends the most recent data from areas 305 to 312 into the next available area in a seven-area circular queue of destination areas starting with area 1. The areas sent to the workstation are centered at coordinates 43° N and 75° W and are limited to a size of 480 lines by 640 elements.

Revised 6/95 4-45

### SEQ

Updates an image frame loop.

The ADDE command IMGDISP may be used in place of SEQ.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

#### **Formats**

SEQ barea earea bframe eframe locate y-coord x-coord mag [keywords] SEQ barea earea bframe eframe locate station mag [keywords]

#### Parameters

barea beginning area number to search

earea ending area number to search

bframe beginning image frame number to search

eframe ending image frame number to search

locate coordinate type for loading images (default=AU, meaning the area coordinates are displayed with the upper-left corner line and element); use one of these coordinate systems:

A area

E earth

I image

T TV

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

optionally followed by:

R uses the current enhancement table set up by command IS

0 to 8 uses this enhancement table number set up by command IS

y-coord y-axis coordinate (default=upper-left corner)

x-coord x-axis coordinate (default=upper-left corner)

station 3-letter station ID, e.g., MSN, DSM; must be preceded by EU, EC or ED

mag blowup or blowdown factor of the image (default=1)

#### Keywords

BAND= band number, the range is 1 to 32; command LA will list bands higher than 9 as A, B, C, etc.; they must be entered as integer, that is, A=10, B=11, etc. (default=8 for VAS channel, 4 for AVHRR)

CAL= QTIR calibration module name; use QTIR for a fast POES load (default=from area directory); the first calibration is used for the entire image;

the area is unaffected

OPT= ALL reloads all image frames

RTIME= beg end beginning and ending minute range (MM)
for selecting an area with the image time for the
current hour; an area is selected if the image
time falls between the minute range specified
for the current hour; if multiple areas have
image times falling within the range, the first

values

 $\textbf{TEST=} \qquad \qquad \textbf{lists the DF commands that update the}$ 

sequence without running them

area is selected; RTIME values override TIME

TIME= beg end selects an area within the time window specified

above, HH:MM:SS

#### Remarks

SEQ displays real-time images. Areas are not copied into new areas, they are only displayed on image frames. To copy areas and display them, use command MOVIT.

SEQ locates the most recent area in the *barea* and *earea* range and displays it on the image frame loop. The single image frame displayed is selected by determining which existing frame within the *bframe* and *eframe* range displays the most recent image. Then the new image is displayed on the next frame.

Keywords TIME and RTIME are useful for identifying an image to display. They allow you to specify a time range that must be met for the image display to occur. This is especially useful for choosing the desired image when new images are being received frequently, such as GOES images during a RISOP schedule. These keywords also allow you to spread out scheduled image loads so scheduler activity is more evenly distributed throughout the hour.

#### Examples

#### SEQ 100 104 1 4

mage display to occur. This is especially useful for choosing the desired

This entry searches areas 100 to 104 and image frames 1 to 4 for the most recent time and displays the most recent area on the frame following the most recent image in frames 1 to 4.

#### SEQ 100 104 1 4 EC 36 90 -4 OPT=ALL

This entry searches areas 100 to 104 and image frames 1 to 4 for the most recent time. At earth center coordinates 36° N and 90° W, with a 4x blowdown, it displays all image frames arranged in a time series.

#### SEQ 109 112 10 20 EC HUT -2 RTIME=00 05

This entry searches areas 109 to 112 for an area with an image time falling between 0 minutes and 5 minutes after the current hour. The first area that matches these criteria is displayed and centered at Hutchinson, Kansas, with a 2x blowdown, on the frame between 10 and 20 that follows the frame displaying the most recent image.

## **SEQG**

Updates an image and graphics frame loop.

Formats SEQG barea earea bframe eframe locate y-coord x-coord mag [keywords] "command

SEQG barea earea bframe eframe locate station mag [keywords] "command

Parameters beginning area number searched

earea ending area number searched

bframe beginning image frame number searched

eframe ending image frame number searched

locate coordinate type for loading images (default=AU, meaning the area coordinates are displayed with the upper-left corner line and element); use one of these coordinate systems:

> A area

B sandy and the McLDAS-X and the earth

vd asstruvrevo ed vem mas andmer I ad t image

followed by one of these locations:

U upper-left corner

C center

D lower-right corner

optionally followed by:

uses the current enhancement table set up by the

IS command

0 to 8 uses this enhancement table number set up by the

IS command

y-coord y-axis coordinate (default=upper-left corner)

x-axis coordinate (default=upper-left corner) x-coord

station 3-letter station ID e.g., MSN, DSM; must be preceded by

EU, EC or ED

blowup or blowdown factor of the image (default=1) mag

command graphics command to update the graphics frames

#### Keywords

BAND= band number, the range is 1 to 32; command LA will list bands higher than 9 as A, B, C, etc.; they must be

entered as integer, that is, A=10, B=11, etc. (default=8

for VAS channel, 4 for AVHRR)

CAL= QTIR calibration module name; use QTIR for a fast

POES load (default=from the area directory); the first calibration is used for the entire image;

the area is unaffected

OPT= ALL displays all frames

#### Remarks

SEQG displays real-time images with graphics overlays. Areas are not copied into new areas, they are only displayed on image frames. To copy areas and display them, use command MOVIT.

SEQG locates the most recent area in the *barea* and *earea* range and displays it on the image frame loop. The single image frame displayed is selected by determining which existing frame within the *bframe* and *eframe* range displays the most recent image. Then the new image and graphics are displayed on the next frames.

Use keyword OPT=ALL to display all image frames.

On workstations with embedded graphics (VGA, McIDAS-X and the briefing frames on a WWW), the graphics sent may be overwritten by the images displayed.

SEQG places graphics on the graphics frame number corresponding to the image frame. That is, an image on frame 5 will have its graphics displayed on graphics frame 5.

#### **Examples**

#### SEQG 110 115 2 10

This entry searches areas 110 to 115 and image frames 2 to 10 for the most recent time and displays the most recent image on the image frame following the latest displayed image frame, using the upper-left area coordinates.

SEQG 105 108 1 4 EC 43 89 OPT=ALL "MAP; SP WX SAT This entry displays areas 105 to 108 on TV frames 1 to 4 from the earliest to most recent, earth centered at 43° N and 89° W. It plots map and surface data on corresponding graphics frames 1 to 4.

## **SETLUP**

Defines frame bounds from loop parameters.

**Format** 

SETLUP loop

**Parameter** 

loop number of a loop defined with the LOOP command; the range is 1 to 9

Remarks

SETLUP defines the following parameters from the LOOP command:

- frame loop bounds from the loop parameter; graphics loop bounds from the loop number
- dwell rates for the loop
  - enhancement table whose number is the loop number

Use this command to define executable strings for different loops. Then you can access these image loops by simply typing the defined keystroke.

The enhancement must be stored on the workstation if SETLUP is run from it.

**Examples** 

TE 1 "SETLUP 1

TE 3 "SETLUP 3

TE 4 "SETLUP 4

TE 6 "SETLUP 6

These entries define string table values 1, 3, 4 and 6 to loop frames.

Typing 1, 3, 4 or 6 will loop the images defined for loop number 1, 3, etc.

### **SVGA**

### Generates an area from virtual graphics.

**Format** 

SVGA virt area width [keywords]

Parameters

virtual graphics number; the range is 1 to 1024

area

virt

area number to put graphics in; must be 500 lines by 640

elements

width

graphics line width, in pixels (default=1)

Keywords

LEV=

lev1...7 brightness values for graphics levels; the

range is 0 to 255 (default=32 64 96 128 160

192 224)

TERM=

terminal number where the virtual graphic is stored

(default=current)

Remarks

Create virtual graphics by appending the keyword VIRT to any graphics

command.

SVGA adds virtual graphics to an existing area, so maps and other

graphics can be permanently added to an image.

Examples

SVGA 101 6848 2

This entry writes virtual graphic 101 into area 6848, with a line width of two pixels. Graphics color level 1 is transformed into a brightness value

of 32; level 2 becomes a brightness value of 64, etc.

SVGA 114 6852 LEV=255 200 150

This entry writes virtual graphic 114 into area 6852, with a line width of one pixel. Level 1 has a value of 255, level 2 of 200, level 3 of 150. Other

levels retain their default values.

SVGA 250 5265

This entry writes virtual graphic 250 into area 5265 with a line width of

one pixel.

### **TIRCAL**

Calibrates POES images.

**Format** 

TIRCAL area [keyword]

**Parameter** 

area POES area number to calibrate

Keyword

CAL= QUICK

applies quick calibration to the area

FULL

fully calibrates the area (default)

#### Remarks

### Caution! Do not run TIRCAL on TIP data.

The FULL option generates a calibration for each group of five image lines through the entire area. The QUICK calibration uses the average calibration for the first five good lines and applies that calibration to the entire area. The quick calibrated data shows only slight differences visually. Do not rely on the quick calibration for scientific purposes. Temperature differences of 2-3 degrees along with radiance differences have been seen at the end of GAC areas.

If commands TPREP and MULTIR are run, you do not have to run TIRCAL as they call it.

### **TPREP**

Calibrates and navigates POES images.

**Format** 

TPREP area [keyword]

**Parameter** 

area POES area number to calibrate and navigate

**Keyword** 

CAL= QUICK applies quick calibration to the area
FULL fully calibrates the area (default)

Remarks

Caution! Do not run TPREP on TIP data.

TPREP is a macro that calibrates and creates a navigation codicil for real-time POES images using TIRCAL and NK, respectively. If a navigation codicil is not created, use command NK with a day where navigation is available. Use NVU LIST to list the available days.

Schedule the command MULTIR on your event scheduler to automatically calibrate and navigate each POES image after it is ingested.

The FULL option generates a calibration for each group of five lines through the entire area. The QUICK calibration uses the average calibration for the first five good lines and applies that calibration to the entire area. The quick calibrated data shows only slight differences visually. Do not rely on the quick calibration for scientific purposes. Temperature differences of 2-3 degrees along with radiance differences have been seen at the end of GAC areas.

# **Chapter 5. Derived Image Products**

AAMAP	Remaps an area into a Mercator or polar stereographic projection 5-1
AVGI	Reduces image resolution by averaging 5-3
CLDMAK	Generates and displays stereo perspective cloud images 5-4
DF3D	Displays an area for false stereo view
<b>IMGPRO</b>	Generates derived satellite imagery products 5-9
IMSCAT	Displays a scatter plot of two images' data 5-13
MA	Modifies an area 5-14
MC	Combines areas
REMAP	Remaps an area into a different projection 5-22
STRDF	Displays images for stereo perspective display 5-24
TOPO3D	Generates a 3-D topographical map
TRNIMG	Translates images from one area to another 5-26

Issued 4/93

## **AAMAP**

Remaps an area into a Mercator or polar stereographic projection.

Format	AAMAP sarea darea frame projection clat clon res line ele [keywords]			
Parameters	sarea	source area number of the data		
	darea	destination area number; must be different than sarea		
	frame	image frame number for display; the data in <i>darea</i> is displayed on this frame (default=does not display the image)		
	projection	MERC remaps to a Mercator projection PS remaps to a polar stereographic projection		
	clat	center latitude		
	clon	center longitude		
	res	remapped image resolution in kilometers (default=1)		
	line	number of lines in darea (default=number of lines in frame)		
	ele	number of elements in <i>darea</i> (default=number of elements in <i>frame</i> )		
Keywords	ASIZE=	ALL creates a destination area to contain the entire source area (default=number of lines and elements in <i>frame</i> )		
	BAND=	band number for multiband sarea		
	SPLINE=	spline size (default=20)		

#### Remarks

AAMAP remaps any navigated image to a Mercator or polar stereographic projection.

Use keyword SPLINE to improve the quality of the remapped image, especially along the edges. Choosing a spline size smaller than the default of 20 may increase the quality, but will also increase the time and cost of running the AAMAP command.

### **Examples**

#### AAMAP 4960 6848 2 MERC 35 90 4

This entry remaps area 4960 into a Mercator projection centered on 35°N and 90°W. The new image, which has a resolution of 4 km, is stored in area 6848 and displayed on image frame 2.

#### AAMAP 7500 7501 5 PS 70 140 SPLINE=5

This entry remaps area 7500 into a polar stereographic projection with a spline size of 5 centered on 70°N and 140°W. The new image, which has a 1 km resolution, is stored in area 7501 and displayed on image frame 5.

#### AAMAP 2001 9000 X PS 44 72

in clared (defection, unibur of

This entry remaps area 2001 into a polar stereographic projection centering it on 44°N and 72°W. It stores the resulting image in area 9000, but does not display it.

### **AVGI**

Reduces image resolution by averaging.

**Format** 

AVGI sarea darea lres eres [keyword]

**Parameters** 

sarea source area to average

darea destination area of the averaged data

lres number indicating the resolution reduction for lines

(default=1)

res number indicating the resolution reduction for elements

(default=lres)

**Keyword** 

BAND= band number from multibanded areas (default=lowest

numbered band)

Remarks

The area size cannot exceed 10,000 elements.

**Examples** 

AVGI 2112 1288

This entry averages area 2112 by one line and element and places the

averaged data in area 1288.

AVGI 10 20 4

This entry blows down area 10 four times by averaging pixel values.

The new area number is 20.

### **CLDMAK**

Generates and displays stereo perspective cloud images over a topographical map.

#### **Format**

CLDMAK irarea visarea darea frame [keywords]

#### **Parameters**

irarea area number of the IR image

visarea area number of the corresponding visible image

darea destination area number for the topographical map and stereo perspective images; four consecutive areas are used

unless you specify keyword TOPO

frame frame number on which the left eye view of the perspective

image is displayed; the right eye view is displayed on the

opposite frame

### Keywords

LAT= south north latitude extents (default=30.0 40.0)

LON= east west longitude extents (default=80.0 90.0)

TOPO= first area number of the areas containing the topographical

map; should be the value of darea in a previous

CLDMAK command

#### Remarks

CLDMAK uses IR temperature and a visible image to create a stereo perspective cloud image over a topographical map. The right and left eye views of the map are stored in the first 2 areas used; the right and left eye views of the cloud image are stored in the next 2 areas. The areas are loaded onto the specified image frame and its opposite. One-half of the total number of frames is color enhanced red; the other frames are color enhanced green. Use the N key to combine the images and enhancements, thereby creating a display which appears to be in stereo when viewed with red-green glasses.

The containing box used in the display is 24 km high.

#### **Examples**

#### CLDMAK 112 107 11210 7

me me evodo brus fil de might

This entry generates a stereo perspective cloud image from the IR image in area 112 and the visible image in area 107. The image and map are displayed on frame 7 and its opposite. The geographic area covered is the southeast central USA.

### CLDMAK 109 105 6900 1 LAT=35 45 LON=75 85

This entry uses the IR image in area 109 and the visible image in area 105 to generate a stereo perspective cloud image. The image is displayed over a topographical map on frame 1 and its opposite. The geographical extents are 35° to 45°N latitude and 75° to 85°W longitude.

CLDMAK 110 106 6902 2 LAT=35 45 LON=75 85 TOPO=6900 This entry uses the IR image in area 110 and the visible image in area 105 to generate a stereo perspective cloud image. The topographical map generated in the first example is used. This image is displayed on frame 2 and its opposite. The two sets of images created in these examples can be animated using the L key.

### DF3D

Displays an area for false stereo view.

#### **Formats**

DF3D area frame locate y-coord x-coord mag t1 t2 t3 t4 tref shift range tunits [keywords]

DF3D area frame locate station mag t1 t2 t3 t4 tref shift range tunits [keywords]

#### **Parameters**

area

area number of the visible image; must have the same resolution as the IR area

frame

image frame number for display

OPP displays the image on the frame opposite the current frame

locate

type of coordinates the TV load will use as a reference point; (default=AUS, meaning the area coordinates are displayed with the upper-left corner line and element; the image is shifted left and above the screen); use one of these coordinate systems:

A area
E earth
I image

T TV

followed by one of these locations:

C center

D lower-right corner

U upper-left corner

followed by one of these shifting factors:

H split screen, view images side-by-side

Q right shift and above screen

S left shift and above screen

V right shift and below screen

W left shift and below screen

y-coord y-axis coordinate (default=0)

x-coord x-axis coordinate (default=0)

station ID, e.g., MSN, DSM, 2C2; it must be preceded by EU, EC or ED

mag	image blowup or blowdown factor (default=1) SQUA gives pixels a square aspect ratio				
t1	low temperature (default=164)				
<i>t</i> 2	high temperature (default=164)				
<i>t</i> 3	low temperature of nonlinear shift (default=t1)				
t4	high temperature of nonlinear shift (default=t2)				
tref	reference temperature level of the TV screen; overrides stereo geometry key if used (default=none)				
shift	maximum left/right shift (default=32)				
range	percent of shift allocated to nonlinear region (default=50)				
tunits	F he M he P pr T te	mperature in Celsius (default) eight in feet eight in meters ressure level in mb mperature in Kelvin neta surface in Kelvin			
ANN=	bkgrd char	gray scale values for the annotation line's background and characters located at the bottom of the screen (default=32 160)			

#### **Keywords**

BAND= area band number; the range is 1 to 9; command LA will list bands higher than 9 as A, B, C, etc.; they must be entered as integer, that is, A=10, B=11, etc. (default=8 for GOES IR, 1 for POES)

EMAG= element only blowup or blowdown factor

IR= area number for the IR data

LMAG= line only blowup or blowdown factor

#### Remarks

This command works only on tower workstations.

Display the shifted image generated by DF3D on the frame opposite the visible image. You must have an IR area on disk that corresponds to the visible image time and resolution. To display the false stereo red and green coloring, execute the following two commands:

Type: ET NOR
Press: Enter
Type: N
Press: Enter

Now look through the red and green glasses to see stereo. If the image does not appear in stereo, try flipping your glasses.

The coordinates for displaying images are listed below.

Location	Y-coordinate	X-coordinate	Format
E	latitude	longitude	DDD:MM:SS,
Han Line of		magnetic affirm	DDD.fraction
			or station ID
I	line	element	0 to 5 digits
T	raster	pictel	0 to 3 digits
A	area line	area element	0 to 5 digits

### **Examples**

#### DF3D 1288 20

This entry displays area 1288 on image frame 20 shifted for stereo view. The image is loaded from the upper-left corner of the area and shifts the image a maximum of 32 pixels to the left. The ground is at screen level. To view, wear the red lense over your right eye.

Use the commands below to display a false stereo image.

#### **DF 106 1 EC MSN**

This entry loads visible area 106 into TV frame 1 at earth center MSN. Make sure the image resolutions of the visible and IR data match.

#### DF3D 101 OPP ECS MSN

This entry loads a stereo image with left shift on the frame opposite the visible image.

#### ET NOR

This entry generates a red and green color enhancement table.

#### N

This entry overlays the imagery in red-green stereo. View the display with red-green glasses; place the red lens over your right eye.

### **IMGPRO**

Generates derived satellite imagery products.

The ADDE command IMGOPER may be used in place of IMGPRO. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

_			
	~	m	at
_		•	aı

IMGPRO sarea darea [keywords] "text

**Parameters** 

source area number; keyword AREA overrides this entry

(no default)

darea

sarea

destination area number (no default)

"text

text to attach to the destination area directory;

32 characters maximum

**Keywords** 

AREA=

single or multiple source area numbers (default=sarea)

BAND=

single or multiple band numbers (default=lowest band

number)

COEF=

coefficients for each term in the equation (default=+1.0)

CONST=

constant for the equation (default=0.0)

FACTOR=

internal source and destination scaling factors

(default=1.0; if UNIT=TEMP, default=10.0)

FORM=

ADD

adds each term in the equation (default)

MULT

multiplies each term in the equation

FUNC=

allows a transcendental function operation on the output of the additive or multiplicative equation, i.e.,

LOG, ALOG, LN, EXP (default=NONE)

LLMT=

lower limit thresholds, inclusive, for each term in the

equation (no default)

NAME=

derived imagery product name; up to 4 characters

(default=PROD)

OFF=

offsets for each term in the equation (default=0.0)

POW= powers for each term in the equation (default=+1.0)

QA =YES quits the output area if it already exists

NO does not quit the output area (default)

SCALE= prodlo prodhi britlo brithi minimum and maximum product and brightness values for the calibration (default=none for the product values;

0 255 for the brightness counts)

SIGN= plus the band values for each term in the

equation (default)

M minus the band values

ULMT= upper limit thresholds, inclusive, for each term in the

equation (no default)

UNIT= calibration types for each term in the equation

(default=TEMP)

ZERO= DATA assigns zero pixel values as data and includes

them in the analysis

MISS assigns zero pixel values as missing and excludes them from the analysis (default)

a nonzero numeric value identifies that pixel value to

represent the missing value flag

Remarks

IMGPRO produces simple and complex derived satellite imagery. Each term in the equation can be defined independently. Although the defaults allow for a minimum number of simple mathematical manipulations such as band differencing, averaging or ratioing, the equation specification can be as complicated as you like. The equation formats are:

Output = Constant + FORMat [ Coef\*(Off+Sign\*Band)\*\*Pow ] Output = FUNCtion [ Output ]

Some keyword defaults are context sensitive. If more than one band or input area is processed, the default for the equation keywords is the first value specified for the keyword (see the examples).

When using IMGPRO on POES temperature data, specify FACTOR=1 for each input area.

The derived imagery product is always written into band 1 in the output

IMGPRO has no line limit, but has a 4000 element maximum.

You can specify a maximum of 12 terms for an equation. A maximum of six areas can be opened for any individual job.

You can list bands in any order, but the order must be maintained consistently for all keywords.

By creating a new calibration codicil with its own name (calibration type), you can display the derived imagery product in its appropriate and physically meaningful units. That is, when you access the area information with the D key, the true values are listed under a column heading with the product name. You can use this product name as a parameter in the OD L command to list the derived values contained within the cursor. Use the product name just like any other standard calibration types such as BRIT, TEMP, RAW or RAD.

All areas have the same size, central location and resolution. If this is not the case, use the REMAP, AAMAP or AA command.

Zero pixel values can be treated as missing value codes or real data values. Nonzero numeric values can be substituted to specify a different missing value code other than zero.

#### **Examples**

#### IMGPRO 310 445 SCALE=200 250

This entry processes brightness temperatures from the lowest numbered band in area 310 using a scaling factor of 10. It attaches a new calibration codicil to area 445, linearly stretching the range 200 to 250 between 0 and 255. It also copies the navigation codicil in area 310 into the area 445 navigation codicil and rewrites the source area data with a new calibration codicil into the destination area. No mathematical operations are performed.

IMGPRO 2048 2070 BAND=4 FACTOR=1 SCALE=200 300 This entry writes the band 4 brightness temperatures from area 2048 (which is a multibanded POES image) into area 2070 and defines a new calibration, linearly stretching the temperature range 200 to 300 between 0 and 255. The new calibration type is PROD.

# IMGPRO X 2070 BAND=8 AREA=2048 2049 2050 2051 NAME=AVG COEF=0.25 SCALE=200 300 0 255

This entry calculates the average band 8 brightness temperature from four different areas and writes it into area 2070. It has a calibration type name of AVG and a linear stretch for the temperature range 200 to 300 degrees between 0 and 255 brightness counts.

### IMGPRO 2048 2070 FORM=M BAND=7 8 POW=1 -1 NAME=RATI SCALE=0.5 1.5 UNIT=BRIT FACTOR=X X 100

This entry calculates the ratio of band 7 brightness counts to band 8 brightness counts from area 2048 and writes it to area 2070 scaled up by a factor of 100. That is, the brightness ratios are saved to the hundredths decimal place. It is calibrated for a range of 0.5 to 1.5 to linearly stretch between 0 and 255.

### IMGPRO 2048 2070 BAND=7 8 NAME=DIFF SIGN=X M SCALE=-10 10 UNIT=TEMP TEMP FACTOR=10 10 10 LLMT=230 ULMT=270

This entry calculates the difference between band 7 and band 8 brightness temperatures warmer than 230° and cooler than 270° from area 2048 and writes it to area 2070 scaled up by a factor of 10. That is, the temperature differences are saved to the nearest tenth of a degree. It is calibrated for a range of -10° to +10° to linearly stretch between 0 and 255. The calibration is named DIFF.

### IMGPRO X 2070 BAND=8 AREA=2048 COEF=0.0118 OFF=267 POW=1.75 SIGN=M CONST=-1.117 ULMT=253.2 NAME=RAIN SCALE=0 10

This entry applies a power law regression algorithm for estimating rain rate to band 8 GOES temperatures. This generates a rain rate image in area 2048 in units of 0.1mm. The rain rate can be accessed using the calibration type (i.e., product name) RAIN.

### **IMSCAT**

Displays a scatter plot of two images' data.

**Format** 

IMSCAT image1 image2 [keywords]

**Parameters** 

image1 x-axis image number (default=current frame)

image2

y-axis image number (default=opposite frame)

Keywords

COLOR= graphics color level of the plot (default=3)

XP=

min max div sdiv x-axis plotting parameters

min minimum brightness value on the axis

max maximum brightness value on the axis

div number of labeled tic marks

sdiv number of tic marks between the labels

(default=0 260 10 4)

YP=

min max div sdiv y-axis plotting parameters

Remarks

IMSCAT plots a graph of *image1* vs. *image2* on the current graphics frame. The cursor bounds define the plotted data.

**Examples** 

#### **IMSCAT**

and data; you must specify the band when

This entry makes a scatter plot of the current image versus the opposite image brightness values using the data within the cursor. It is plotted in graphics color level 3. The x and y axes range from 0 to 260.

#### IMSCAT COLOR=5

This entry plots the current vs. the opposite image data in graphics color level 5 on the current graphics frame, using the default values for the x and y axes labels.

#### IMSCAT 10 11 XP=100 220 10 YP=170 200 15 1

This entry plots image 10 vs. image 11 data. The x axis labels range from 100 to 220 with 10 major tic marks; the y axis labels range from 170 to 200 with 15 major tic marks and one subdivision between each major tic.

### MA

Modifies an area.

The ADDE command IMGOPER may be used in place of MA with options ADD, C, FLX, LIN, SCA, and TEM. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

MA sarea darea frame option p1 p2 p3 p4 [keyword]

**Parameters** 

sarea source area number

darea destination area number

frame image frame number to display modified area

(default=area is not displayed)

option A automatic enhancement

C contrast stretching

E lookup table enhancement

F data fill

G gradient

H high pass filter

L low pass filter

N shot noise filter

S digital stretching

ADD adds a parameter to the data

BAD removes buffer flakes and bad lines; places the

average in all bad lines

CLN removes buffer flakes and bad lines; places zeros

in the bad lines

FLX converts the IR counts to flux in W/M\*M/2

LIN converts the square root digitization to a linear scale

SCA scales the data

TEM converts the IR counts to Kelvin-100

p1-p4 these parameters vary with the selected option; see the

Remarks below

Keyword

BAND= band number to process; defaults to the single band when

using single band data; you must specify the band when

using multiband data

#### Remarks

The MA command modifies the brightness values in an area by applying a data operator, transferring the result to another area, and displaying the data on an image frame. Sarea specifies the input area; darea specifies the output area. If darea is zero, the modified area is written into sarea. Frame specifies the frame number if the area is to be displayed following modification; the default is not to load.

The maximum number of elements in a line is 5000.

Option indicates one of the data operators which may require the use of p1 to p4 for control parameters. Each option is further described below.

#### A

A means automatic enhancement. It makes a histogram of the occurrence of the values for the input area. The output area is an enhancement of the input area where the range of digital values is proportional to the occurrence of the histogram values. That is, if there are many digital values in a small range of brightnesses on the input area, they are stretched to a wider range of brightnesses in the enhanced output. The values p1 and p2 are ignored.

#### ADD

This option adds the constant p1 to the digital data. J(I)=J(I)+p1. The overflow is set to 255; the underflow is set to 0. p1=constant added to the data; -255 < p1 < 255 (no default)

#### BAD

This option locates bad lines and replaces them with the average of the lines on either side. It also removes buffer flakes with a shot noise filter. The program finds bad lines by correlating each line with the last good line. Lines with averages of 255 or 0 are automatically defined as bad. p1=shot noise window; 0 < p1 < 255 (default=40) p2=first good line of the area (default=1) p3=last line to be cleaned up (default= last line) p4=correlation criteria between lines (default=20)

C

C is an enhancement that stretches the values between p1 and p2 to range between 0 and 255.

p1=lower digital value (default=8)

p2=upper digital value (default=240)

- positive stretch
- negative stretch (p1=255, p2=0)
- compress stretch, (p1=-300, p2=600)
- real numbers (p1=26.8, p2=150.2)

#### CLN

CLN performs the same function as the BAD option, except that zeros replace the bad lines if there is more than one bad line in a row. The maximum number of elements in a line is 1680.

p1=shot noise window; 0 < p1 < 255 (default=40)

p2=first good line (default=1)

p3=last line to be cleaned up (default=last line)

p4=correlation criteria between lines (default=20)

#### Ε

This option applies the enhancement from the video lookup tables to the digital data. pl = B(blue, default), G(green) or R(red) lookup table.

F

This option fills in the holes along a line. The holes have values between p1 and p2. The average value of the data on either side of the hole is placed in the hole.

p1=lower value that defines the hole; 0 < p1 < 255 (default=0) p2=upper value that defines the hole; 0 < p2 < 255 (default=0)

#### FLX

FLX converts the infrared image into an image of longwave flux divided by 2 in units of watts/m<sup>2</sup>. The formula is:  $J(I) = 0.543*(5.66x10^{-8})*J(I)^4 + 44.538$ 

G

This option applies a gradient operator (IABS[J(I)] - J[I+1]) along each line. p1 and p2 are not used.

н

This option applies a high pass filter (suppressing low frequency or broad features) along a line.

p1=filter radius; 1 < p1 < 500 (default=50 pixels) p2=filter efficiency; 1 < p2 < 100 (default=100%)

L

This option applies a low pass filter (suppressing high frequency or small features) along a line.

p1=filter radius; 1 < p1 < 500 (default=30 pixels) p2=filter efficiency; 1 < p2 < 100 (default=100%)

#### LIN

This option converts the SMS square root digitization to a linear scale in which the visible image brightness values are proportional to the radiances measured by the satellite. J(I) = P2\*(J[I]\*J[I]/16-p1/4)/3969 p1 = calibration offset; space view (default=8) p2 = scaling factor (default=200)

#### N

This option applies a shot noise filter to remove spikes along a data line. The shot noise pixel is replaced by the average value of the pixels, one to the left and two to the right. p1=shot noise window (default=40 pixels)

S

This option takes an enhancement of the digital data which throws away the lower p1% and upper p2% of the data and stretches the remaining data to fit between 0 and 255.

p1=lower cutoff percentage; 1 < p1 < 100 (default=3) p2=upper cutoff percentage; 1 < p2 < 100 (default=3)

#### SCA

This option scales the data by multiplying by p1. The J(I)\*p1 overflow is set to 255. p1=multiplying factor; it can be an integer or real number (default=1)

#### TEM

This option converts the infrared counts into an image of temperature -100 (in Kelvin -100). p1 and p2 are not used.

#### **Examples**

#### MA 6512 6513 2 CLN

This entry cleans up the data in area 6512, places the new data in area 6513 and displays the new image on frame 2.

#### MA 6513 6514 10 C 150 200

This entry contrast stretches area 6513 into area 6514 displaying the image on frame 10. It stretches digital values 150 to 200 between values 0 and 255.

#### MA 1000 2500 X ADD 100

I O does a pixel-by pixel combination of up to four areas to produce a new

This entry adds the constant 100 to each digital value in area 1000. The destination area is 2500; no image is displayed. Any new values greater than 255 become 255.

#### MA 7384 7385 0 BAD BAND=A

This entry removes buffer flakes and bad lines from BAND A data in area 7384 and places the modified data in area 7385.

# MC

Combines areas.

The ADDE command IMGOPER may be used in place of MC with options ADD, AVE, DIV, MAX, MIN, MPY, RAT, RMS, SUB, and WAV. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

MC sarea1 sarea2 sarea3 sarea4 darea option p1 p2 p3 p4 p5 [keywords]

**Parameters** 

sarea1 ... 4 source area numbers to combine

dareadestination area number to store the combined results;

the area is 1-byte data with VISR calibration

AVE averages the brightness values option

> CLD clouds

COR cloud cores

DIS discriminate

DIV divides images by a constant

MAX saves the maximum brightness values MIN saves the minimum brightness values

MPY multiplies images by a constant

RAT color ratio

RMS root mean square

SPL generates a split screen image SUB subtracts brightness values

WAV weighted average

p1..5 these parameters vary with the selected option; see the

Remarks

Keywords

BAND=

band 1 ... 4 band numbers corresponding to the area

numbers

IMA=

image frame number; displays darea

Remarks

MC does a pixel-by-pixel combination of up to four areas to produce a new output area which has an area directory equal to the directory for the first input area, plus the appropriate message code. All areas must be the same size, centered at the same location, and have the same resolution.

The options available are described below. sarea1, sarea2, sarea3 and sarea4 are the entire source areas. s1, s2, s3 and s4 are individual pixels from sarea1 to 4, respectively. A lowercase s is a pixel from sarea1 to 4; d1 is the pixel value of the destination area.

#### **AVE**

Averages up to 4 areas.

Function:  $d1 = \underline{s1 + s2 + s3 + s4}$ 

p1 and p2 are threshold limits. A pixel is included in the average if p1 < s < p2. (default=0 for p1; 255 for p2)

#### CLD

Creates an area of only clouds (using the minimum brightness composite from the MIN option) in *sarea2* as background brightness. *p1* defines the brightness threshold.

Function: d1=s1 (if s1 > s2 + p2). Otherwise d1=p1. (default=0 for both p1 and p2)

#### COR

Selects cloud cores by comparing the brightness values defined by p1 and p2 and placing the results in darea.

Function: If brightness s1 > p1 and brightness s2 > p2, then d1=p3. Otherwise, d1=p4 (default=0 for p1, p2 and p3; 255 for p4).

#### DIS

Discriminates the values of one area against the values in a second area. Function: d1=p5 if p1 < s1 < p2 and p3 < s2 < p4. Otherwise, d1=s1. (default=0 for p5)

### DIV

Normalizes the area ratio of two areas and, if desired, changes the brightness value. p1 cannot equal zero.

Function: d1=100 \*(s1/s2)\*p1/100+p2

p1 = normalization factor; p2 = factor to increase or decrease the baseline brightness (default=100 for p1; 0 for p2)

#### MAX

Selects the maximum brightness value from up to 4 areas. Function: d1 = MAX(s1, s2, s3, s4). If s1, s2, s3 or  $s4 \ge p1$ , it is ignored. If all values  $\ge p1$ , d1=p2. (default=255 for p1)

#### MIN

Selects the minimum brightness value from up to 4 areas. Function: d1 = MIN(s1, s2, s3, s4). If s1, s2, s3 or  $s4 \le p1$ , it is ignored. If all values  $\le p1$ , d1=p2. (default=0 for p1)

#### MPY

Multiplies two areas together. Function: d1 = (s1 \* s2) + p1(256) (default=0 for p1)

#### **RAT**

Makes color ratios of two areas. Function: d1=(p1\*s1 - p2\*s2)\*p3 + p4 s1+s2(default=1 for p1 and p2; 100 for p3; 0 for p4)


#### **RMS**

Root-mean-square of up to 4 areas. Function:  $d1 = (s1^2 + s2^2 + ...)1/2$ (number of areas)

#### SPL

beet to set benitob estate

Combines two or four areas to make a split image. For two vertically split images, enter: MC sarea1 sarea2 darea SPL p1 p2 (where sarea1 and sarea2 are the area numbers to combine, darea is the destination area of the split image, p1 is an integer whose value exceeds the number of lines in sarea1 and sarea2, and p2 defines the TV element where the split occurs). The left side of sarea1 and the right side of sarea2 comprise the final image. See the diagram below. You may need to do several AA commands to get the desired result.



For 2 horizontally split images, p1 defines the line number where the split occurs and p2 must be larger than either area's line number. The p1 and p2 coordinates define the origin of the new image.

For a 4-way split, enter:

MC sarea1 sarea2 sarea3 sarea4 darea SPL p1 p2 p3 p4 where p1 is the TV line number where the split occurs, p2 is the TV element number where the split occurs and p3 and p4 are integers whose value exceeds the number of lines and elements, respectively, in sarea1 through sarea4. See the figure below.

#### SUB

Subtracts two areas. Function: d1 = (p1\*(s1 - s2)) + p2. (default=1 for p1; 0 for p2)

#### WAV

WAV is the weighted average of up to four areas. p1 must be greater than zero. If p1 and p2 are not specified, the AVE option is used.

Function: 
$$d1=(s1*p1) + (s2*p2)$$
  
 $p1+p2$ 

(default=1 for p1 and p2)

#### **Examples**

#### MC 9 10 95 100 16 AVE IMA=5

This entry averages areas 9, 10, 95 and 100 placing the result in area 16 and displaying it on frame 5.

#### MC 13 6 2 SUB 10

This entry subtracts area 6 from area 13 and stores the results in area 2, but does not display the new image. It stretches the brightness range using pl=10.

#### MC 6512 6513 6520 SPL 1000 300 IMA=10

This entry combines areas 6512 and 6513 into a vertically split image, placing the output in area 6520 and displaying it on frame 10. The source areas are all less than 1000 lines; therefore, the image is vertically split on TV pictel 300.

# REMAP

Remaps an area into a different projection.

**Format** 

REMAP sarea darea spline [keywords]

**Parameters** 

sarea

source area number to remap

darea

destination area number for the remapped image;
darea contains the projection that sarea is remapped

into

spline

spline function (default=20 pixels)

Keywords

BAND=

band number (default=lowest numbered band)

MERGE=

YES mer

merges the data in sarea with the data in darea

NO overwrites the data in darea (default)

SMOOTH=

limb data

provides limb and/or data smoothing

limb

YES for limb smoothing

NO for no limb smoothing (default)

data

YES for data smoothing

NO

for no data smoothing (default)

#### Remarks

The default for REMAP zeros out the destination area before remapping the source area into the new projection. The MERGE=YES keyword does not zero out the destination area. In this case, the source area data overwrites the destination area data. MERGE is useful to combine polar orbiter images.

For REMAP to be successful, the destination area must meet the requirements below. See command CA for more information.

- The destination area must be 1-band (no specific one) and 1-byte data (ZRES=1 and ZSIZ=1). The source area can be 2-byte or 1-byte data.
- The calibration type must be VISR; the source type BRIT.
- The sarea and darea must contain navigation before you can remap images.
- Both the area PREFIX and VALCOD must be zero.

#### See Also

Use command AAMAP to remap an area into a Mercator or polar stereographic projection.

### **Examples**

#### REMAP 1 2

This entry remaps area 1 into area 2 where area 1 is a GOES East image and area 2 is a GOES West image. After execution, area 2 contains the remapped GOES East image.

#### REMAP 710 6000 MERGE=Y BAND=4

This entry remaps the POES data in area 710, band 4, into area 6000, overwriting the area coverage that overlaps.

#### REMAP 50 51 SMOOTH=YES NO

This entry remaps area 50 into area 51, providing a smooth edge on the image in area 51. The remap applies only to the navigable points in area 50. The data is not smoothed.

# **STRDF**

Displays images for stereo perspective display.

**Format** 

STRDF area frame

**Parameters** 

area

displays four areas beginning with area into frame

frame

designates image frame and image frame + 1 and their opposites as the destination for the four TV loads

Remarks

STRDF displays a sequence of 4 areas into 2 image frames and their

opposites for stereo and motion perspective.

**Example** 

STRDF 2000 1

This entry displays areas 2000 to 2003 on image frames 1 and 2 and

their opposites.

# TOPO3D

### Generates a 3-D topographical map.

_		
$\mathbf{r}$	rm	21

TOPO3D area view [keywords]

#### **Parameters**

area number of the area in which to create the topography map; also creates a depth map in area+1

view 1 generates left eye view (default)

-1 generates right eye view

### Keywords

DEPTH= view depth (default=1.0)

DIM= dimming factor of the topographical map; 1 is full

brightness (default=0.8)

HGT= bottom top height extents in meters

(default=0.0 12000.0)

HROT= horizontal rotation angle (default=0.0)

LAT= south north latitude extents (default=20.0 50.0)

LON= east west longitude extents (default=60.0 125.0)

MAP= name of the map outline file from the MAP command

(default=OUTLUSA)

MESH= number of mesh points (default=5000)

VROT= vertical rotation angle (default=0.0)

#### **Examples**

#### TOPO3D 2010

This entry generates a topographical map in area 2010 and a depth map in area 2011 for left eye view.

#### TOPO3D 1100 1 LAT=26 49 LON=75 112

This entry generates a topographical map in area 1100 and a depth map in area 1101 for left eye view. The extents are 26° to 49° North and 75° to 112° West, suitable for use with the default extents of the VAS4D analyses. US boundaries are drawn on the map.

# **TRNIMG**

Translates images from one area to another.

**Format** 

TRNIMG sarea darea time spline [keywords]

**Parameters** 

sarea area number of the source data (no default)

darea

area number of the destination for the remapped image

(no default)

time

forecast time, HH:MM:SS (default=1 hour)

spline

spline function, area pixels (default=10)

**Keywords** 

AREA= dir

dir spd unit

area direction, speed and unit

(default unit=kt)

CELL= dir spd unit

cell direction, speed and unit; the

unit range is in kt (default),

mph, km/hr or mps

STAY=

lat lon radius unit

sets the region; the unit range is

in nmi (default), km or mi

Remarks

Command TRNIMG translates (remaps) image data at a specified speed and direction for a forecast time. It was originally designed for radar data (thus keywords AREA and CELL), but may be extended to

satellite images.

See Also

Command REMAP remaps an area into a satellite projection.

Example

TRNIMG 2076 4013 1:00 AREA=270 15 CELL=225 30 STAY=40 90 20

This entry translates the radar image in area 2076 to area 4013, predicting the location of the echoes 1 hour from the image time. From another source we have determined that the radar area is moving from 270° at 15 kt (AREA=270 15), and the cells are moving from 225° at 30 kt (CELL=225 30). There is a ground clutter area within 20 nmi of the radar at 40°N 90°W that remains stationary (STAY=40 90 20).

# **Chapter 6. Frame Analysis**

AC	Computes area statistics 6-1
AX	Defines the area statistics options 6-2
C	Lists an image frame's directory 6-4
CF	Changes an image frame directory 6-5
COTV	Contours data and produces a 2- or 3-dimensional plot 6-7
CPYPTH	Copies a path to an LW file
CTY	Displays county outlines 6-1
D	Lists the digital area values at the cursor center 6-1
DIST	Finds the distance on a navigated frame 6-1
E	Lists the earth coordinates at the cursor center 6-1
ENH	Displays NESDIS enhancement curves 6-1
ET	Generates enhancements for image frame overlays 6-1
FIND	Locates a city by name and state 6-2
FRONT	Draws a front through path points 6-2
GO	Generates an area statistics outline 6-2
LF	Lists an image frame directory
LP	Displays a line plot of an image line 6-2
LPLOTS	Displays a line plot of an image box 6-2
MAKNAV	Generates a navigation codicil for an area 6-2
MAP	Displays a map and latitude/longitude lines on a graphics frame 6-3
MDOA	Lists area statistics calculations 6-3
OD	Lists the digital data bounded by the cursor 6-3
PATH	Displays a 2-dimensional path for object tracking 6-4
PC	Positions the cursor at a desired point on the frame 6-4
PLAX	Lists satellite parallax at the cursor position 6-4
PO	Restores the position of the area statistics outline 6-4
SEG	Updates a graphics frame loop with the current graphics 6-4
TOWNS	Lists the 20 towns closest to the cursor center 6-5

Revised 11/93

ii

# AC

## Computes area statistics.

_			-
$\mathbf{E}_{\mathbf{A}}$	-	no	•
Гυ	П	IIC	1 L

AC outline area [keywords]

**Parameters** 

outline

outline number; the range is 0 to 500 (default= last

outline generated)

area

area number to compute statistics on (default=current)

Keywords

BAND=

band number (default is data dependent)

COORD=

EAR uses earth coordinates

IMA uses image coordinates

CUT=

low high brightness limits used for measurements;

the range is 0 to 255

FILL=

does not fill the outline (default)

fills the outline with graphics color level 1

2 fills the outline with graphics color level 2

3 fills the outline with graphics color level 3

HDEV=

CRT

lists a histogram on the text screen

GRA

displays a histogram on the graphics

NONE

does not output a histogram (default)

PRI

lists a histogram on the line printer

TAIL=

tail brightness percent (default=0)

Remarks

Use the keywords to modify the area statistics options set up by

command AX.

**Examples** 

AC

This entry computes area statistics on the last generated outline.

AC 20 10 HDEV=PRI

This entry applies outline 20 to area 10 and lists the histogram on the

line printer.

# $\mathbf{AX}$

Defines the area statistics options.

Format	AX file [key	e [keywords]				
Parameter	file	MD file number for the results; once you define the MD file number, you don't have to enter it again				
Keywords	COLOR=	used when OTYPE=GO  1 uses graphics color level 1 for the outline type				
		(default)  2 uses graphics color level 2 for the outline type  3 uses graphics color level 3 for the outline type				
	COORD=	EAR defines outline in earth coordinates IMA defines locates outline in image coordinates				
ide level 1 les level 2 les level 2 les level 5 les level 5 les graphies	CUT=	low high brightness or temperature limits used for measurements; the range is 0 to 255 for brightness, 163 to 330 for temperature				
		<ul> <li>does not fill the outline with graphics (default)</li> <li>fills the outline with graphics color level 1</li> <li>fills the outline with graphics color level 2</li> <li>fills the outline with graphics color level 3</li> </ul>				
		CRT lists a histogram on the text screen GRA displays a histogram on the graphics NONE does not output a histogram (default) PRI lists a histogram on the line printer				
An ola par si	LAG=	distance the cursor must be moved before command GO will draw an outline segment, in pixels (default=7)				
	NPAIR=	number of user specified threshold/limit pairs; the range is 1 to 16  O clears all pairs				
	ОТҮРЕ=	CUR uses the cursor to define the outline (default) GO uses the cursor to draw the outline				

PAIR=	low high	defines a brightness threshold/limit pair for measurement; the range is 0 to 255; when PAIR is defined, keyword NPAIR is set to the appropriate number of pairs
SUM=	IDE	identity function used for the weighted sum (default)
	SPL	spline function used for the weighted sum
TAIL=	tail bright	ness percent (default=0)
TINT=	sampling	time interval (default=200 microseconds)
UNIT=	PIX	uses the pixel brightness count to compute statistics (default)
	TEM	uses IR temperatures to compute statistics

#### Remarks

Set your area statistics options before using command GO or AC. Outlines are filled when FILL=1, 2 or 3, only after command AC is executed.

#### **Examples**

#### AX 1050

This entry defines the default area statistics options for MD file 1050.

#### AX 1000 COLOR=1 HDES=PRI

This entry defines the outline color as graphics color level 1, sends the histogram output device to the nearest line printer and stores the results in MD file 1000.

### AX OTYPE=GO

This entry defines the outline type as cursor drawn. It is not necessary to specify an MD file number, as this example assumes the MD file was specified in a previous command.

# C

Lists an image frame's directory.

#### Remarks

To list the current image frame's directory,

Press: Alt C

or

Type: C Press: Enter

The output looks like this:

FRM	SS	YYDDD	HHMMSS	BAND	LINE	ELEM	LMAGN	EMAGN	AREA
5	61	91042	91300	4	2923	41	1/4	1/4	9400

Each column is defined below.

Column	Definition
FRM	image frame number
SS	sensor source
YYDDD	year and Julian day
<b>HHMMSS</b>	image time
BAND	band number
LINE	first (uppermost) image line displayed in the image
	frame
ELEM	first (leftmost) image element displayed in the image frame
LMAGN	the first number is the blowup factor applied to the image lines; the second number is the area's resolution
EMAGN	the first number is the blowup factor applied to the image elements; the second number is the area's resolution
AREA	area number

A local ALT C on an image whose area resides on the mainframe lists the correct frame directory because the DF command transfers the directory to the workstation. The AREA number listed is -1. Entering ALT C on the host for an image residing on the workstation will list incorrect results in most cases because a local DF command does not transfer the frame directory to the host. The directory listed is for the last image frame displayed while in the host mode.

# **CF**

Changes an image frame directory.

**Format** 

CF image parm1...parm13 [keywords]

**Parameters** 

image image frame number of the directory to be changed

parm1...13 new directory value; insert X to indicate no change

**Keywords** 

pri sec changes the primary and secondary

codicil navigation pointers

TERM=

NAV=

terminal number of the directory to be changed

TV =

raster pictel changes the first TV raster and pictel

coordinate

Remarks

#### Caution!

Be very careful when using this command. It changes the mainframe copy of the frame directory only. The directory on the workstation is unaffected. Changing the frame directory entry is not recommended under normal conditions.

### **Examples**

To change the time, HHMMSS, from 19 GMT to 1930 GMT, first list the frame directory for the displayed frame 1.

Type: LF Press: Enter

The information below is displayed on the screen.

 FRAM
 SS
 YYDDD
 HHMMSS
 LINE
 ELEM
 ZCOR
 INBU
 ELBU
 INBD
 ELBD
 BAND
 AREA

 1
 30
 84289
 190000
 2192
 8181
 1
 1
 1
 1
 1
 NA
 104

To change the time,

Type: CF 1 X X 193000

Press: Enter

#### This information is displayed on the screen.

FRAME CREATION DATE

FRAM SS YYDDD HHMMSS LINE ELEM ZCOR LNBU ELBU LNBD ELBD BAND AREA
1 30 84289 193000 2192 8181 1 1 1 1 NA 104

200313

NAVIGATION CODICIL--3084289 193000 FIRST LINE OF DATA AT TV LINE=1 ELEMENT=1 AREA CREATION DATE 84289 190023

# COTV

Contours the data inside the cursor and produces a 2- or 3-dimensional plot.

The ADDE command IMGPROBE may be used in place of COTV. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

COTV interval unit [keywords]

**Parameters** 

interval

contour interval number; do not use with a 3-dimensional

plot (default=1)

unit

BRIT

brightness values (default)

RAD

radiance

TEMP

temperatures

 $\mathbf{RAW}$ 

value stored in the area

or any valid unit that is output by command D

Keywords (General) BAND=

band number of the area; the range is 1 to 32; command

LA will list bands higher than 9 as A, B, C, etc.; they must be entered as integer, that is, A=10, B=11, etc.

(default=current image band)

COLOR=

graphics color level (default=1)

DIM=

2 draws a 2-dimensional display (default)

3 draws a 3-dimensional mesh, where height is

related to brightness

OPTION=

G 2-dimensional gradient (default=digital data counts)

RANGE=

beg end

range of values to contour (default=0 to 255)

Keywords

(2-Dimensional Only)

LMOD=

1 labels every line

2 labels alternate lines (default)

SIZE=

height of the labels, in pixels, (default=6)

SMO=

contour smoothing parameter (default=20)

#### Keywords

(3-Dimensional Only)

ELE= min max element limits for the plot (default=50 600)

ELV= elevation viewing angle (default=20°)

LINE= min max line limits for the plot (default=50 450)

PAN= graphics panel number; the range is 1 to 4

**ROT**= rotation angle (default=45°)

#### Remarks

You may need to blow up the image resolution when using 2-dimensional contours. Otherwise, the plot inside the cursor may be too cluttered to read. You can use a maximum of 30,000 pixels within the cursor when plotting.

#### **Examples**

#### COTV

This entry contours the entire brightness range of the data inside the cursor with a contour interval of 1 count. The 2-dimensional plot is plotted in graphics color level 1.

#### COTV 3 COLOR=3

This entry contours the data inside the cursor every 3 counts in graphics color level 3.

#### COTV DIM=3

This entry draws a 3-dimensional mesh of the data inside the cursor.

# **CPYPTH**

Copies a path to an LW file.

**Format** 

CPYPTH sfile spath dfile dpath

**Parameters** 

sfile source file of the path to copy (default=PATHFIND)

spath

source path name to copy

dfile

destination file of the path

dpath

destination path name (default=spath)

Remarks

CPYPTH copies any path from the system path LW file PATHFIND, or any other LW file containing paths, and writes it to a new LW file which can then be saved on tape.

Once you create an LW file containing paths, you can use any of the PATH utilities by adding the FILE= keyword.

See Also

See the PATH command in this chapter.

**Examples** 

CPYPTH PATHFIND CYCLONE MYLWFILE 3MAY8312Z This entry copies path CYCLONE from the system path file to LW file MYLWFILE and renames the path 3MAY8312Z.

CPYPTH PATHFIND STORM ANYFILE

This entry copies path STORM from the system path file to LW file ANYFILE.

CPYPTH MYLWFILE WATCHBOX NEWLWFILE BOX126
This entry copies path WATCHBOX from LW file MYLWFILE to LW
file NEWLWFILE and renames the path BOX126.

# **CTY**

## Displays county outlines.

### **Format**

CTY map color [keywords]

#### **Parameters**

map SAT satellite projection (default)

MID Midwest

NTE northeast region

STE southeast region NTC north central region

PL plains

STC south central region W western region Post Office abbreviation

color graphics color level (default=1)

### **Keywords**

LAT= min max minimum and maximum latitude bounds

LON= min max minimum and maximum longitude bounds

#### **Examples**

#### CTY

This entry displays county outlines over a satellite projection in graphics color level 1.

#### CTY STE 5

This entry displays county outlines of the southeast region in graphics color level 5.

#### CTY LAT=30 60 LON=80 110

This entry displays county outlines in satellite projection from  $30^{\circ}$  to  $60^{\circ}$ N and  $80^{\circ}$  to  $110^{\circ}$ W.

D

Lists the area values at the cursor center.

The ADDE command IMGPROBE may be used in place of D.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

Remarks

To list the area value and other appropriate units of the image pixel under the cursor's center,

Press: Alt D

or

Type: D

Press: Enter

The D command lists area number, area coordinates, image coordinates, raw digital values, brightness values, radiance, blackbody temperature, or other units appropriate to the data source.

The data must reside on the mainframe.

Any 2-byte IR or dwell sound GOES data converted to 1-byte data, via command SENAA or AA, assigns missing temperature or brightness values of zero. Brightness values of 255 also indicate missing values. This includes data off the earth edge or missing lines.

See Also

Command OD lists the area inside the cursor.

# **DIST**

Finds the distance on a navigated frame.

Formats	DIST CI	R angle inc distance [keywords]
	DIST RO	OT angle inc distance [keywords]
	DIST ST	E angle din distance [keywords]
	DIST E	lat lon [keywords]
	DIST I l	ine ele [keywords]
	DIST T	raster pictel [keywords]
Parameters	CIR	draws a circle around the initial cursor location beginning at a specified distance and angle
	ROT	draws all or part of a circle around the initial cursor location beginning at a specified distance and angle
in sty bötröttales.	STE	steps the cursor away from the initial cursor location at a specified distance and angle
	E eccess a	steps the cursor away from the initial cursor location by the specified latitude and longitude increments
	I	steps the cursor away from the initial cursor location by the specified line and element increments
		a new principal Administration of the Commission
	Tools 563	steps the cursor away from the initial cursor location by the specified raster and pictel increments
	angle	moves the cursor away from the original location by this angle, in degrees (default=0)
	inc	increment to shift the cursor along its circular path, in degrees
	distance	number of km to move the cursor from its original location
	din	increment to step the cursor along its straight line path, in km
	lat	degrees of latitude to move the cursor; northward is positive
	lon	degrees of longitude to move the cursor; westward is positive

line number of lines to move the cursor, downward is positive

ele number of elements to move the cursor, rightward is

positive

raster number of TV lines (rasters) to move the cursor, downward

is positive

pictel number of TV elements (pictels) to move the cursor,

rightward is positive

### **Keywords**

COLOR= graphics color level of the characters; the range is 1 to 7 (default=1)

SIZE= height of the plotted characters, in pixels (default=5)

SYM= . use the period character to mark off distances (default)

- + use the plus sign to mark off distances
- \* use an asterisk to mark off distances
- o use a lowercase o to mark off distances

#### Remarks

Command DIST will not run unless the satellite image is navigated or a MAP command is run.

Each cursor location that you mark on the graphics frame is indicated by a period (default) or a symbol chosen with keyword SYM. A symbol is plotted on the graphics frame at the new cursor location each time you press the space bar.

DIST runs interactively when specified with no parameters, or with the ROT, STE, E, I or T parameter.

#### **Examples**

Position the cursor at the point on a navigated frame that is the starting point of the calculation. Then,

Type: **DIST** Press: **Enter** 

The program replies:

READY

HIT SPACE FOR POINT---HIT . TO EXIT

Move the cursor to the point where you want the distance measured and type one period in place of one spacebar. The distance from the original cursor location appears on the screen. When you reposition the cursor, DIST refers to the original cursor location for measurements. You must type two periods (..) to exit.

#### DIST CIR 45 30 100 SYM=\*

This entry draws a circle of asterisks on the graphics frame 100 km away from the original cursor location beginning at angle 45. The circle contains 12 asterisks since the increment is 30°.

# E

Lists the earth coordinates at the cursor center.

#### Remarks

To list the earth coordinates at the cursor center,

Press: Alt E

or

Type: E Press: Enter

The output format of E looks like this:

al auto	FRAME/SCENE	LATITUDE	LONGITUDE	TVLIN	TVELE	LINE .	ELE
IMAGE	nn	DDD:MM:SS	DDD:MM:SS	nnnn	nnnn	nnnnnn	nnnnnn
GRAPHIC	nn/nn	DDD:MM:SS	DDD:MM:SS	nnnn	nnnn		

Each column is defined below.

Column	Definition
FRAME/SCENE	image and graphics frame number and navigated graphics scene number; normally 1 (using the first navigated graphics found); will vary for commands using panels (keyword PAN)
LATITUDE	latitude of a pixel on a navigated frame; use command EKEY UNIT=D to change to decimal output
LONGITUDE	longitude of a pixel on a navigated frame; use EKEY UNIT=D to change to decimal output
TVLIN	TV raster (line) coordinates
TVELE	TV pictel (element) coordinates
LINE	satellite image line coordinates
ELE	satellite image element coordinates

To list the graphics coordinates, disconnect the image using the K command on workstations supporting separate graphics frames.

The last image or graphic displayed via host-based commands is listed when a host-based E command is run. Use a local E command when displaying images or graphics that reside on the workstation since the navigation is not sent to the host.

# **ENH**

Displays NESDIS enhancement curves.

#### **Formats**

ENH AVA ENH name

#### **Parameters**

AVA lists the 2-letter names of the available enhancements (default)

name 2-letter enhancement curve name to display on the current frame

AB locates tropical cyclones at night using IR to depict cirrus canopy and cumulus cloud bands

BB enhances hurricane patterns in certain temperature ranges

BD Dvorak hurricane curve

CA enhances cold cloud tops with a steep linear enhancement for coldest and warmest data

CB convective activity curve for fall and spring; enhances warm features, thunderstorms and CB tops; see also DB, EB and MB curves

CC cloud interpretation over colder northern latitudes in winter

CE cloud level differentiation at higher latitudes

DB convective activity curve for spring and fall

DD enhances features in the snow production temperature zone

EB middle cloud and convective activity; delineates thunderstorm turrets that penetrate the tropopause

EC convective cloud tops in the cool season

FB hydrology curve, for snow melt in spring and soil moisture content

FC for Midwest snow melt and soil moisture content

GC hurricane and severe storm cirrus canopies to measure cloud height, structure and precipitation

HB low clouds and better definition in clouds above the freezing level

HC frontal band cloudiness, CBS and tropical developments

HD low clouds, freezing level, mid-tropospheric frontal

JF identifies ocean currents, low cloud systems and freezing level; also estimates rainfall

JG locates water mass boundaries, low stratus and coastal fog in winter

JН	cloud top temperature for summer convective storms
	in the subtropics and tropics for IR only
JI	IR enhancement in the Gulf Floater for the cold season
LA	visible enhancement for forecasting early morning fog dissipation
МВ	defines low and mid clouds, thunderstorms and overshooting tops
NA	summer enhancement to depict sea surface temperature, low clouds, clouds near trade wind inversions, freezing level, and thunderstorm tops
PB	coastal upwelling along western U.S. from late spring to early fall
PC	coastal upwelling along western U.S. during late summer to early fall
SA	sea surface temperature detail during winter while maintaining landmark features
TA	land/water/low cloud contrast, precipitation estimates and tropical storm classification
ZA	standard general purpose enhancement for IR sectors; enhances low and upper level clouds
ZB	standard enhancement displaced towards colder temperatures for use in northern latitudes in winter

### Remarks

The enhancements available in this command are taken from the 1983 <u>GOES User's Guide</u>, U.S. Department of Commerce, NOAA and NESDIS, J. Dane Clark, ed., Office of Satellite Data Processing and Distribution, Washington, D.C.

#### **Examples**

#### **ENH**

This entry lists the 2-letter names of the available enhancement curves.

#### ENH PC

This entry applies the enhancement PC to the current image.

# ET

### Generates enhancements for image frame overlays.

F	o	rı	m	a	ts

ET NOR

ET CUR scale

ET TIN scale ry yg gc cb bm

ET CON vlo vhi irlo irhi scale ry yg gc cb bm

#### **Parameters**

NOR coloring for false stereo which combines straight red with a straight green enhancement table

CUR uses the current enhancement of the IR image to color the overlay of the IR and visible images

TIN colors the visible sensor image with the information derived from the IR image; although the colors are predefined, you can select the breakpoints and saturation

CON colors the visible sensor image with information derived from the IR image; only brightness values falling within both thresholds are colored; the colors are predefined, but you can choose the breakpoints and thresholds

scale color depth, saturation, or scaling factor to apply; the smaller the number the darker the tint; the range is 1 to 10 (default=5)

ry the point in the opposite frame scale to change from a red to a yellow tint; the range is 0 to 63 for towers and 0 to 255 for WIDE WORD Workstations (WWW) (default=63 for towers and 255 for WWWs)

yg the point in the opposite frame scale to change from a yellow to a green tint; the range is 0 to 63 for towers and 0 to 255 for WWWs (default=63 for towers and 255 for WWWs)

gc the point in the opposite frame scale to change from a green to a cyan tint; the range is 0 to 63 for towers and 0 to 255 for WWWs (default=63 for towers and 255 for WWWs)

cb the point in the opposite frame scale to change from a cyan to a blue tint; the range is 0 to 63 for towers and 0 to 255 for WWWs (default=63 for towers and 255 for WWWs)

bm	the point in the opposite frame scale to change from a blue to a magenta tint; the range is 0 to 63 for towers and 0 to 255 for WWWs (default=63 for towers and 255 for WWWs)
vlo	lowest visible threshold; the range is 0 to 63 for towers and 0 to 255 for WWWs (default=0)
vhi	highest visible threshold; the range is 0 to 63 for towers and 0 to 255 for WWWs (default=63 for towers and 255 for WWWs)
irlo	lowest IR threshold; the range is 0 to 63 for towers and 0 to 255 for WWWs (default=1)
irhi	highest IR threshold; the range is 0 to 63 for towers and 0 to 255 for WWWs (default=64 for towers and 256 for WWWs)

### Remarks

ET only works on tower and WIDE WORD workstations. It generates a  $63 \times 63$  enhancement table on tower workstations and a  $255 \times 255$  on WWWs for overlaying frames.

Use the N key to toggle the table in and out of the video refresh data path. When the table is in the data path, two video frames are combined pixel by pixel, and the combination is displayed on the TV monitor. The pixel value from the current frame is indexed into the rows of the table, while the pixel value from the frame opposite the current frame is indexed into the columns of the table. The value at the intersection contains the red-blue-green levels to display for this pixel. A common application is to tint clouds in varying colors according to height. In this case, the opposite frame displays an IR image complementing the current visible picture.

The table runs from pixel values 0 through 255. The 0-63 input values on the tower are scaled to 0-255 for display. A pixel with a level zero causes peculiar things to happen on the screen.

### Deep Convection Enhancement

The CON (deep CONvection) enhancement is similar to the TIN method described below, except it also accepts IR and visible input thresholds. Assume a visible image is placed on a frame with the corresponding IR image on its opposite. The CON option lightly colors the visible image based on the IR data. It enhances only the image data that falls within both the visible and IR thresholds. The color scheme is based on five color breakpoints which may or may not fall within the IR threshold. The lowest shading of the IR is red. The color breakpoints are based on a data range from 0 to 63 on towers and 0 to 255 on a WWW. The visible input threshold enables you to differentiate between deep convection cloud tops and high cirrus, indistinguishable from the IR data alone.

### **Cloud Height Tinting**

The TIN (cloud height TINting) enhancement sets up a special table to achieve the following effect. Assume the current frame contains a GOES image from the visible sensor and the opposite frame contains the corresponding image from the IR sensor. The TINT table lightly colors the visible sensor image with information derived from the IR image. The lowest values of IR tint the visible image with red, followed by yellow, green, cyan, blue and magenta. Since the brightness values in the IR correspond roughly to temperature, and temperature to height, the color tint of the visible image is an indication of cloud height.

You can control the color depth of the tint and the breakpoints of the ry, yg, gc, cb and bm changes in the IR brightness scale.

### **Examples**

In all examples, press the N key to display the pseudocoloring frame overlay.

#### ET NOR

This entry applies red and green pseudocoloring to view the false stereo image with red and green glasses.

#### ET CUR 3

This entry uses the current pseudocoloring on the IR image to tint the visible image. The 3 lightens the color saturation.

#### ET TIN X 20 30 40 50 60

This entry uses the default saturation to tint the overlay, using brightness breakpoints of 20, 30, 40, 50 and 60 on the tower.

#### ET CON 20 220 21 221 4 42 84 126 168 210

This entry uses the convective enhancement method to tint the overlays, using brightness breakpoints of 42, 84, 126, 168 and 210, between visible brightnesses 20 and 220 and IR brightnesses 21 and 221.

# **FIND**

Locates a city by name and state.

**Format** 

FIND state "string"

**Parameters** 

state

2-character state abbreviation

"string"

character string to search for the city; both double

quotes are mandatory

Remarks

If only one match is found, the cursor will move to its location. When the string is entered without a space before the second set of quotes, all cities either partially or entirely matching the string are listed. If a space is included, the string must be a perfect match with the city in order to be listed. Counties and latitude and longitude locations are also listed.

FIND also works on graphics coordinates. FIND only works for the contiguous USA (48 states).

**Examples** 

FIND WI "MAD"

This entry lists all Wisconsin cities beginning with MAD. They are Madison, Madison Truax Airport and Madsen.

FIND WI "MAD"

This entry (with one space following MAD) lists no exact matches.

FIND WI "MADISON "

This entry lists Madison only. Two spaces are necessary to distinguish it from Madison Truax Airport. The cursor moves to the location of Madison.

# **FRONT**

Draws a front through path points.

**Format** 

FRONT option path [keywords]

**Parameters** 

option COLD

OCL draws an occluded front SPLI draws a curve fitting only STA draws a stationary front

STA draws a stationary front WARM draws a warm front

draws a cold front

path

path name generated by command PATH; FRONT's curve is fitted along the points generated by PATH

**Keywords** 

ALTC=

height of the cold front barb, in pixels (default=15)

ALTW=

height of the warm front barb, in pixels (default=10)

BASE=

length of the cold or warm front barb, in pixels

(default=15)

COLOR=

curve cold warm color of the curve, cold front and

warm front; occluded front has a

purple curve (default=blue blue red)

DASH=

YES

plots a dashed line for the SPLI option

NO

does not plot a dashed line (default)

GRA=

graphics frame number (default=current)

ORIENT=

1 -1 plots barbs on the right side of the front (default)

plots barbs on the left side of the front

SKIP=

number of pixels between barbs (default=12)

SYM=

COLD

first barb on the front is a cold barb (default)

WARM

first barb on the front is a warm barb

#### Remarks

The front curve is generated as a cubic spline approximation based on the set of points collected in command PATH. If the curve is not as smooth as you want, correct your points with the PATH edit command. The frontal barbs can be modified in size and color with several FRONT keywords.

#### **Examples**

#### PATH MAKE WARMF

This entry generates a path file named WARMF. After selecting the desired points along a warm front with the PATH ADD command, you are ready to draw the front.

#### FRONT WARM WARMF

This entry draws a warm front using the points from path file WARMF.

### FRONT SPLI SETC COLOR=4

This entry fits a curve using the points in path file SETC in graphics color level 4.

#### FRONT STA FRONT1 SYM=WARM

This entry draws a stationary front using the points in path file FRONT1. The first barb is a warm barb.

# GO

Generates an area statistics outline.

### Remarks

Use command GO to outline the region on which the area statistics can be calculated. Before running GO, use the AX command to initialize the area statistics MD file. To execute GO,

Type: GO Press: Enter

Then wait for the message shown below to appear on the screen.

HIT SPACE TO BEGIN, "." TO END

Place the cursor at the desired starting location and type a period and press Enter. Move the cursor and repeat this procedure to outline the region of data until the outline is closed. We suggest defining a single letter command or F key with a period to reduce this to a single keystroke. You can exit the program at any time by pressing two periods (..), but if you terminate the outline drawing before closing it, the outline is not stored.

Up to 500 outlines may be assigned to a workstation. Outline numbers are assigned sequentially.

#### See Also

Set keywords TINT, COLOR and LAG in command AX to adjust the line drawing parameters.

## LF

### Lists an image frame directory.

Format LF bframe eframe [keywords]

Parameters beginning image frame number to list (default=current)

ALL lists all image frames

eframe ending frame number to list (default=bframe)

Keywords FORM= ALL lists an expanded directory

STN lists the standard listing (default)

TERM= terminal number with the image frames to list

(default=current)

Remarks The number of the current frame is taken from User Common.

Examples LF

This entry lists the current image frame directory.

LF 2 6

This entry lists the image frame directory for frames 2 through 6.

LF 5 FORM=ALL

This entry lists an expanded image frame directory for frame 5.

LF ALL TERM=9

This entry lists the image frame directory for all frames on terminal 9.

### LP

Displays a line plot of an image line.

The ADDE command IMGPROBE may be used in place of LP.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Formats** 

LP CUR [keywords]
LP SEG [keywords]

**Parameters** 

CUR draws a line plot the values of the entire TV line that

passes through the cursor center (default)

SEG

draws a line plot of a line segment

**Keywords** 

BAND= band number; the range is 1 to 32; command LA will

list bands higher than 9 as A, B, C, etc.; they must be entered as integer, that is, A=10, B=11, etc.

(default=current image band)

COLOR= graphics color level (default=3)

PLOT= any ASCII character

SLD plots with connecting line segments (default)

**DOT** plots only dots with no line segments

SCALE= ymin ymax xmin xmax

modifies the x and y scales to new values

(default=0 255 1 max pixels)

UNIT= calibration unit; use the D key to list choices

(default=original from area)

Remarks

A line plot of image data is drawn on the graphics.

**Examples** 

 $\mathbf{LP}$ 

This entry draws a line plot using the values of the entire TV line passing through the cursor center.

passing unrough the earson center

LP CUR

This entry draws a line plot of the cursor center line.

#### LP SEG

This entry prompts you to position the cursor at the desired starting location. Type two periods, then move the cursor to the end of the segment and type two more periods. The line plot is drawn after typing the second set of periods.

Revised 6/95 6-27

## **LPLOTS**

Displays a line plot of an image box.

The ADDE command IMGPROBE may be used in place of LPLOTS. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

LPLOTS [keyword]

Keyword

SCALE= ylo yhi xlo xhi

modifies the x and y scales to new values

(default=0 255 1 max pixels)

Remarks

A graph of image data is drawn on the graphics. A maximum of 9999 points (data values) can be plotted. Pixel numbers increase from left to right and top to bottom inside the cursor.

See Also

Use command OD to list the data values in the cursor.

**Examples** 

#### LPLOTS

This entry draws a line plot of all data values inside the cursor.

#### LPLOTS SCALE=60 170

This entry draws a line plot of data inside the cursor. The Y axis (brightness) ranges from 60 to 170. The X axis (pixel number) ranges from 1 to the cursor size.

## **MAKNAV**

Generates a navigation codicil for an area.

**Format** 

MAKNAV area [keywords]

**Parameter** 

area

area number to navigate (default=0)

**Keywords** 

LAMB= npl npe slat1 slat2 qlon size pole

Lambert conformal

projection

npl pole image line

npe pole image element

slat1 first standard latitude (default=30)

slat2 second standard latitude (default=60)

qlon normal or center logitude

size size of one pixel, in km, at standard latitude

pole N North Pole (default)

S South Pole

MERC= eql eqe slat qlon size Mercator projection

eql equator image line

ege equator image element

slat standard latitude (default=0)

glon normal or center longitude

size size of one pixel, in km, at standard latitude

**PLANET**= planet to navigate (default=EARTH)

PS= npl npe slat qlon size pole polar stereographic projection

npl pole image line

npe pole image element

slat standard latitude (default=60)

qlon normal or center longitude

size size of one pixel, in km, at standard latitude

pole N North Pole (default)

S South Pole

RADR= cenl cene clat clon size rot radar projection

cenl radar site center line

cene radar site center element

clat radar site latitude

clon radar site longitude

rot image rotation (default=0)

RECT= lin lat ele lon deglin degele rectilinear projection

lin image line number
lat image line latitude
ele image element number
lon image element longitude
deglin degrees latitude per image line
degele degrees longitude per image element

SIN= cenl cene clat clon size sinusoidal equal area projection

cenl radar site center line
cene radar site center element
clat radar site latitude
clon radar site longitude
size size of one pixel, in km, at standard latitude

#### Remarks

Specifying the *area* parameter assigns a ticketed codicil number to the area and enters it in the string table under the name NAVNUM. If *area* is not specified, use the CA command to attach the navigation to an area by entering either CA *area* NAV=#NAVNUM or CA *area* NAV=ticket#.

#### See Also

Use the REMAP command to remap into the map projection created by MAKNAV.

#### Example

The example below takes a current satellite image in area 112 and remaps into a Mercator projection in area 6000.

#### GA 6000 500 640

This entry creates area 6000 to be 500 lines by 640 elements.

#### CA 6000 30 85058 123000 1 1 8 8

This entry changes the area directory to get the satellite day, time, upper-left line, element and resolution.

#### MAKNAV 6000 MERC=2000 2000 0 90 1

This entry generates a Mercator projection codicil entry for area 6000.

#### **REMAP 112 6000**

This entry remaps area 112 into area 6000.

## MAP

Displays a map and latitude/longitude lines on a graphics frame.

_		_1
ГO	m	at

MAP map color1 LALO color2 [keywords]

	om all sal sevel mio	o soulo eng i volvo
Parameters map	DEF	draws a map in Mercator projection with latitude/longitude ranges that you specify; the map file is selected as in SAT below
	EURB	Europe's political boundaries; latitude=20 80, longitude=-60 30; map file OUTLHPOL
	EURO	Europe; latitude=20 80, longitude=-60 30; map file OUTLSUPW
	Н	North America; medium resolution; map file OUTLUSAM
		world coastal outlines; used with satellite projection; map file OUTLSUPW
	LALO	no map; latitude/longitude lines only
	MID	Midwest; latitude=34 50, longitude=83 104; map file OUTLUSAM
	NA	North America; latitude=25 80, longitude=55 179; map file OUTLUSAM
	OUTLCONC	Northcentral USA county outlines
	OUTLCONE	Northeast USA county outlines
	OUTLCOPL	Great plains USA county outlines
	OUTLCOSC	Southcentral USA county outlines
	OUTLCOSE	Southeast USA county outlines
	OUTLCOW	Western USA county outlines
	OUTLHPOL	world political outlines
	<b>OUTLHRES</b>	world coastal outlines; high resolution
aladal acid abushmol	OUTLSUPU	continental USA; high resolution
	OUTLSUPW	world coastal outlines; medium resolution
	<b>OUTLUSAM</b>	North America; medium resolution
	PO abbreviation	NY, for example; map file OUTLUSAM
	POLI	world political boundaries; map file OUTLHPOL
	PRC	Asia; latitude=15 55, longitude=-145 -65; map file OUTLSUPW
	PRCB	Asia's political boundaries; latitude=15 55,
		1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1

SAT

longitude=-145 -65; map file OUTLHPOL

draws a map in satellite projection using the OUTLUSAM map file for North America and OUTLSUPW for all other areas (default)

		USA	continental USA; latitude=23 56, longitude=66 126; map file OUTLUSAM
		VH	continental USA; high resolution; map file OUTLSUPU
		WIS	Wisconsin; latitude=41 48, longitude=85 95; map file OUTLUSAM
		WORL	world coastal outlines; used with Mercator projection; map file OUTLSUPW
	color1	graphics color	r level for the map (default=1)
	LALO	draws latitud draw lines)	le/longitude lines with a map (default=does not
	color2	graphics color	r level for latitude/longitude lines (default=2)
Keywords	ACC=	accuracy for l (default=4)	atitude/longitude lines; the range is 1 to 10
	BOX=	YES color	draws a box around the map in the specified graphics color level (default for all except SAT, L, H, VH and X; default color=1)
		NO	does not draw a box
	ELE=	min max	TV element extents (default depends on frame size)
	GRA=	graphics fran	ne number (default=current)
	<b>ІМА=</b>	image frame	number (default=current)
	INT=	lat lon	intervals for latitude and longitude lines (default=computed)
		North con North An Live 1 NX, for so	on adds latitude/longitude line labels (default); specify the graphics color levels for latitude and longitude; use this keyword when LALO is specified; see the Labels section below does not add labels to latitude/longitude lines
		lat1 lat2	latitudes of the points at the lower-right and upper-left corners of the map
	LIN=	min max	TV line extents (default depends on frame size)

LON=	lon1	lon2

longitudes of the points at the lower-right and upper-left corners of the map; if you choose a CONF projection and specify SCALE, the map is centered at that coordinate on the TV screen if only lat1 and lon1 are entered; in other cases, the point with coordinate lat2, lon2 is placed in the upper-left corner; the other point is shifted or removed to create a map with a given scale; defaults for the SAT projection are the range taken from the image or map geographical limits; for CONF and MERC projections, defaults are latitude -90° to +90° and longitude -180° to +180°

NAME= map file name; it overrides a default map file

PAN= panel number; the range is 0 to 4 (default=0, whole screen)

PRO= CONF conformal projection; see the Projections

section below

MERC pseudo-Mercator projection (default for all

maps except H, VH, L or LALO)

SAT satellite projection (default if map and

projection are not specified or map is H, VH,

L or LALO and the projection is not

specified)

SCALE= map scale for a CONF projection; scale values in the range

up to 1000 are multiplied by 1,000,000 (default=no scale)

SLAT= standard latitude(s) for a CONF projection only; one value

for a polar stereographic projection (default= $60^{\circ}$ ); two

values for general Lambert conformal projection

SLON= standard longitude, for a CONF projection only

(default is computed)

#### Remarks

To display a map on a satellite image, use L, H, VH or SAT (or X, since SAT is the default) as the map parameter. The BOX= keyword will not work with these map types.

#### **Projections**

The MERC (pseudo-Mercator) projection has equidistant latitude lines; otherwise it is the same as a true Mercator projection. The CONF (Lambert conformal) projection includes polar stereographic projection as a special case. If you enter only one positive SLAT value, or if you accept the default of 60°, the projection is polar stereographic with the North Pole as the origin of projection. If you enter only one negative value for SLAT, the origin of the polar stereographic projection is the South Pole. You must enter two SLAT values to obtain a general Lambert conformal projection. If SLAT1 + SLAT2 > 0, the North Pole is the origin of projection. If SLAT1 + SLAT2 < 0, the South Pole is the origin of projection.

For some values of keywords LAT, LON, SLON and SLAT, the area defined cannot be found. If this happens, an error message is displayed and the program aborts. Use SLON for CONF projections only. The default value is computed by assuming that the standard meridian is located in the middle of a box set by two points and is parallel to the left and right edges of the TV screen. If a map is centered, the default SLON is equal to LON.

#### Labels

In some cases, labels overlap. You can usually adjust this by changing the latitude/longitude line intervals and/or the accuracy.

#### **Examples**

The examples below are divided into four groups that include satellite, pseudo-Mercator projection, polar stereographic and general Lambert conformal projections. Command lines that won't fit on one line are continued on a second line that is indented.

#### **Satellite Projection**

#### MAP X 5 LALO 6 INT=5 10

This entry draws a map on a satellite image in graphics color level 5. It draws latitude/longitude lines in graphics color level 6 and labels them. The interval for latitude lines is 5°. The interval for longitude lines is 10°.

#### MAP VH X LALO LABEL=NO

This entry draws a high resolution USA map and latitude/longitude lines without labels.

#### Pseudo-Mercator Projection

#### MAP AK X LALO

This entry draws a map of Alaska and latitude/longitude lines with labels.

#### MAP EURO 2; MAP EURB X LALO

This entry draws a map of Europe with coastal and political boundaries.

#### MAP CA X LALO NAME=OUTLCOW

This entry draws a map of California from map file OUTLCOW instead of the default map file OUTLUSAM.

#### Polar Stereographic

#### MAP WI PRO=CONF

This entry draws a map of Wisconsin in conformal projection.

#### MAP LALO PRO=CONF LAT=0 70 LON=90 -90

This entry draws latitude/longitude lines and labels for the specified North American region.

#### MAP OUTLSUPU X LALO PRO=CONF LAT=30 45 LON=90 110 SLON=100

This entry draws a map and latitude/longitude lines for a region with the specified latitude/longitude range and standard longitude. The map is taken from the OUTLSUPU high resolution map file. In this case, the map file name can be abbreviated as VH.

#### MAP X X LALO PRO-CONF LAT--20 -20 LON-0 180

This entry draws a map of the northern hemisphere with the North Pole as the origin of projection.

## MAP X X LALO PRO=CONF LAT=20 20 LON=0 180 SLAT=-60

This entry draws a map of the southern hemisphere with the South Pole as the origin of projection.

## MAP X X LALO PRO=CONF LAT=-10 60 LON -10 20 SCALE=20

This entry draws a map of the latitude/longitude range specified in 1:20000000 scale. The point with latitude 60 and longitude 20 is located in the upper-left corner of the TV screen.

#### MAP PRO=CONF LAT=-90 LON=0 SLAT=-60 SCALE=35

This entry draws a map centered at the South Pole, with the origin of the projection at the South Pole and a standard latitude of 60°. The point with latitude -90 and longitude 0 is in the middle of the TV screen. The standard longitude is 0° and the scale is 1:35000000.

## MAP X X LALO PRO=CONF LAT=-5 -35 LON=-115 -170 SLAT=-60

This entry draws a map of Australia with latitude/longitude lines and labels in the projection centered at the South Pole.

## MAP X X LALO PRO=CONF LAT=-60 0 LON=-70 -145 SLAT=-60 SLON=-40

This entry is the same map of Australia but rotated by 180°, with the South Pole at the lower-right corner of the screen.

## Lambert Conformal Projection

MAP PRO=CONF LAT=20 60 LON=70 165 SLAT=40 60 This entry draws a Lambert conformal map of the USA.

MAP X X LALO PRO=CONF LAT=40 70 LON=150 -150 SLAT=40 60

This entry draws a map of the Alaska region. In the Lambert conformal projection, the map splits but the information is complete.

MAP X X LALO PRO=CONF LAT=-15 LON=-135 SLON=180 SCALE=25 SLAT=-60 40

This entry draws a map of Australia with latitude/longitude lines.

MAP X X LALO PRO=CONF LAT=-80 LON=15 SLON=10 SLAT=-70 -10 SCALE=40

This entry draws a map of Antarctica.

OST DEPOS OF DESCRIPTION OF DESCRIPTION OF THE PROPERTY OF THE

1:20000000 see le. It he point with bethad to cold forest under 20 le

## **MDOA**

Lists area statistics calculations.

Format MDOA outline image [keyword]

Parameters outline number for which to list statistics

ALL lists statistics for all outlines

image image number to which the outline is applied; the range is

1 to 30

**Keyword** MDF= MD file number containing the statistics

(default is from MDU SET file)

Remarks The image number is not an image frame number, but the order in which

the outline is applied to image data. Up to 30 image sectors can use one outline. Their numbering begins with one, where one is the first image

used.

Examples MDOA ALL

This entry lists the area statistics calculations for all outlines.

MDOA 50 5 MDF=5210

This entry lists statistics from the fifth image applied to outline 50 stored

in area statistics MD file 5210.

## OD

Lists the data bounded by the cursor.

The ADDE command IMGPROBE may be used in place of OD.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

#### **Format**

#### OD mode data a b c [keyword]

<b>Parameters</b>	mode	$\mathbf{C}$	contours data
		${f F}$	data frequency distribution
	solitalitate of the	and kines	data interval percentage
		L	lists data (default)
		S	lists data by sensor source; GOES visible only
	data	A	values stored in the area (default)
	adia	В	grayscale brightness conversion
		R	radiance
		T	temperature conversion, in Kelvin
		name	any valid calibration name (BRIT, TEMP, RAD, etc.)
	a,b,c	specify	de I, specify $a$ and $b$ as the data range; for mode C, $a$ as the contour interval, and $b$ and $c$ as the horizontal ertical replicators

#### Keyword

BAND= band number (default=from the frame directory)

#### Remarks

Mode S lists brightness data by sensor source. Do not use the data positional parameter with the S mode.

Use the D command to determine the available data types in the area. If the data is not on disk, OD can't list it. The output is the same resolution as the area. Use system keyword DEV to send output to the line printer.

If you list data values for large cursor sizes, the output is divided into sets. A set is 50 lines by the number of elements that can fit on a text screen. This number depends on the data type, i.e., you can fit more brightness values on a line than IR radiance values. If there are too many elements for a line of data, the set is divided into parts. The set and part numbers are the x and y coordinates, respectively, of the data blocks relative to the upper-left corner of the cursor.

The default data parameter is the calibration type. To determine the calibration type, use the command: LA area FORM=ALL.

Any 2-byte IR or dwell sound GOES data converted to 1-byte data, via command SENAA or AA, assigns missing temperature or brightness values of zero. Brightness values of 255 also indicate missing values. This includes data off the earth edge or missing lines.

#### **Examples**

#### OD

This entry lists the data for the area bounded by the cursor.

#### OD F

This entry lists a histogram of the data inside the cursor. It is linearly scaled so that a small peak in the distribution is less than one level on the graph. Consequently, the peak is not displayed.

Suppose you've displayed a GOES VIS image and you want to list the default values in the cursor area. To do this, enter:

#### OD L

This entry lists the digital brightness values in the cursor area on the image, as the default calibration type for a GOES VIS image is BRIT.

#### OD L T

This entry lists the data for the area inside the cursor on the text screen. Use this entry with IR data.

Suppose you've displayed a GOES IR area at full resolution (4km). If the cursor size is 115 lines by 51 elements and you want to list digital radiance data on the text screen, enter:

#### OD L R

This entry lists 6 blocks of data by sets and parts like this:

Block	Set, Part
1	1,1
2	1,2
3	2,1
4	2,2
5	3,1
6	3,2

Since there are 115 lines of data to list, OD breaks the data into 3 sets. Sets 1 and 2 have 50 lines each; set 3 has 15 lines. Because there are 15 radiance values to list per line and the screen can only display 11, OD displays each set in 2 parts. Part 1 shows the first 11 values; part 2 shows the last 4 values.

To determine where the data blocks lie in relation to the cursor, paste the parts together sequentially from left to right for each set. Then paste the sets together sequentially from top to bottom. The result looks like this:

	Part 1	Part 2
Set 1	Block 1	Block 2
Set 2	Block 3	Block 4
Set 3	Block 5	Block 6

### **PATH**

Displays a 2-dimensional path for object tracking.

#### **Formats**

PATH ADD name CUR [keywords]

PATH ADD name index CUR [keywords]

PATH ADD name index FILE [keywords]

PATH ADD name index station [keywords] "label

PATH ADD name index lat lon [keywords] "label

PATH DEL name CUR [keywords]

PATH DEL name index CUR [keywords]

PATH DEL name index1 index2 ... indexn FILE=

PATH DIR [keywords]

PATH EDIT name index [keywords] "label

PATH LIST name FILE=

PATH MAKE name FILE=

PATH PLOT name [keywords]

PATH QUIT name FILE=

#### **Parameters**

ADD adds a segment to a path

CUR interactively use the cursor to add or delete a path point

DEL deletes a path segment

DIR lists the directory of paths including path name, date created

and user's initials (default)

EDIT edits a latitude, longitude or path label

FILE adds path points from an LW file; the file must have the same

name as the path

LIST lists the contents of a path; includes indices, latitudes,

longitudes and labels

MAKE generates a path

**PLOT** plots the path on the graphics frame

QUIT deletes a path

name path name, 1 to 12 characters

index number assigned to a point on the path; points are

numbered sequentially beginning at one

station 3- or 4-letter station ID used as a point on the path

latitude of the point

lon longitude of the point

"label label plotted at the latitude and longitude of the point;

1 to 20 characters

Keywords COLOR= graphics color level of the path (default=2)

FILE= source file of the path (default=PATHFIND)

LABEL= YES plots labels on the path

NO does not plot labels on the path (default)

LAT= latitude for the point; valid with EDIT option only

LCOLOR= graphics color level for labels (default=3)

LINE= YES draws a line between points (default)

NO does not draw a line between points

LON= longitude for the point; valid with EDIT option only

LSIZE= label height, in pixels (default=6)

NUM= number of entries to list, starting at the top; valid with

DIR option only (default=all entries)

USER= user initials of the owner; valid with DIR option only

(default=current)

ALL lists paths for all owners

Remarks

PATH can be used to plot tracks of weather systems (e.g., hurricanes) or draw boundaries such as watch boxes.

Use the EDIT option to add labels or change latitude and longitude points.

To create or use paths from a file other than the system path file (PATHFIND), specify the source file with keyword FILE=.

When adding or deleting points from a path, all points are automatically renumbered with new index numbers. Adding a new point does not overwrite the existing point. When adding points with the interactive mode, you may either manually specify or use the cursor to determine which index number the new point receives. When using the cursor, the new point is assigned the index number that follows the index number of the point inside the cursor. Changing the cursor type to BOX or XBOX can help isolate points to delete or renumber.

LW files can be used to create a new path or add points to an existing path. Information for each point should be on a separate line in either of these formats:

indexnumber stationid label indexnumber latitude longitude label

For example, if the LW file TRACK consists of the following 3 lines:

- 1 42:34:30 69:26:11 42N 69W
- 2 PVD Providence
- 3 42:22 71:02 Boston

the command PATH ADD TRACK 1 FILE will add the three points and labels to the path named TRACK. Points defined by the *stationid* format are converted to latitude and longitude when stored in the path.

#### **Examples**

#### PATH MAKE ANDREW

This entry generates a path named ANDREW.

#### PATH DIR

This entry lists all the paths for the current user stored in the default path file PATHFIND.

PATH ADD ANDREW 1 11:00 38:00 "8/16/92 22 UTC Position This entry adds the first point in the path ANDREW. Nothing is plotted on the graphics.

PATH ADD ANDREW 2 14:30 47:10 "8/17/92 22 UTC Position This entry adds the second point to the path ANDREW. Again, nothing is plotted on the graphics.

## PATH PLOT ANDREW LABEL=YES COLOR=3 LSIZE=10 LCOLOR=4

This entry plots the points in path ANDREW in graphics color level 3 with labels in graphics color level 4, 10 pixels high.

#### PATH ADD ANDREW CUR LABEL=YES

This entry begins the interactive mode where the cursor is used to add one or more points to path ANDREW. Position the cursor at the desired location and then type and enter a period (two periods will appear). Repeat the process to add multiple path points. Labels can be added to the new points. For example, . "8/18/92 22 UTC Position will add the new point and its label. You must insert at least one space between the period and double quote. Because LABEL=YES was included with this entry, each new point and its label are plotted. Without it, the label is not plotted, although it is stored with the point in the path. To exit the interactive PATH command, type and enter two periods (three will appear). The end of the newly generated path will be plotted and the new points listed.

#### PATH LIST ANDREW

This entry lists all points in path ANDREW.

#### PATH ADD ANDREW 5 CUR LABEL=YES

This entry begins the interactive mode where the cursor is used to add one or more new points before point 5. Each new point and its label are plotted.

#### PATH DEL ANDREW 3 CUR

This entry deletes point 3 from the path and begins the interactive mode where additional points are deleted by placing the cursor over the point to delete. The corrected path is redrawn each time a point is removed.

#### PATH DEL ANDREW 1 4 6 7

This entry deletes points 1, 4, 6 and 7 from path ANDREW.

#### PATH EDIT ANDREW 1 LAT=11:10 LON=38:20

This entry changes the latitude and longitude of point 1 in path ANDREW to 11:10N and 38:20W, respectively.

#### PATH QUIT HUGO FILE=HURRICANE

This entry removes the path HUGO from the path file HURRICANE.

#### PATH ADD VT 5 BTV "BURLINGTON, VT

This entry adds BTV to the path VT and labels it BURLINGTON, VT.

### PC

Positions the cursor at a desired point on the frame.

#### **Formats**

PC C

PC L station

PC E lat lon

PC I line ele

PC T raster pictel

PC G line ele [keyword]

#### **Parameters**

C positions the cursor at the center of the frame

L positions the cursor at the station ID or synoptic ID location

E positions the cursor at the latitude and longitude earth

coordinates

I positions the cursor at the line and element image

coordinates

T positions the cursor at the raster and pictel TV coordinates

G positions the cursor at the line and element graphics

coordinates

station 3- or 4-character station ID

5- or 6-digit station ID

latitude of the location

lon longitude of the location

line image or graphics line of the location

ele image or graphics element of the location

raster TV raster (line) of the location

pictel TV pictel (element) of the location

#### **Keyword**

SCENE = virtual graphics scene number used with PC G

#### Remarks

The station parameter can be either a letter identifier, or a RAOB station number. Non-US stations are available.

Command PC disconnects the mouse from the cursor control on OS/2-based workstations. Use command P to regain cursor control. On McIDAS-X workstations, PC has no effect on the cursor control.

The image or graphics must have a frame directory on the mainframe when using options L, E and I, i.e., they will not work on images or graphics that reside on the workstation's disk.

#### **Examples**

#### PC E 36 -98

This entry positions the cursor at 36° North and 98° East.

#### PC I 3300 1200

This entry positions the cursor at image coordinate line 3300 and element 1200.

#### PC L MSN

This entry positions the cursor over Madison, WI.

#### PC T 100 356

This entry positions the cursor at TV raster 100, pictel 356.

#### PC G 200 300 SCENE=4

This entry positions the cursor at graphics coordinates 200 and 300 on the displayed virtual graphics scene 4.

#### PC L 72250

This entry positions the cursor over Brownsville, TX.

### **PLAX**

Lists satellite parallax at the cursor position.

**Formats** 

PLAX [keywords]

PLAX height direction [keywords]

**Parameters** 

height

cloud height, in kilometers

direction

 $\mathbf{C}\mathbf{G}$ 

cloud to ground parallax (default)

GC

ground to cloud parallax

Keywords

LAT=

latitude to position the cursor (default=current)

LON=

longitude to position the cursor (default=current)

Remarks

Use keywords LAT and LON to position the cursor over the desired

location.

Use PLAX without parameters to calculate delta latitude/longitude per

km at the cursor position.

**Examples** 

PLAX

This entry calculates satellite parallax at the cursor position.

PLAX 8 LAT=40 LON=90

This entry positions the cursor at 40°N and 90°W and calculates the

cloud to ground parallax at 8 km above the earth.

## PO

Restores the position of the area statistics outline.

**Format** 

PO boutline eoutline [keywords]

**Parameters** 

boutline

beginning outline to restore; the range is 1 to 500

eoutline

ending outline to restore (default=boutline)

Keywords

AREA=

area number of the image (default=current)

IMA=

image frame number (default=current)

MDF=

MD file number for the results (default=current)

NAV=

pri sec

primary and secondary navigation codicils

stored in the area statistics MD file

(default=image area codicils)

Remarks

One outline may be applied to a maximum of 30 different images.

See Also

Use command GO to generate the outline.

**Examples** 

PO 20

This entry draws outline 20 over the displayed image.

PO 36 38 MDF=6512

This entry restores outlines 36 to 38 from MD file 6512.

## SEG

Updates a graphics frame loop with the current graphics.

F	O	r	m	12	at

SEG bframe eframe bvirt evirt option [keyword] "command

#### **Parameters**

beginning physical graphics frame number to search

eframe ending physical graphics frame number to search

buirt beginning virtual graphics to search

evirt ending virtual graphics to search

option BOTH writes on both the physical and virtual

graphics

PHYS writes on the physical graphics frame only

(default)

VIRT writes on the virtual graphics only

"command graphics command to execute

#### Keyword

OPT= ALL displays the graphics command on each

frame in the designated boundaries

#### Remarks

SEG automatically erases the physical and virtual graphics before writing to them. If BOTH is used, the physical and virtual starting points may differ. However, they must have the same length.

Use SEG in the scheduler to update frames.

#### See Also

Use command SEQG to update image and graphics frames.

#### **Examples**

#### SEG 1 4 "SP T VT

This entry plots the current surface temperatures for Vermont in the latest graphics frames 1 to 4.

#### SEG 1 4 1001 1004 BOTH "SHIPC T FL;SP WXS FL

This entry contours the current temperatures for Florida and surrounding ship reports, and plots current weather symbols over Florida in the latest graphics frames 1 to 4 and virtual graphics 1001 to 1004.

## **TOWNS**

Lists the 20 towns closest to the cursor center.

#### Remarks

TOWNS only works on navigated images. The information below is listed for the 20 towns closest to the cursor position.

Column	Definition	oframe	a profession of
1	city		
2	county		
3	state		
4	latitude		
5	longitude		

## Chapter 7. MD Files

LSCHE	Lists an MD file schema
MDC	Copies MD files
MDCLAS	Classifies MD file data
MDE	Edits MD files
MDEX	Modifies the row and column headers in an MD file 7-6
MDFIX	Edits MD files using the cursor position or station ID 7-7
MDL	Lists MD file data 7-8
MDOX	Lists MD file records
MDPACK	Packs MD file data records
MDSCAT	Displays a scatter plot of MD file data 7-12
MDU	MD file utility
MDX	Plots, contours or grids data from MD files or grids 7-10
SENMD2	Sends a mainframe MD file to a workstation

## **LSCHE**

Lists an MD file schema.

**Formats** 

LSCHE schema version HED

LSCHE FIND key

**Parameters** 

schema name of an MD file schema to list (no default)

ALL lists all schemas

version

schema version number to list

ALL lists all schema version numbers

(default=latest version)

key

name of a schema key; a schema entry point descriptor

HED

lists the file header only (default=lists header and keys)

FIND

lists the schemas that contain the specified key

Remarks

Before using LSCHE, register the MD files using command SCHE which is documented in the McIDAS-X and McIDAS-OS2 Users Guides.

Use LSCHE to list the schema header and keys.

**Examples** 

LSCHE IRAB

This entry lists the international upper air file schema.

LSCHE ISFC ALL DEV=P

This entry prints all versions of the international surface file schema.

LSCHE ISHP X HED

This entry lists the header only for the international ship file schema.

LSCHE FIND IDN

This entry lists all schemas that contain the key IDN (upper air station ID number).

## MDC

Copies MD files.

The ADDE command PTCOPY may be used in place of MDC.

See the ADDE section of the <u>McIDAS-X</u> or <u>McIDAS-OS2 Users Guide</u>
for more information.

**Format** 

MDC sfile dfile [keywords]

**Parameters** 

sfile source MD file number

dfile

destination MD file number (default=sfile)

**Keywords** 

DC= destination MD file column starting point; see the Remarks

DR=

destination MD file row starting point (default=1)

APPEND

appends data to the first row in the file

SC=

min max

source MD file column range (default=all)

SR=

min max

source MD file row range (default=all)

Remarks

To copy an entire file, supply only the MD file numbers. Use all the keywords when adding onto another file. If the size of the destination file is too small to contain the new data, generate a new destination file of the appropriate size with MDU MAKE.

If keyword DC is omitted and the row header contains the key CMAX, MDC begins copying into the first empty record. Otherwise, MDC begins copying into column one.

Examples

MDC 30 6512

This entry copies MD file 30 into MD file 6512.

MDC 34 6514 SR=1 20 SC=1 50 DR=10 DC=1

This entry copies MD file 34 into MD file 6514, moving rows 1 to 20 and columns 1 to 50 into file 6514, beginning at row 10, column 1.

## **MDCLAS**

Classifies MD file data.

**Format** 

MDCLAS key min max [keywords]

Parameters

key key from the MD file; use MDL to list keys

min

minimum value for a key

max maximum value for a key

Keywords

**COLOR** = graphics color level of the plot (default=3)

INT= group interval; NUM is calculated

MDF = MD file number (default=from MDU SET file)

NUM=

number of classes; INT is calculated (default=10)

XP= min max div sdiv x-axis plot parameters min max range values of the scale

div

number of divisions

sdiv

number of subdivisions

YP= min max div sdiv y-axis plot parameters

Remarks

Any key found in the MD file may be used as a subset of the file (ROW,

COL are valid). The MD file original units are used.

Example

MDCLAS T 243 303 INT=2 MDF=4 TIME=18 LAT=30 50

LON=80 110

This entry plots frequency of temperature in 2°C bins at 1800 UTC, from ISFC file 4, latitude 30 to 50, longitude 80 to 110, from 243K to 303K

(i.e., -30°C to 30°C).

## **MDE**

#### Edits MD files.

**Formats** 

MDE file KEYS=LIST

MDE file KEYS=DEL conditions

MDE file KEYS=REST ROW= COL=

MDE file INI SAVE KEYS= VALU= UNIT= conditions

**Parameters** 

file

MD file number to edit (default is set by MDU SET or by

the previously executed MDE command)

INI

initializes the string table entries used by MDE

(default=does not initialize)

SAVE

saves keywords and values in the string table; all

subsequent executions of MDE will recall the values saved

in the string table (default=does not save)

Keywords

KEYS=

keys in the MD file to edit

**DEL** deletes the records that meet the search conditions

LIST lists the keywords in the MD file schema by row

and column headers and data

**REST** restores a deleted record; specify ROW= and COL=

UNIT=

units in which the new key values are entered

VALU =

new value for the keys

MISS enters a missing data value

conditions search conditions to meet when searching for a record to edit; use any or all of the following options:

COL = min max column number or range of numbers

(default=1)

 $ROW = min \ max$  row number or range of numbers

(default=1)

schema keyword= low high units

range and units of the schema keyword you're seaching for; units are only

necessary if the range is specified in units other than those native to the

MD file

#### Remarks

Save keys, values, units and search conditions in a string table (see parameters INI and SAVE) so you don't have to reenter them for each MDE execution. Before editing system MD files, move them into your assigned file numbers with command MDC. If you delete a record accidentally, you can recover it with keyword KEYS=REST provided you have not repacked the file. Use MDE KEYS=LIST to list key names; MDE will only edit data keys.

#### See Also

Use command MDEX to edit row and column headers.

#### **Examples**

MDE KEYS=DEL ROW=1 5 COL=15 20

This entry deletes columns 15 to 20 in rows 1 through 5.

MDE 6514 KEYS=LIST

This entry lists the keys for MD file 6514.

## MDE 6512 INI SAVE KEYS=T VALU=32 UNIT=F ID=MSN TIME=12

This entry searches for MSN at 12 GMT in MD file 6512 and changes the temperature to 32°F. It initializes the string table and saves the new string values.

#### MDE KEYS=T TD VALUE=MISS ID=MSN TIME=12

This entry flags the temperature and dew point as missing for MSN at 12 GMT.

The following example edits a ship observation in MD file 31. Before editing data, move MD file 31 into your assigned file numbers (file 6512 in this example).

#### 1. MDC 31 6512

This entry copies MD file 31 into MD file 6512.

#### 2. MDU SET 6512

This entry sets the MD file pointer to MD file 6512. All subsequent MD file commands will be performed on this file.

# 3. MDE KEYS=T UNIT=C VALU=20 ID=KWPR TIME=12 This entry locates ship ID KWPR at 12 GMT. Once located, its temperature is changed to 20°C.

## 4. MDE KEYS=DEL ROW=5 COL=10 15 This entry deletes the records at row 5 and columns 10 to 15.

## 5. MDE KEYS=REST ROW=5 COL=10 This entry restores the record at row 5 and column 10.

### **MDEX**

Modifies the row and column headers in an MD file.

Format MDEX file KEYS= VALU= ROW= COL=

Parameter file MD file number to edit (default=set by MDU SET or the

previously executed MDU, MDE or MDEX command)

Keywords COL= min max column number or range of numbers to edit

(default=0)

KEYS= MD file row and column header keys to edit

LIST lists the keys in the MD file schema; the keys

are listed as row and/or column header keys

and data keys

ROW= min max row number or range of numbers to edit

(default=0)

VALU= new values for the keys

Remarks

Caution!

Be very careful when using MDEX. Any change made in a row header is reflected in all records in that row. The same is true with column headers. To determine which schema keys are in the row and column headers, use MDEX KEYS=LIST.

See Also

Use command MDE to edit the data keys.

Example

MDEX 6512 KEYS=TIME VALU=12 ROW=5 7

This entry changes the times in the row headers of rows 5 through 7

of MD file 6512 to 12 GMT.

## **MDFIX**

Edits MD files using the cursor position or station ID.

Format	MDFIX sfile dfile time station [keywords]				
Parameters	sfile	source MD file with the bad data (default=current)			
	dfile	destination MD file for the corrected data; use an X in place of <i>dfile</i> if you do not want to copy the entire MD file (default=current)			
	time	time of the bad report, HH:MM:SS			
	station station ID or IDN (for example, LBB or report; if excluded, the cursor position is		O or IDN (for example, LBB or 72451) with the bad excluded, the cursor position is used		
Keywords	LEV=	for IRAB	data, specify vertical level		
older table	PARM=	p1 p2	MD file parameters in error		
	TYPE=	0 1 2	hourly surface report (default) special report, see the MD file schema for this value special report, see the MD file schema for this value		
	UNIT=	u1 u2	units of the parameters if not the default unit		
	VAL=	v1 v2 MISS	corrected value of the parameter enters the missing value		

#### Remarks

You must specify values for keywords PARM and VAL. It is acceptable to specify only one parameter in error and one corrected value. Copy real-time MD files into scratch files before modifying them. You can change a maximum of two parameters at one time.

#### Example

#### MDFIX 5 6512 18 MSN PARM=T VAL=25

This entry edits the ISFC data for station MSN, parameter T, to  $25^{\circ}$  C. It then copies the edited MD file into 6512 from real-time file 5.

## MDL

Lists MD file data.

The ADDE command PTLIST may be used in place of MDL. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

MDL file ALL INI SAVE KEYS= UNIT= conditions

**Parameters** 

file

MD file number (default is set by MDU SET or the

previously run MDL or MDE command)

ALL

lists all occurrences that meet the search conditions

(default=first occurrence)

INI

initializes the string table entries used by MDL

(default=does not initialize)

SAVE

saves the MDL keywords in the string table

(default=does not save)

**Keywords** 

FWIDTH=

changes the default field widths for each variable; the

practical maximum number of characters is 10

KEYS=

keys to list from the MD file schema

LIST lists the keys in the MD file schema by row

and/or column header keys and data keys

UNIT=

units in which to list the values; specify this keyword if

the units are different than those native to the MD file

conditions

search conditions to meet when searching for a record to

list; use any or all of the following options:

COL=min max column number or range of numbers

(default=1)

ROW=min max row number or range of numbers

(default=1)

schema keyword=low high units

range and units of the schema keyword you're searching for; units

are only necessary if the range is specified in units other than those

native to the MD file

#### Remarks

Position the parameters for keyword UNIT in the same order as those listed in keyword KEYS.

Use the letter X as a placeholder to list a key in its default unit.

You can store keys, units and search conditions in a string table; see parameters INI and SAVE. It is not necessary to type them for each MDL command.

#### See Also

Use command MDEX to edit the row and column headers. Use command MDE to edit the data keys.

#### **Examples**

#### MDL

This entry lists the first record of the current MD file.

## MDL 3 KEYS=ID TIME T TD ID=MSN TIME=12 This entry lists the station ID, time, temperature and dew point for

Madison, WI, at 12 UTC from MD file 3.

## MDL 33 ALL KEYS=ID T TD TIME LAT LON T=20 21 C UNIT=X C C TIME=12

This entry lists the station ID, temperature, dew point, time, latitude and longitude from all reports in MD file 33 meeting the conditions TIME=12 UTC and the temperature is between 20° and 21° C.

## MDL INI SAVE KEYS=Z T TD DIR SPD UNIT=FT F F X KT ROW=1 COL=5

This entry lists the height (FT), temperature (F), dew point (F), wind direction, and wind speed (KT) for row 1, column 5.

# MDL 15 ALL KEYS=Z T TD DIR SPD UNIT=FT F F X KT ROW=1 COL=5 FWIDTH=6 X X X 5

This entry lists the height, temperature, dew point, wind direction and wind speed for row 1, column 5. The field widths for the height and wind speed are expanded to accommodate larger values while temperature, dew point and wind direction maintain their default field widths.

## **MDOX**

Lists MD file records.

The ADDE command PTLIST may be used in place of MDOX. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

DCM class with openid sown

MDOX file [keywords]

**Parameter** 

file

MD file number (default=from MDU SET file or the previously run MDL or MDE command)

**Keywords** 

COL=

min max

lists this range of column numbers

(default=all)

ROW=

min max

lists this range of row numbers

(default=all)

Remarks

Use ROW=0 to list column headers; use COL=0 to list row headers.

Unlike MDL, MDOX lists all records, even those flagged as missing or deleted. A record is considered missing if the first field in that record is missing.

**Examples** 

**MDOX** 

This entry lists all MD file records.

MDOX 1000 ROW=1 10 COL=1 50

This entry lists MD file 1000, rows 1 to 10 and columns 1 to 50.

### **MDPACK**

Packs MD file data records.

**Format** 

MDPACK file [keywords]

**Parameter** 

file

MD file number greater than 99 (default=current)

**Keywords** 

COL=

last column to pack (default=entire row)

CMAY

finds the last entry in each row; it is more efficient than allowing the default of the entire

row

ROW=

min max row range to pack (default=entire file)

Remarks

MDPACK will not pack system files 1 to 99, nor will it pack MD files

that contain column headers.

**Examples** 

**MDPACK** 

This entry packs the current MD file and points at the file with

MDU SET file.

MDPACK 1000 COL=CMAX

This entry packs the entire MD file 1000.

### **MDSCAT**

Displays a scatter plot of MD file data.

Formats MDSCAT xparm yparm [keywords]

MDSCAT xparm1 oper1 xparm2 yparm1 oper2 yparm2 [keywords]

Parameters xparm x-axis key from the MD file; use command MDL to list

the keys

yparm y-axis key from the MD file

xparm1 first x-axis key from the MD file

oper1 first arithmetic operator (+, -, \*, /) for addition,

subtraction, multiplication and division

xparm2 second x-axis key from the MD file

yparm1 first y-axis key from the MD file

oper2 second arithmetic operator (+, -, \*, /) for addition,

subtraction, multiplication and division

yparm2 second y-axis key from the MD file

Keywords COLOR= graphics color level of the plot (default=3)

ERASE = YES erases the graphics frame before plotting

(default)

NO does not erase the graphics frame

GRA= graphics frame number (default=current)

PAN= specifies the graphics quarter panel, 0, 1, 2, 3, 4

(default=0, full screen)

MDF= MD file number of the data (default=from

MDU SET file)

SYMB= plots any single alphanumeric character

DOT plots a 1 x 1 box (default)

SLD plots a line, no symbol

**Examples** 

XP= min max div sdiv x-axis plot parameters

min max range of values of the scale; must be used for

xparm and yparm

div number of divisions

sdiv number of subdivisions

YP= min max div sdiv y-axis plot parameters

Remarks Any schema key found in the MD file may be used to set up search

conditions. ROW and COL are valid. Use the MD file original units.

See Also Use command MDL to list the MD file data.

MDSCAT TD T

This entry plots temperature (T) versus dew point (TD) for the current hour. The MD file is from MDU SET file.

MDSCAT TD T MDF=4 ST=WI TIME=18

This entry plots temperature vs. dew point over Wisconsin at 1800 UTC. The data is from ISFC file 4. Temperatures are in Kelvin.

MDSCAT PCP T-TD MDF=2048

This entry plots dew point depression (T-TD) versus 6-hourly precipitation amounts (PCP) over all rows and columns. The data is from MD file 2048.

MDSCAT AV4T/AV5T AV4T-AV5T MDF=9435 ROW=1

This entry plots the ratio between channels 4 and 5 (AV4T/AV5T) versus the difference between these same two channels (AV4T-AV5T) for those values found in the first row. The collocated AVHRR brightness temperatures for each channel are from MD file 9435.

### **MDU**

### MD file utility.

The ADDE commands PTCOPY and PTLIST may be used in place of MDU COPY and MDU LIST respectively. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

#### **Formats**

MDU COPY sfile dfile

MDU DEL bfile efile

MDU DIR file id "comments MDU LIST bfile efile [keyword]

MDU MAKE file schema version nrows ncols id "comments

MDU SET file

#### **Parameters**

COPY

copies the contents of the MD file

DEL

deletes an MD file

DIR

changes a file identification number and comments

LIST

lists the file directory headers

**MAKE** 

makes a new MD file

SET

sets the current MD file number

sfile

source MD file number

dfile

destination MD file number

bfile

beginning MD file number

efile

ending MD file number (default=bfile)

file

MD file number

id

identification number, YYDDD (default=0 if used with

the MAKE option; default=current ID if used with the

DIR option)

"comments

comments added to the file; double quote is mandatory

schema

MD file schema name; for example, IRAB, ISFC

version schema version number; use X for schema defaults

nrows number of rows; use X for schema defaults

ncols number of columns; use X for schema defaults

Keyword DAY= Julian day to list; lists according to created date, YYDDD

Examples MDU COPY 34 6512
This entry copies MD file 34 into MD file 6512.

MDM has menty keywords for fetching and displaying data. They are

MDU DEL 6512 6514
This entry deletes MD files 6512 through 6514.

MDU DIR 6512 91290 "Ship and buoy data This entry changes the ID in the directory of MD file 6512 to 91290 and the comment to Ship and buoy data.

MDU LIST 1 40

This entry lists the MD file directory headers from MD files 1 to 40.

MDU MAKE 1 ISHP 2 X X 91300 "Ship data This entry creates MD file 1 of schema ISHP, version 2, using row and column defaults. It uses the ID of 91300 labeled Ship data.

MDU SET 5
This entry sets the current MD file number to 5. All subsequent MD file commands are performed on MD file 5.

## **MDX**

CLE

Plots, contours or grids data from MD files or grids.

The ADDE commands GRDDISP and PTDISP may be used in place of MDX SOU=GRID and MDX SOU=MDF OUT=PLO respectively.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

restores strings with the specified prefix to their default

#### **Formats**

MDX CLE PREFIX=
MDX LIST PREFIX=
MDX PLT [keywords]
MDX PLT ugrid vgrid [keywords]
MDX grid [keywords]
MDX parm [keywords]

#### **Parameters**

LIST lists the values of the strings with the specified prefix

PLT plots parameters as defined in the prefixed strings

ugrid grid number containing the u component of the wind

vgrid grid number containing the v component of the wind

grid one or more grid numbers of parameters to plot or contour

parm MD file keys or derived parameters; see the Remarks

#### **Keywords**

MDX has many keywords for fetching and displaying data. They are divided into these five groups.

- Parameter keywords control the display characteristics for individual parameters, e.g., color, size, units, scaling.
- Output device keywords control the size of the display and set the output device.
- Grid/contour keywords change the grid size, smoothing and contour interval.
- Map keywords specify maps and projections.
- The miscellaneous keywords perform various functions.

**Parameter Keywords** COLOR= graphics color level of the plotted data graphics; use keyword GCOLOR for contours (default=3) divides the data values before plotting; to multiply, use DIVIDE= a number from 0 to 1 (default=1) FORMAT= FORTRAN format specification for the output (default=I12; character data default=A4) GWIDTH= graphics width, in pixels (default=1) LSIZE= label height, in pixels; if LSIZE=5, all data is plotted; numbers can overwrite each other (default=8) if parameter WNV is specified, a negative LSIZE plots vectors of constant length; if parameter WIN is specified, a positive LSIZE defines a relative length of the wind barb; specify u and vwith the same value MISS= missing data code (default=Z80808080) OFFSET= operates on the data before output (default is DIVIDE=1, OFFSET=0); value = (data-OFFSET)/ DIVIDE; the UNIT keyword uses the DIVIDE and OFFSET PLACE= place to plot the data relative to the station location; the station is located at 41 in a 9 x 9 matrix starting at 1 in the upper-left corner, increasing along a row; use when plotting more than one parameter (default=41) UNIT= units to plot the parameter (default=MD file original units); the possible conversions are: K to C.F MB to INHG MPS, MPH, KT (any) KM, M, CM, MM, MI, NMI, YD, FT, IN (any) plots weather symbols (default=CHAR) **SYMB** graphics element extents (default=depends **Output Keywords** GELE= beg end on screen size) GLINE= graphics line extents (default=depends on beg end screen size) GRA= graphics frame number (default=current) IMA= image frame number (default=current)

OUT= plot (default) CON grid and contour PANEL= graphics panel quadrant; the range is 0 to 4 (default=0, full screen) PELE= beg end text screen/printer element extents (default=1 60 for the text screen; 1 120 for the printer) beg end text screen/printer line extents (default=1 19 for the text screen; 1 60 for the printer) **Grid/Contour** grid contour interval (default=2) Keywords DER= WNV plots wind vectors from grid file data DRAW= YES draws contours after gridding (default) NO does not draw contours GCOLOR= graphics color level (default=2) GRIDF= destination grid file to store grids (default from IGU SET) grid to use as first guess (default=none) **GUESS=** INC= grid increment, in degrees (default=1.0) SMOOTH= smoothing parameter (default=40) Map Keywords LAT= min max minimum and maximum latitude extents LON= min max minimum and maximum longitude extents Midwestern USA MAP= MID North America NA USA USA Post Office abbreviation MCHAR= map character for the text screen/printer output (default=...) MCOLOR= graphics map color level (default=1) 0 for no map

PRO= CONF conformal projection for polar stereographic or Lambert conformal MERC Mercator projection (default) satellite projection

SCALE= map scale ratio for PRO=CONF (default=not true to

scale)

SLAT= lat1 lat2 standard latitude(s); for polar

stereographic specify lat1; for Lambert conformal specify lat1 lat2; used with keyword PRO=CONF (default=60,

polar projection)

SLON= specifies the normal longitude for polar stereographic or

Lambert conformal; used with keyword PRO=CONF

(default=centers longitude of the map limits)

Miscellaneous Keywords DERIVE= use DERIVE=temp dewpoint pressure (elevation)

if THAE, THA or MIX is displayed when the parameter does not appear in the MD file (it will be calculated); use *elevation* with sea level pressure; for SVCA or ISFC

files use: DERIVE=T TD PSL ZS

for RAOB or IRAB files use: DERIVE=T TD P

GRIDF= GRID file number to read (default is from IGU SET)

MDF= MD file number to read; you can combine up to six MD

files using PREFIX= (default is from MDU SET)

PREFIX= MDX stores options and defaults in the system context file with a special prefix at the beginning of the string

name; it can be any character except numeric or #

(default=\$)

If you set up two context files using PREFIX, you can execute these arithmetic operations:

- subtract
- \* multiply
- + add
- / divide
- : catenate

For all operations, except catenate, the MD file must have the same schema; if LAT/LON is not contained in the column header, only I row can be operated on, for example: PREFIX=\$-!

SORT=

of the form: keyword1 loval1 (hival1) keyword2 loval2 (hival2)... etc., selects data from the MD file that meets its conditions; in the SORT=keyword list, do not use an equals sign between keywords and loval, hival; hival is optional if loval is numeric; do not specify hival if loval is alphabetic; keyword is any parameter from an MD file or a ROW and COL number, for example: SORT=TIME 12 13 ST WI

SOU=

MDF

data source is an MD file (default)

GRID

data source is a grid file

#### Remarks

MDX is a flexible routine that plots or contours from any schema MD file or grid. When plotting or contouring ISFC, SVCA, IRAB or RAOB schema MD file data, it is easier to use commands SP, SC, UP and UC. When contouring grid data, it's easier to use the IGTV command.

With each MDX command entry, the information (i.e., parm, time, date, map boundaries, display colors) is stored in strings with a special character prefix. The default prefix is a dollar sign (\$), but you can define a prefix using the PREFIX= keyword with any single character except a pound sign (#) or alphanumeric character.

The most basic command to display data is MDX parm, where parm is any key name in the MD file (use command MDL to list keys), or one of the following derived parameters: ABV, ADV, DVG, MIX, SPD, STR, THA, THAE, VOR, WIN or WNV. The command plots all of this parameter from the current MD file (from MDU SET) on the current graphics frame on a map determined by the limits of the data.

To do anything more with MDX, you must know something about the type of data in the MD file. For example, if you want to plot 500 mb heights for day 91250 at 12Z over the Midwest, you must know that the height, day, and time are referenced through parameters Z, DAY, and TIME in the MD file.

The command to enter (with upper air data in MD file 5000) is:

## MDX Z MAP=MID MDF=5000 SORT=P 500 DAY 91250 TIME 12

When the plus sign (+) is used as the last positional parameter, the command information is stored in the string table, but the data is not plotted. This allows execution of arithmetic operations on the data using the PLT option with the PREFIX= keyword.

4. Plot the temperature from the current surface data for 15Z for a lat/lon box. The MD file is the last digit of the Julian day (if zero, MD=10); today is 91322.

#### MDX T MDF=2 LAT=30 50 LON=90 105 SORT=TIME 15

The above entry doesn't specify only the hourlies (no specials) and degrees C. When MDX is done plotting, enter the command below.

#### EG; MDX T SORT=TIME 15 TYPE 0 UNIT=C

5. Plot a 1000-500 mb thickness over the USA, at 12Z, using MD file 1030, by entering the following command sequence.

MDX CLEAR

MDX Z + SORT=P 500 TIME 12 MAP=USA MDF=1030 PREFIX=\$

MDX CLEAR PREFIX=!

MDX Z + SORT=P 1000 TIME 12 MAP=USA MDF=1030 PREFIX=!

MDX PREFIX=\$-!

6. Take the winds from MD files 2020 and 2045 and grid them for streamlines.

MDX STR + MDF=2020 PREFIX=\$ MDX STR + MDF=2045 PREFIX=! MDX PREFIX=\$:!

 Use THAE, THA, and MIX. It is much easier to use the macros (SP, UP, etc.) to display these derived parameters. When using MDX, an extra keyword, DERIVE, is necessary.

## MDX MIX MDF=3 MAP=MID DERIVE=T TD PSL ZS SORT=TIME 17 DAY 92003 TYPE 0

This entry plots the mixing ratio from the surface data for day 92003.

8. Plot the grid points on the graphics for grid 10, grid file 6512, which contains temperature data.

#### MDX 10 SOU=GRID GRIDF=6512 MAP=MID UNIT=C

9. Plot the wind flags at the grid points for u grid 1 and v grid 2 at 12 GMT.

MDX PLT 1 2 SOU=GRID PRO=SAT SORT=TIME 12

Plot parameters T and TD from MD file 4000 at 12 UTC over Wisconsin.
 Position the temperature above the dew points with the PLACE keyword.
 First, set it up with no plot.

## MDX T TD + MDF=4000 SORT=TIME 12 MAP=WI PLACE=41 50

Now use plot.

#### MDX PLT

destination MID file scheme (definalt=source scheme)

overcosts new destination M.D. als or deletes the destination

11. Plot the u and v component vectors on the graphics from grids 1 and 2.

#### MDX PLT 1 2 SOU=GRID DER=WNV MAP=MID

12. Plot the weather symbols for 18 UTC on day 91301.

## MDX WX1 UNIT=SYMB MDF=1 MAP=MID SORT=TIME 18 TYPE 0 DAY 91301

Revised 5/96

### SENMD2

Sends a mainframe MD file to a workstation.

The ADDE command PTCOPY may be used in place of SENMD2. See the ADDE section of the <u>McIDAS-X</u> or <u>McIDAS-OS2 Users Guide</u> for more information.

**Formats** 

SENMD2 sfile dfile dschema NEW maxrow maxcol [keywords] SENMD2 sfile dfile dschema APP maxrow maxcol [keywords] SENMD2 sfile dfile dschema REP brow maxrow maxcol [keywords]

**Parameters** 

sfile source MD file number on the mainframe (no default)

dfile destination MD file number on the workstation

(default=sfile)

dschema destination MD file schema (default=source schema)

NEW creates a new destination MD file or deletes the destination

file if it exists (default)

APP appends new data to the empty rows following the last

filled row

REP writes new data to brow

maxrow maximum number of rows in the destination file; if not

specified, the search conditions determine the number

of rows in dfile

maximum number of columns in the destination file;

if not specified, the search conditions determine the

number of columns in dfile

brow row number to begin writing new data

**Keywords** 

search conditions=low high may include any keys in the sfile schema

(default=ROW=1, COL=ALL)

#### Remarks

If you create a new destination file using the NEW option, you can use any combination of keys in the source MD file (*sfile*) as search conditions so the destination MD file (*dfile*) contains only needed data. For example, SENMD2 5 10 X NEW TIME=12 T=273 300 TYPE=0 LAT=30 40 LON=80 120 creates workstation MD file 10 containing only the 12 UTC surface hourly data within the specified lat/lon range and temperatures between 273 and 300 K.

You cannot use **ADD** or **REP** to revise destination MD files created using non-header keys as search conditions, for example T=, without completely rewriting the file using the **NEW** option.

Use the APP and REP options only when search conditions include column and row header keys. For example, if mainframe MD file 5 is in the ISFC schema, SENMD2 5 10 X REP 3 24 TIME=2 CO=CN TYPE=0 replaces the data in row 3 of workstation MD file 10 with Canada's 02 UTC surface hourly data.

Specify maxrow and maxcol with the APP and REP options when the scheduler is running the SENMD2 command. The scheduler creates the destination MD file if it does not exist; if it already exists, maxrow and maxcol are ignored. As data cannot be appended to a row greater than maxrow or to a column greater than maxcol, choose these parameters carefully when creating the destination MD file, especially if data will be appended later.

#### See Also

Use command LSCHE to list the keys in the sfile schema.

#### **Examples**

#### **SENMD2 103**

This entry sends the first row in MD file 103 to a workstation in the current directory.

#### SENMD2 10 100 X NEW 72 1250 ROW=1 6

This entry sends rows 1 to 6 from mainframe MD file 10 to workstation MD file 100, which has 72 rows, with 1250 columns in each row.

SENMD2 24 24 IRSG NEW IDN=72000 72999 TIME=12 This entry sends the 12 UTC upper air significant level data for all U.S. stations from mainframe MD file 24 to the same workstation MD file.

#### SENMD2 4 4 X NEW 12 TIME=12 TYPE=0

This entry sends 12 UTC type zero data from mainframe MD file 4 to row 1 of the newly created workstation MD file 4. The new file has 12 rows and the same number of columns in each row as mainframe MD file 4.

#### SENMD2 4 4 X APP TIME=13 23 TYPE=0

subschiler in running the SEDMIP2 command. The schedular courter the

ment reduces wor a so belonging of formula and he were required to the

This entry appends 13 to 23 UTC type zero data from mainframe MD file 4 to workstation MD file 4.

#### SENMD2 3 3 X REP 20 TIME=19 21 TYPE=0

This entry replaces workstation MD file 3 data with data from mainframe MD file 3. The new data (19 to 21 UTC type zero) is written in rows 20 through 22 and overwrites any data previously stored in them.

7-26 Revised 5/96

## **Chapter 8. Gridded Data Files**

CG	Defines the grid header description	.1
COMPGG	Compares grid values to collocated grid values	.2
COMPMG	Compares MD file values to collocated grid values 8-	.5
GMOVIE	Generates a streamline graphics movie	.7
GRDDIR	Grid directory utility	.9
GRDIMG	Generates an area from a grid	11
IGG		12
IGTV	Generates contours and streamlines from grids	17
IGU	Grid file utility	20
IMGGRD	Grids image data 8-	22
SENGRD		25

Revised 6/95

Revised 6/95

### CG

### Defines the grid header description.

**Format** 

CG bgrid egrid [keywords]

**Parameters** 

bgrid beginning grid number

egrid

ending grid number (default=bgrid)

**Keywords** 

DATE= new date, YYDDD (default=current)

GRIDF= grid file number (default=current)

LEVEL= new vertical level (default=current)

NAME = new parameter name (default=current)

SRC= new source program name (default=current)

TIME= new time (default=current)

**Examples** 

CG 10 15 DATE=94236

This entry changes the date in the grid header for grids 10 through 15 in the current grid file to day 94236.

CG 14 TIME=151000 NAME=TD GRIDF=3610

This entry changes the time to 1510 UTC and the parameter name to TD in the header for grid 14 in grid file 3610.

## **COMPGG**

Compares grid values to collocated grid values.

Format COMPGG gridf1 gridf2 gridf2 [keywords]

Parameters gridf1 grid file number containing grid1 (default=current)

grid number 1; the x-axis variable (default=1)

gridf2 grid file number containing grid2 (default=gridf1)

grid2 grid number 2; the y-axis variable

(default=grid1+1)

Keywords COL= min max column limits for grid1 (default=full grid)

**COLOR**= color level of the plot (default=3)

ERASE= YES erases the graphics frame before plotting

(default)

NO does not erase the graphics frame before

plotting

FACTOR= sca1 sca2 internal scaling factors for the grid values

(default=1.0 1.0)

**FORM**= **DIFF** produces a scatter plot display with a zero

line and the grid2 values along the x-axis, and the grid2-grid1 differences along the

y-axis

NONE does not plot (default)

**REGR** produces a scatter plot display with a line of

slope equal to the linear regression results; displays the grid2 values along the x-axis

and the grid1 values along the y-axis

**RESD** produces a scatter plot display with a zero line and the *grid2* values along the x-axis

and the linear regression residuals along

the y-axis

SCAT produces a scatter plot display with a line of

slope=1 and the *grid2* values along the x-axis and the *grid1* values along the y-axis

GRA=	graphics	frame number	(default=current)
------	----------	--------------	-------------------

LAT= min max latitude limits for grid1 (default=full grid)

LON= min max longitude limits for grid1 (default=full grid)

MAX= upper limit threshold (default=grid1 maximum)

MIN= lower limit threshold (default=grid1 minimum)

ROW= min max row limits for grid1 (default=full grid)

SYMB= plot symbol; can be any single alphanumeric character

DOT 1x1 box (default)
SLD line, no symbol

XL= x-axis label; up to 12 characters (default=X)

XP= min max div sdiv

x-axis (GD1 file) plot parameters; div is the number of

divisions; sdiv is the number of subdivisions

YL= y-axis label; up to 12 characters (default=Y)

YP= min max div sdiv

y-axis (GD2 file) plot parameters; div is the number of

divisions; sdiv is the number of subdivisions

#### Remarks

The values of *grid2* are collocated relative to the values of *grid1*. Several different sets of comparison statistics representing descriptive (univariate), difference (bivariate), and correlation (regression) statistical measures are displayed to the text screen, regardless of the graphics display format section.

#### **Examples**

#### COMPGG

This entry compares the grid values of the first and second grids in the current grid file. It does not plot the values.

#### COMPGG 2048 34 2049 34 FORM=SCAT

This entry compares the grid values from the thirty-fourth grid in grid file 2048 and the thirty-fourth grid in grid file 2049. A full set of descriptive (univariate), difference (bivariate), and correlation (regression) statistics are displayed on the text screen, while a scatter plot of the two sets of grid values are displayed on the current graphics frame along with a line representing a "perfect" correlation (slope=1). Data values are plotted with a small square symbol.

COMPGG 216 70 13 1 FORM=REGR SYMB=\* ROW=20 30 COL=1 20 MIN=230 MAX=280 XP=220 300 5 10 YP=220 300 5 10 GRA=15

This entry compares the grid values of an NGM model 500 mb temperature 12 UTC forecast from the 12 UTC run in grid file 216, grid 70 to a radiosonde observation of 500 mb temperature in grid file 13, grid 1. It plots a scatter plot with a line of slope equal to the linear regression result. The values compared are limited to those grid points between rows 20 to 30 and columns 1 to 20 from the NGM 500 temperature 12 UTC forecast grid, and the collocated grids in the RAOB observation. The lower limit value threshold is set to 230° K; the upper limit threshold is set to 280° K. Data values are plotted with the asterisk (\*) symbol. X- and y-axis values plotted between 220 and 300° K are divided into 5 intervals with 10 subdivisions. The comparison statistics are displayed on the text screen. The scatter plot is displayed on graphics frame 15.

## COMPMG

Compares MD file values to collocated grid values.

Format COMPMG parm level mdf gridf grid [keywords]

Parameters parm MD file variable parameter, e.g., T, TD, SPD, DIR, Z, etc.

level MD file level parameter, e.g., SFC, TRO, 1000, 850,

700, etc.

mdf MD file number (default=current)

gridf grid file number (default=current)

grid number (default=1)

Keywords COLOR= color level of the plot (default=3)

ERASE= YES erases the graphics frame before plotting

(default)

NO does not erase the graphics frame before

plotting

**FACTOR**= internal scaling factor for grid values (default=1.0)

FORM= DIFF produces a scatter plot display with a zero

line and the grid values along the x-axis and the MD file minus the grid differences along

the y-axis

NONE does not plot (default)

**REGR** produces a scatter plot display with a line of

slope equal to the linear regression results; displays the grid values along the x-axis and

the MD file values along the y-axis

RESD produces a scatter plot display with a zero

line and the grid values along the x-axis and the linear regression residuals along the

y-axis

SCAT produces a scatter plot display with a line of

slope=1 and the grid values along the x-axis

and the MD file values along the y-axis

GCOL= min max grid column limits (default=full grid)

GRA= graphics frame (default=current)

GROW= min max grid row limits (default=full grid)

MAX= upper limit grid value threshold (default=grid max)

MIN= lower limit grid value threshold (default=grid min)

SYMB= plot symbol; can be any single alphanumeric character

DOT 1x1 box (default)
SLD line, no symbol

XL= x-axis label; up to 12 characters (default=GDF//TYPE//LEVEL)

XP= min max div sdiv

x-axis (GDF file) plot parameters; div is the number of

divisions; sdiv is the number of subdivisions

YL= y-axis label; up to 12 characters (default=MDF//TYPE//LEVEL)

YP= min max div sdiv

y-axis (MDF file) plot parameters; div is the number of

divisions; sdiv is the number of subdivisions

#### Remarks

Grid values are collocated relative to MD file station locations. Several different comparison statistics representing descriptive (univariate), difference (bivariate), and correlation (regression) statistical measures are displayed on the text screen, regardless of the graphics display format selection. MD file parm values are quality controlled for bad data by establishing thresholds of  $\pm$  33% of the grid min/max values.

#### **Examples**

#### COMPMG T 500 2048 2048 34 FORM=REGR ROW=5 COL=1 100

This entry compares the 500 mb temperature radiosonde data from MD history file 2048 contained in its fifth row and between columns 1 and 100 to the grid values from the thirty-fourth grid of grid file 2048. A full set of descriptive (univariate), difference (bivariate), and correlation (regression) statistics are displayed. The scatter plot of values is displayed on the current graphics frame along with a line of slope equal to the linear regression coefficient between the two sets of values.

#### COMPMG T 500 18 208 70 FORM=SCAT TIME=0 XL=0UTC 12VT NGM YL=0UTC RAOB GRA=15

This entry compares 0 UTC 500 mb temperature radiosonde data from MD file 18 to an NGM model (500 mb temperature) 12 UTC forecast from the 0 UTC run. It produces a scatter plot with the x-axis labeled 0 UTC 12VT NGM and the y-axis labeled 0 UTC RAOB. The scatter plot is displayed on graphics frame 15. The comparison statistics are displayed on the text screen.

Generates a streamline graphics movie.

GMOVIE grid interval map [keywords]

**Parameters** 

grid

u-component grid number

interval

contour interval (default=2)

map

DEF define your map boundaries using keywords

LAT and LON

SAT

satellite projection

NONE

no map

US region

NTE for Northeast, STE for Southeast, NTC

for North central, STC for South central, W for

Wisconsin, etc.

State Post Office abbreviation

Keywords

min max

graphics TV element limits

GRA=

graphics frame number to draw on (default=current)

GRAY=

low high

graphics color levels to use

GRIDF=

grid file number containing the grid (default=current)

GWIDTH=

graphics width, in pixels (default=current)

LAT=

min max

latitude limits; use with DEF map

LIN=

min max

graphics TV line limits

LON=

min max

longitude limits; use with DEF map

PAN=

panel number; the range is 1 to 4

RANG=

low high

range of grid values for use with keyword

SLEN

SLEN=

min max

line segment lengths based on keyword

RANG (default=2 40)

#### Remarks

Use command GU to change graphics color levels. Use command GMOVIE to generate a streamline graphics movie. Use command CM in the local mode to run (step through) the graphics movie created by GMOVIE. This series of commands allows you to convert gridded data to graphics levels, load them into the current frame (or the frame you specify), and run them as a streamline graphics movie.

If parameter map is DEF, you must specify keywords LAT and LON.

#### **Examples**

#### **GMOVIE 25 X USA**

This entry creates a streamline graphics movie using the u-component grid 25 in the USA map projection. The V-grid is number 26.

Use the three commands below to change the graphics color level and generate and run a streamline graphics movie. Run command CM in the local mode.

#### **GU MAKE 5 RED**

This entry defines graphics color level 5 as red.

#### GMOVIE 14 4 DEF LAT=30 50 LON=80 110

This entry generates a streamline graphics movie using grid 14, with an interval of 4. It defines the map boundaries with latitudes ranging from 30° to 50° North and longitudes ranging from 80° to 110° West.

#### CM 1 6 INT=12

This entry steps through a streamline graphics movie, coloring graphics levels 1 to 6, with a timing interval of 12 milliseconds between each level.

## **GRDDIR**

### Grid directory utility.

Format	GRDDIR	R file grid [keywords]					
Parameters	file	grid file number (default=current)					
	grid	grid number (default=1)					
Keywords	COL=	beg end	beginning and ending column limits (default=1 maximum column)				
	FORM=	EXP	lists the grid header directory in expanded format (default)				
		ALL NO	lists all 64 words of the grid header suppresses the grid header directory listing				
	HIST=	YES NO	lists a grid point value histogram analysis suppresses a grid point value histogram analysis (default)				
	ROW=	beg end	beginning and ending row limits (default=1 maximum row)				
	STAT=	YES NO	lists grid point summary statistics (default) suppresses grid point summary statistics				
	VAL=	YES NO	lists individual grid point values suppresses the list of individual grid point values (default)				

#### Remarks

The statistics, histogram and value options are exercised only over the specified row and column bounds.

GRDDIR accesses the grid header and/or grid point values in text form. It is meant to supplement IGG LIST, not supersede it. GRDDIR lists grid point statistics and/or histogram analysis of the grid point value's distribution.

#### **Examples**

#### **GRDDIR**

This entry lists the grid header directory in expanded format for grid 1 of the current grid file. It also lists the grid value summary statistics for all grid points on grid 1 of the current grid file.

#### GRDDIR 30 16 VAL=YES ROW=1 5 COL=1 10

This entry lists the grid header directory in expanded format for grid 16 of grid file 30. It lists grid point summary statistics and individual grid point values for rows 1 through 5 and columns 1 through 10 in grid 16 of grid file 30.

#### GRDDIR X X FORM=ALL HIST=YES

This entry lists all 64 words of the grid header for grid 1 of the current grid file. It lists a grid point value histogram for all points in grid 1 of the current grid file.

## **GRDIMG**

### Generates an area from a grid.

Format GRDIMG grid area rmag cmag [keywords]

Parameters grid source grid number

area destination area number

rmag grid row magnification factor (default=1)

cmag grid column magnification factor (default=1)

Keywords COL= beg end beginning and ending column limits (default=1 maximum column)

GRIDF= grid file number (default=current file set by IGU SET gridf)

RANGE= loval hival britlo brithi

specifies the range of grid and brightness values

loval low grid data value (default=minimum value)
hival high grid data value (default=maximum value)
britlo low pixel brightness value (default=0)

brithi high pixel brightness value (default=255)

ROW= beg end beginning and ending row limits (default=1 maximum row)

Use keyword COL to define a data subset. The maximum element size is 2000. Use a smaller column magnification or COL if an error results.

Examples GRDIMG 11 360

This entry uses grid 11 data to generate area 360 using the minimum and maximum grid values to determine the pixel brightness range. All other values are stretched within this range.

GRDIMG 1 5000 RANGE=270 300

This entry uses grid 1 data to generate area 5000. The temperatures from 270° to 300° K take on values ranging from 0 to 255. All values below 270 are 0; those above 300 are 255.

Remarks

## **IGG**

Grid utility.

The ADDE commands GRDCOPY and GRDLIST may be used in place of IGG GET and IGG LIST respectively. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Formats** 

IGG DEL bgrid egrid [keywords]

IGG LIST bgrid egrid [keywords]

IGG GET sgridf bgrid egrid dgridf bgrid

IGG MAKE grid1 option1 ... gridn optionn [keywords] "comment

IGG PACK sgridf

IGG DIR bgrid egrid "comment

**Parameters** 

DEL

deletes grids

LIST

lists grids

GET

copies grids from one file to another or within the same file

MAKE

arithmetic operations performed on grids;

see option below

**PACK** 

sequentially renumbers the grids

DIR

creates a grid directory

bgrid

beginning grid number

egrid

ending grid number

sgridf

source grid file number (default=terminal number or

from IGU SET gridf)

dgridf

destination grid file number

grid1 ... n

a grid number

"comment

comment appended to the grid directory; up to 48

characters

option 1 ... n

ABV

creates a grid of vorticity when the grid is u-comp

(grid + 1 = v-comp) with the coriolis force; the second grid in the command is not used;

units are 10<sup>-5</sup>sec<sup>-1</sup>; see keyword V

a a grid with the specifications of to rich but fills it with the conservation ad for the second, e.g., MAR 13	ADD	adds grids on a point-by-point basis, or adds a constant to a grid; see the Remarks
s u and v converged grids of the ophic wind idf most be a acrylis		advects the parameter specified as the second grid by the wind of the first grid; u-comp assumes grid + 1 = v-comp; see keyword V
olies a grid by anniher grad or a not see the literately		averages grids
tes EMS and bins afterences of twi- l grid.  s a good of wind speed, grid inport in		changes all input grid points with values greater than the specified constant to that constant in the output grid; grid points with values less than the constant are not changed; see the Remarks
	CHLT	changes all input grid points with values less than the specified constant to that constant in the output grid; grid points with values greater than the constant are not changed; see the Remarks
ete a grid from another grid or a me use the Remerks  as grid of vortedly when the grid o		compares two grids for overlapping values; for the threat score, the second grid should be followed by two numbers that specify the range of values to include e.g., MAK 12 COM 18 -500 500
id <sup>14</sup> ; the geomid grad in the con men uned; see keyword V		creates a grid of the coriolis force using the boundaries of grid 1
ir meridional flow; only works with displayers DVC and DST (default) acreet for meridional flow		divides a grid by another grid or a constant; see the Remarks
	DSH	is not used; see keyword V
	DST	
		creates a grid of divergence when the grid

creates a grid of divergence when the grid is u-comp (grid + 1 = v-comp); units are 10<sup>-6</sup> sec<sup>-1</sup>; if you specify a second grid, the divergence of that parameter is computed; if the second grid is zero, type ZERO for that grid; see keyword V

ent to a great suc the freeze or adds a		creates a grid with the specifications of the first grid but fills it with the constant value specified for the second, e.g., MAK 12
	d Jurin	creates u and v component grids of the geostrophic wind; grid1 must be a height grid
	MPY	multiplies a grid by another grid or a constant; see the Remarks
		computes RMS and bias differences of two named grids
	SPD	creates a grid of wind speed; grid input is u-comp (grid + 1= v-comp); the second grid
		is not used; it is not linked to u and v grids;
		it can be used with any two successive grids to reproduce a grid of the square root of the
		sum of the squares; see keyword V
		sum of the squares, see keyword v
6,171	SQR	for square root; only applies to the first grid
tern two gride for court, aping values; e blamat scare, the court grad d'heathle wid by two norders that	SOB	subtracts a grid from another grid or a constant; see the Remarks
		creates a grid of vorticity when the grid is u-comp (grid + 1 = v-comp); units are $10^{-6}$ sec <sup>-1</sup> ; the second grid in the command
that grid of the combine force vising this name of critical		is not used; see keyword V
Keywords ADD=		corrects for meridional flow; only works with
		the derived options DVG and DST (default)
	NO	does not correct for meridional flow
	sorts t	he list by day(s); use with the LIST parameter
V heavy yazt been theen		-tiilh f th- MAKEti
DGRID=		ation grid number for the MAKE option lt=next available grid)
formation evetch when the grid is		it-next available grid)
FORM=	ALL	lists the grid header and directory; allows an individual directory explanation for each grid; use with the LIST parameter
ente atique de mouve a + birmi que		
GRIDF=		le to work on (default=from IGU SET gridf)
	labels	the resulting grid (default depends on operation)
LEV=		he list by level(s); use with the LIST parameter

NAME=	sorts the list by parameter; use with the LIST parameter
SMO=	YES smoothes the resulting grid; only works with the derived options ABV, DVG, VOR, ADB, DST and DSH (default)
lots Phalif.	NO does not smooth the resulting grid
SRC=	sorts the list by data source; use with LIST parameter
TIME=	sorts the list by time(s); use with LIST parameter
V=	number of the v grid to input if it does not follow the u grid (default=u grid + 1)
VT=	sorts the list by valid time(s); use with LIST parameter

#### Remarks

To apply a constant to an arithmetic function (ADD, SUB, MPY, DIV), enter a negative number for the second named *grid*. The absolute value of this number is used as a constant.

In the CHLT and CHGT options, the number specified for the second named grid parameter (gridn) is used as a constant. Input grid point values less than (CHLT option) or greater than (CHGT option) this constant are changed to the constant in the output grid.

A sample output of command IGG LIST is shown below followed by the column definitions.

GRID FILE: 114	**				**	SPACE UN	NUSED:83	77986
# YYDDD HHMMSS	NAME	LEVEL	SRC	VT NR	NC	LLNW	ROWINC	COLING
1 92353 170000	T	SFC	MDX	0 17	22	50/104	1.0000	1.0000

Column	Definition
#	grid number
YYDDD	year, Julian day
HHMMSS	hours, minutes, seconds of the grid
NAME	name of the gridded parameter
LEVEL	description of the atmospheric level and units
SRC	name of the program that generates the grid
VT	hours that the forecast grid is valid after generation
NR	number of rows in the grid
NC	number of columns in the grid
LLNW	latitude and longitude of the upper-left corner
ROWINC	row grid spacing, in degrees
COLINC	column grid spacing, in degrees

#### See Also

See commands IGTV and MDX to plot and contour grid point values.

### **Examples**

ends (tropage TDF

#### IGG LIST

This entry lists all the grids in your workstation's current grid file.

#### IGG DEL

This entry deletes grid one in the current grid file.

# IGG DIR 1 "Dew Point Depression Field

This entry attaches the grid description Dew Point Depression Field to grid 1.

#### IGG GET 10 5 7 20 1

This entry moves grids 5 to 7 from grid file 10 into grid file 20, beginning at grid 1.

### IGG LIST 1 10 FORM=ALL

This entry lists the first 10 grids from the current grid file including the grid directory.

# IGG LIST 1 20

This entry lists all grids from 1 to 20.

#### IGG MAKE 2 SUB 1

This entry makes a new grid by subtracting grid 1 from 2.

#### IGG MAKE 2 MPY -4 ADD 5 DIV -60

This entry multiplies each grid point in grid 2 by the constant 4, adds them to grid 5 and divides by the constant 60. The new grid number is generated in the next available location.

# IGG MAKE 3 ADV 1 "Temperature Advection

This entry makes an advection field from u and v grids 3 and 4 with grid 1 and places the result in the first empty grid with the comment field in the directory.

IGG LIST SRC=NGM VT=12 36 LEV=500 850 GRIDF=201 This entry lists all the 500-850 mb grids in grid file 201 for the 12 through 36 hour forecasts for the NGM model.

IGG LIST LEV=SFC TIME=15 18 DAY=91020 GRIDF=9630 This entry lists all the surface grids in grid file 9630 for the time period 15 through 18 UTC.

## IGG MAKE 100 CHLT 273

saulay into airg amenica bas toly at ECIA bas VIII shasa uro out

This entry creates a new grid by checking each grid point value in grid 100 and changing all the grid points with values less than 273 to 273. The grid points with values greater than 273 are not changed.

# **IGTV**

grid

Generates contours and streamlines from grids.

The ADDE command GRDDISP may be used in place of IGTV.

See the ADDE section of the <u>McIDAS-X</u> or <u>McIDAS-OS2 Users Guide</u>
for more information.

**Format** 

IGTV grid interval map output [keywords]

**Parameters** 

number of the grid to contour; see keyword V and the Remarks for drawing streamlines or contouring the wind's u-component or v-component

interval contour interval; use integer values 1 through 10 or a multiple of 10 (default=2)
or enter a string name that contains up to 64 values

map DEF defines your own boundaries; use the LAT and

LON keywords

MID Midwest USA map

NA North America map

NONE does not draw a map

SAT satellite projection

USA USA map

State Post Office abbreviation (default is the grid domain)

output if DEV=C or P, use 1 to displays contours, 2 to display the grid and contours, or 3 to display grid points on the text screen or printer

Keywords CMAP= graphics color level for the map (default=1)

COLOR= graphics color level for the contours; use positive numbers for solid lines and negative numbers for dashed lines; no map is drawn with negative numbers (default=2)

POS dash negative contours only dash positive contours only dash all contours

ELE= min max graphics TV element bounds

GRA= graphics frame to display the plot (default=current)

GRIDF= grid file number (default=current)

IMA= image frame number (default=current)

LAT= min max minimum and maximum latitude extents

LIN= min max graphics TV line bounds

LINT= contour label interval (default=1)

LON= min max minimum and maximum longitude extents

LSIZE= height of the contour labels in pixels (default=7)

MAG= magnifies the data by an order of magnitude (default=0)

PAN= graphics frame panel number; the range is 1 to 4

PRO= MERC Mercator projection
CONF conformal projection
(default is the grid projection)

SCALE= map scale for a CONF projection; values up to 1000 are multiplied by 1,000,000 (default=no scale)

SLAT= lat1 lat2 standard latitude; for polar stereographic specify lat1; for Lambert conformal specify lat1 lat2 (default=60, polar projection)

SLON= lon normal longitude; for polar stereographic and Lambert conformal, e.g., PRO=CONF (default=center longitude of the map limits)

TEXT= YES plots the grid text label (default)
NO does not plot the grid text label

DIR prints the grid text label and directory information

UNIT= contour units; depends on the contoured parameters

V= number of the v-component grid; used for drawing streamlines; see the Remarks (default = u-grid + 1)

#### Remarks

IGTV does not generate gridded data. Use commands MDX, SC, UC, etc., to generate the grids. Use commands IGG and IGU to manipulate grids and grid files.

IGTV allows for map scales up to 10<sup>8</sup>. Values entered should be integers less than 1000. The scale value is this integer multiplied by 1,000,000, so SCALE=33 gives a 33,000,000:1 scale.

To draw streamlines, specify the u-component grid number as *grid*, and the v-component grid number in the keyword V. To contour the wind's u-component, specify its grid number as *grid* and specify V=0. To contour the wind's v-component, just specify its grid number as *grid*.

IGTV defines grid point values outside the lat/lon domain as missing values. Since the contouring routine will not draw to a missing value, if the lat/lon limits are not defined as exact multiples of the grid lat/lon increments offset from the NW corner lat/lon, the contours may not be drawn to the edges of the map domain, but only to the last available grid point.

# **Examples**

### IGTV 7

This entry contours grid 7 and displays it with a contour interval of 2.

### IGTV 5 X X 3 DEV=P

This entry prints the grid points from grid 5.

#### IGTV 2 X MID 2 DEV=C

This entry displays the grid points and contours from grid 2 over the Midwest.

## IGTV 17 4 USA PRO=CONF SLAT=25 50 SCALE=10

This entry displays the contours from grid 17 with a contour interval of 4. The map is a Lambert conformal projection of the USA with standard latitudes of 25° N and 50° N. The map is scaled 10,000,000 to 1.

# IGTV 3 10 USA DASH=NEG GRIDF=14

This entry displays the contours from grid 3 in grid file 14 on a USA Mercator projection, using a contour interval of 10 with dashed negative values.

#### IGTV 23 4 USA MAG=2

This entry displays the contours from grid 23 on a USA map using a contour interval of 4. Grid 23 is a precipitation grid with values in one-hundredths of an inch. The MAG=2 allows IGTV to contour the values to one-hundredth of an inch by magnifying the data by 10\*\*2. Therefore, a data value of 0.04 inches is contoured on the screen as a 4; a data value of 0.08 inches is contoured as an 8, etc.

Create the following string called LEV:

TE LEV "30 50 60 65 80

Then use IGTV to contour the grid:

#### IGTV 1 LEV MID UNIT=F

This entry contours only the 30, 50, 60, 65 and 80 degree isotherms. In this special feature of IGTV, there is no pound sign before the string name, i.e., #LEV.

# IGU

# Grid file utility.

The ADDE command GRDCOPY may be used in place of IGU COPY and IGU MAKE. The ADDE command GRDLIST may be used in place of IGU LIST. See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

## **Formats**

IGU LIST bgridf egridf [keywords]

IGU DEL bgridf egridf

IGU SET gridf

IGU COPY sgridf dgridf RENUMBER

IGU MAKE gridf maxgrd "text
IGU DIR gridf date project "text

#### **Parameters**

LIST lists a directory on the text screen

DEL deletes a grid file

SET sets the current grid file number

COPY copies a grid file

MAKE generates a grid file

DIR modifies a directory for a grid file

RENUMBER renumbers grids after copying a file

bgridf beginning grid file number

egridf ending grid file number

gridf grid file number

sgridf source grid file number

dgridf destination grid file number

maxgrd maximum number of grids in the grid file

(default=159)

date date the grid file was generated (default=current)

project your project number (default=current)

"text identification text for the grid file; the double quote

is mandatory

Keywords DAY= lists the grid files with this date or range of dates, YYDDD

**PROJ**= lists the grid files with this project number or range of

project numbers

Remarks There is no practical limit to the number of grids that can be stored in a

grid file. Maxgrd defaults to 159 and could be much larger.

Default grid files (those matching the terminal number) can only be

deleted from terminal 0.

Examples IGU LIST

This entry lists grid file 1.

IGU DEL

This entry deletes grid file 1.

oclaspound in a be cla too (defin

IGU SET

This entry sets the current grid file number.

IGU LIST 1000 1020 DAY=92100

This entry lists the grid files from 1000 to 1020 for day 100 in 1992.

IGU COPY 1000 2000 RENUMBER

This entry copies grid file 1000 into grid file 2000, renumbering the grids

to compact the file.

IGU SET 2000

This entry points at grid file 2000. All subsequent grid operations are

performed on file 2000 unless another IGU SET is run.

IGU MAKE 7000 200 "Test Grids

This entry generates grid file 7000 and allocates space for 200 grids. The grid file is labeled Test Grids. Use IGG GET to copy grids from

another grid file.

# **IMGGRD**

# Grids image data.

	a tradition of the Alle			
Format	IMGGRD fra	me dgridf [	[keywords] "text	
Parameters of medical and a	frame	source fran	ne number (default=current)	
nur ie. ean only be	dgridf	destination	n grid file number (default=current)	
ou spine and the same	"text		g label in the grid directory words 43-50; er maximum (no default)	
Keywords	AREA=	backgroun	per to grid; enables the command to run in the d in a batch job (default=area number in the ne directory)	
	BAND=	band number to grid (default=from the frame directory; if an area number is specified, the band number is the lowest numbered band)		
.865 or 001 year of	FACTOR=		aling factor appropriate for the calibration ult=10.0 for TEMP and 1.0 for all others)	
		AVG averages the pixel values in a grid box centered on the grid points (default)  SUM sums the same subsets of pixel values  STD generates standard deviations of these same subsets of pixel values; any or all values may be used regardless of their order		
	INC=	latitude/lo	ngitude grid increment, real value (default=1.0)	
	LAT= bird	min max	latitude grid limits (default=current frame; when keyword AREA is used, default=frame directory)	
	LON=	min max	longitude grid limits (default=current frame; when keyword AREA is used, default=frame directory)	
	UNIT=	BRIT TEMP RAD RAW	output calibration-type brightness values (default) temperature values radiance values raw values; typically has an associated calibration codicil for image display	

ZERO= DATA assigns zero pixel values as data and

includes them in the analysis

MISS assigns zero pixel values as missing and

excludes them from the analysis (default)

a nonzero numeric value identifies that pixel value to

represent the missing value flag

## Remarks

Command IMGGRD objectively analyzes an area and stores the results, with navigation parameters, in a grid. This grid can be displayed and/or further manipulated using the appropriate McIDAS gridded data file commands.

IMGGRD can be costly to run on large areas due to the many calculations. To reduce CPU time, use the REMAP command to reduce the image resolution. Reducing a 1 KM image to 4 KM (8 KM) resolution reduces the CPU time by a factor of 16 (or 64) without significantly altering the representation of a 1 x 1 degree grid.

Images stored in a MERC projection are processed much faster by the program. Use the REMAP command to convert an image to a MERC projection.

The maximum allowable grid size is 60 K grid points. Grid points off the image are assigned missing values.

Multiple IMGGRD commands can be run using a higher grid resolution to cover a large area.

A pseudo-Mercator projection is used for GOES imagery and ascending and descending POES orbital imagery. A polar stereographic projection is used for POES orbital imagery over the North or South Pole.

Grid analyses of area data are poor near earth edge boundaries. IMGGRD cannot process areas that have data surrounded by areas of no data, i.e., a 200-line by 200-element section of good data centered in a 540 by 600 area. Use the LAT and LON keywords to avoid this situation.

#### **Examples**

#### **IMGGRD**

This entry grids brightness counts from the area displayed on the current image frame onto a 1 x 1 degree grid which covers the latitude and longitude range of the displayed image. The analyzed grid of average brightness counts is stored in the first available grid of the current grid file. The grid file can be set using command: IGU SET gridf.

#### **IMGGRD 11 2048**

This entry is similar to the first example, except the image currently displayed on frame 11 is gridded and stored in the first available grid of grid file 2048.

## IMGGRD 11 2048 INC=0.5 LAT=-15 1 LON=40 85

This entry is similar to the second example, except the grid domain is defined to cover a region between (15° S, 40° W) and (1° N, 85° W) with a 0.5 degree increment.

# IMGGRD X 2048 AREA=2060 BAND=10 INC=0.5 LAT=-15 1 LON=40 85

This entry is similar to the above example, except it grids band 10 from area 2060.

# IMGGRD 11 2048 FORM=AVG STD UNIT=TEMP INC=0.1 LAT=44 45 LON=89 90

This entry grids a very small region of the image displayed on frame 11 with high resolution in temperature units and stores both the analyzed pixel temperature averages and standard deviations in grid file 2048.

# SENGRD

Sends a grid from a mainframe to your workstation or another mainframe.

The ADDE command GRDCOPY may be used in place of SENGRD. See the ADDE section of the <u>McIDAS-X</u> or <u>McIDAS-OS2 Users Guide</u> for more information.

**Formats** 

SENGRD sgridf ALL dgridf dgrid [keywords]
SENGRD sgridf bgrid egrid dgridf dgrid [keywords]

**Parameters** 

sgridf source grid file number (no default)

ALL sends all grids in the grid file

bgrid beginning grid to send (no default)

egrid ending grid to send (default=bgrid)

dgridf destination grid file number on the workstation or

mainframe (no default)

dgrid destination grid number in the workstation or mainframe

grid file (default=1)

Keywords

**APPEND=** YES appends grids onto dgridf (default)

NO overwrites existing grids in dgridf beginning

at dgrid

**DEL=** YES deletes dgridf prior to transfer of the data

NO doesn't delete dgridf (default)

MAXGRD= maximum number of grids in the grid file on the

workstation or mainframe (default=159)

Remarks

Command SENGRD reads a McIDAS grid from a McIDAS-MVS grid file, compresses the data, and sends the grid file header, grid header (uncompressed), and gridded data (compressed) via SENOUT calls, to a workstation or another mainframe.

Run SENGRD on the mainframe containing the source grid.

# **Examples**

#### SENGRD 3610 ALL 1000

This entry copies all grids in the McIDAS-MVS grid file 3610 to the workstation grid file 1000.

#### SENGRD 4960 3 12 2000 5

This entry copies grids 3 to 12 in the McIDAS-MVS grid file 4960 to the workstation grid file 2000, beginning at grid 5.

#### SENGRD 201 1 300 50 1 MAXGRD=500

This entry sends grids 1 to 300 from grid file 201 to destination grid file 50 on the workstation. When the grid file is created on the workstation, it allocates slots for 500 grids.

Remorks \*

# **Chapter 9. Weather Analysis**

FASTXT	Fast listing for weather text and observations	9-1
FC	Lists short-range TAF forecasts	9-5
FOUSL	Lists FOUS14 data	9-6
FOUSP	Plots or contours FOUS14 data	9-7
FT	Lists terminal aviation forecasts	9-9
FTL	Lists US and Canadian terminal forecasts	9-10
HGTSUR	Interpolates an upper air sounding to standard altimeter settings	9-11
HODO	Plots a wind sounding hodograph	9-13
ISC	Grids and contours isentropic data	9-15
ISENT	Calculates theta surface levels for upper air data	9-17
ISP	Plots isentropic data	9-19
LIST4D	Lists the contents of the 4-D trajectory analyses	9-21
MDR	Grids manually digitized radar data	9-22
MDRIMG	Displays a USA image from manually digitized radar data	9-23
MDRPLT	Plots manually digitized radar data	9-24
MG	Plots a 24-hour surface meteorogram	9-26
MGXS	Plots a meteorogram cross section	9-28
MKMAND	Derives upper air mandatory levels from significant levels	9-30
MR	Plots a 4-day upper air meteorogram	9-31
NMCL	Lists NMC grids	9-33
NMCX	Contours or plots NMC grids	9-35
SAO	Lists SA data	9-38
SC	Grids and contours surface data	9-40
SHEAR		9-43
SHIPC	Grids and contours ship and surface data	9-44
SHIPP	Plots surface and ship data	9-46
SKEWT		9-48
SL		9-51
SP		9-55
STAB		9-58
STABIL		9-59
STG		9-60
STUVE		9-62
TAF		9-64
TEXT		9-65
UC	Grids and contours upper air data	9-68
UL		9-71
UP		9-73
VAS4D		9-75
WWLIST		9-76
WWPLOT		9-77
XSECT		9-78

Revised 6/95

15.8

ii

Revised 6/95

# **FASTXT**

Fast listing for weather text and observations.

The ADDE command WXTLIST may be used in place of FASTXT.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Formats** 

FASTXT ADD product [keywords] "text

FASTXT DEL product [keywords]

FASTXT EDIT product [keywords]

FASTXT LIST product [keywords]

FASTXT group1 [keywords]

FASTXT group2 [keywords]

FASTXT group2 id [keywords]

FASTXT group3 id dtime [keywords]

**Parameters** 

ADD adds a product code

DEL deletes a product code

**EDIT** edits search conditions for an existing product code

LIST lists all system and current user defined product codes,

AFOS headers and alias names (default)

product 3-character product code

"text text describing the product

group 1 3-character AFOS header or alias name for any of the

following national products: EON, EPD, ERD, HMD,

HSD, NWX, PMD, PWO, SCS, SWO

group2 3-character AFOS header or alias name for any of the

following local, state or regional products: CCF, CLI, EFP,

 $LFP,\,NOW,\,RER,\,RNS,\,RWS,\,SFD,\,SFP,\,SPS,\,STO,\,STP,$ 

SVS, SWR, SWS, ZFP

group3 3-character AFOS header or alias name for any of the

following time-dependent products: ADM, FFW, FLW,

LSR, SCC, SVR, TOR

id station ID or 2-letter state abbreviation (default differs

between group2 and group3; see the Remarks)

dtime number of hours back from the current time to search

(default=1)

Keywords ALIAS= alias name for the product code

DAY= Julian day to begin the search, YYDDD (default=current)

DELWMO= deletes the specified WMO header from the product

description

**DTIME**= number of hours before the current hour to search

FIL= LW file name containing the product code descriptions

(default=FASTXTINFO)

ID= station ID in the WMO header line

IND= index file to use for defining new products

MAT= secondary match string for the search

NUM= number of matches to find; not valid with group3

(default=1)

OWNER= lists or deletes products created by the specified user

(default=system and current user defined products)

WMO= 5- or 6-character WMO headers to search; used with

the ADD and EDIT options

Remarks FAST:

FASTXT uses data decoded by the sequential index filing system (SIFS).

FASTXT has a limited number of product options, whereas the TEXT command is more flexible. The main benefits of FASTXT include its ease of use and its ability to return results much faster because it uses the filing system more efficiently than the TEXT command.

You can add product codes to the existing list of system defined product codes. To do this, you must know the complete WMO (World Meteorological Organization) header of the product. The WMO header is the first 5 or 6 characters of a product displayed with the TEXT command using the HEAD=YES option. You can edit and delete only the product codes that you create. To list your product codes, use the OWNER keyword with your initials. Product codes created by other users can also be listed with this keyword.

User created product codes that include a search value for keyword ID and do not have a value for keyword DTIME are listed under group1, national products. Product codes that have no search values for ID or DTIME are listed under group2, local products. Any product that has a search value for DTIME is listed under group3, time dependent products.

If no ID is specified with *group2*, FASTXT matches the most recent report issued. If no ID is specified with *group3*, FASTXT lists all reports issued during the last *dtime* hours.

FASTXT limits its search to the line containing the WMO header. For example, you cannot make a product code such as SAO which scans for surface hourly reports for a specific station. This is because the station ID on the WMO header line is not the ID of the reporting station.

# **Examples**

# FASTXT TO SECOND OUT OF THE REAL PROPERTY.

This entry lists all currently defined product options, AFOS headers and alias names.

#### FASTXT LFP

This entry lists the most recent local forecast on the system.

## FASTXT LFP MSN NUM=3

This entry lists the last three local forecasts issued for Madison, Wisconsin.

#### FASTXT LOCAL AZ

This entry lists the last local forecast issued for each forecast station in Arizona.

#### FASTXT SVR X 6

This entry lists all severe thunderstorm warnings issued during the last six hours.

#### FASTXT FLASH TUL 4

This entry lists all flash flood warnings issued during the last four hours for Tulsa, Oklahoma.

## FASTXT LIST SCC

This entry lists the search conditions for product code SCC.

# FASTXT ADD FRF ALIAS=FRUIT WMO=FXUS81 "Fruit Frost Forecast

This entry creates product code FRF, alias name FRUIT, which searches for the Fruit Frost Forecast. FASTXT searches for WMO header FXUS81.

# FASTXT ADD REC ALIAS=RECREATION WMO=FWUS1 FWUS11 "Recreation

This entry creates product code REC which searches for WMO headers FWUS01 and FWUS11.

# FASTXT ADD SEL ID=KMKC DTIME=2 WMO=WWUS9 "Severe Local Storm Watch

This entry creates product code SEL which searches for WMO header WWUS9. The default station is KMKC, and the default amount of time to look back is 2 hours.

# FASTXT ADD HMD WMO=FXUS3 MAT=FXUS03 "Hemi Map Discussion

This entry adds a product code to list the Hemispheric Map Discussion. FASTXT searches for WMO headers of FXUS3 and does a secondary match for FXUS03. The secondary match condition is added so WMO header FXUS3, the 500 mb Type Correlations, is not listed.

## FASTXT EDIT NWX DELWMO=ABUS2 ABUS3

This entry deletes WMO headers ABUS2 and ABUS3 from the product code listing the National Weather Summary.

# FASTXT EDIT TOR DTIME=3

This entry changes the number of hours to search back in time for tornado warnings to 3 hours.

# FASTXT LIST OWNER=ALL

This entry lists all product codes currently defined for FASTXT.

#### FASTXT LIST

This entry lists all product codes defined by the operators plus any created by the current user.

#### FASTXT LIST OWNER=JSP

This entry lists the product codes created by JSP.

# FASTXT DEL OWNER=JSP MAL

This entry deletes all product codes created by JSP and MAL. Only persons logged on as OPER can delete products for multiple users.

## FASTXT DEL FRF

This entry deletes product code FRF.

# FC

# Lists short-range TAF forecasts.

#### **Formats**

FC id1 id2...idn nfor [keywords]

FC LIST option FC LIST REG= FC LIST CO=

FC DEFINE REG= ID= FC DELETE REG=

# Parameters

LIST lists IDs in a region or country

DEFINE defines a new station or region

**DELETE** deletes a station or region

idstation or region identifier

number of forecasts to list; the maximum is 12 nfor

(default=most recent)

option

REGIONS

lists all currently defined region IDs

COUNTRIES

lists all currently defined country IDs

## Keywords

CO=

country ID, 4 characters maximum

ID=

station ID

REG=

region ID, 4 characters maximum

#### Remarks

If a station reports in a 4-character format even though it is a 3-character station, you must request it as a 4-character station. For example, the FC for London Heathrow comes in as EGLL. To list the FC for EGLL, you must enter: FC EGLL.

FC (6-9 HOUR TAFs) are primarily made for European stations.

If you define a region for the FC command, it is also defined for the TAF and FTL commands.

## Example

#### FC LIST REGIONS

This entry lists all currently defined regions.

# **FOUSL**

# Lists FOUS14 data.

**Formats** 

FOUSL LIST

FOUSL station time [keywords]

**Parameters** 

LIST

lists the valid FOUS14 stations (default)

station

3-letter station ID

time

model run time, 0 or 12 (default=current day's latest)

**Keywords** 

DAY=

forecast run day, YYDDD (default=current)

MDF=

FOUS14 MD file number (default=current)

Remarks

FOUS14 data is Model Output Statistics (MOS) based on multiple linear regression analysis of forecasts from the Nested Grid Model (NGM).

**Examples** 

FOUSL

This entry lists the valid FOUS14 stations.

FOUSL MSN

This entry lists the latest forecast for Madison.

FOUSL MSN 12 MDF=1000

This entry lists the 12 UTC forecast for Madison from MD file 1000.

# **FOUSP**

# Plots or contours FOUS14 data.

**Formats** 

FOUSP LIST

FOUSP parm map time [keywords]

**Parameters** 

LIST

lists the valid parameters that can be plotted (default)

parm

FOUS14 parameter to be plotted or contoured

map

USA USA (default)

MID Midwestern USA

SAT satellite projection

**DEF** define a map with keywords LAT and LON

State Post Office abbreviation

time

hours past the run time for the forecast, HH (default=6)

**Keywords** 

CINT= contour interval (default=5)

COLOR= graphics color level (default=3)

DAY= day of the FOUS14 data, YYDDD (default=current)

GRA= graphics frame number for the output (default= current)

**GRIDF**= destination grid file number (default=current)

LAT= minimum and maximum latitude bounds to plot or contour

LON= minimum and maximum longitude bounds to plot or contour

**LSIZE**= plotting height of the characters, in pixels (default=6)

MDF= FOUS14 MD file number (default=current)

OUT= PLO plots data CON contours data

PAN= graphics panel number; the range is 1 to 4 (default=full screen)

TIME= model run time, 0 or 12 (default=current day's latest)

UNIT= parameter units for the plot or contour; valid for T, TD, TMIN, TMAX (default=F) and SPD (default=MPS) only

#### Remarks

FOUS14 data is Model Output Statistics (MOS) based on multiple linear regression analysis of forecasts from the Nested Grid Model (NGM).

If your FOUSP command entry produces a blank plot, the *time* may be set to a invalid value for that FOUS14 parameter. Use command FOUSL to list a station forecast and check the valid *time* entries for the FOUS14 parameter.

# **Examples**

## **FOUSP**

This entry lists and describes the valid parameters that can be plotted and the default units.

#### FOUSP CC

This entry plots cloud cover for 6 hours past the lastest run time for the current day over a map of the United States.

### FOUSP CC MDF=9663 DAY=93063

This entry plots cloud cover as above except it uses history file 9663.

## FOUSP TMAX SAT 24 OUT=CON GRIDF=1001

This entry contours the maximum temperature for 24 hours past run time over the satellite image on the current frame. The output grid file is 1001.

# FT

# Lists terminal aviation forecasts.

**Format** 

FT station time day

**Parameters** 

station ISFC station ID or state post office abbreviation (lists all

stations in the state)

time

lists the valid forecast time (default=current)

ALL lists all forecast times; use only when day is set

to its default

day

valid forecast day, YYDDD (default=current)

Remarks

This command converts the FT forecast into an easily readable format.

**Examples** 

FT MSN

This entry lists the current forecast for Madison, Wisconsin.

**FT KS 12** 

This entry lists the 12 UTC forecast for all stations reporting in Kansas.

FT DSM ALL

This entry lists all forecasts for Des Moines, Iowa.

# FTL

# Lists U.S. and Canadian terminal forecasts.

**Formats** 

FTL id1 id2...idn nfor [keywords]

FTL LIST option FTL LIST REG= FTL LIST CO=

FTL DEFINE REG= ID= FTL DELETE REG=

**Parameters** 

LIST lists IDs in a region or country

**DEFINE** defines a new station or region

**DELETE** deletes a station or region

id station or region identifier

nfor number of forecasts to list; the maximum is 12

(default=most recent)

option REGIONS lists all currently defined region IDs

COUNTRIES lists all currently defined country IDs

**Keywords** 

CO= country ID, 4 characters maximum

ID= station ID

REG= region ID, 4 characters maximum

Remarks

If you define a region for the FTL command, it is also defined for the TAF

and FC commands.

**Examples** 

FTL MSN MKE SEA 2

This entry lists the last two terminal forecasts for Madison, Milwaukee

and Seattle.

FTL LIST REG=IA

This entry lists the stations currently defined for Iowa.

FTL DEFINE REG=FRED ID=EGLL MSN RJTT

This entry defines a region called FRED which contains Madison, London

Heathrow and Tokyo.

# HGTSUR

Interpolates an upper air sounding to standard altimeter settings.

**Format** 

HGTSUR time [keywords]

**Parameter** 

time time of the upper air observation (default=latest time)

**Keywords** 

DAY= year and Julian day of the data, YYDDD (default=current)

**DMDF**= destination MD file for the height data (default=current)

OPT= LOW obtains data from 1000 to 18,000 feet

SIG= history MD file for the significant data

SMDF= source MD file containing the upper air data

(default=current day's file)

Remarks

HGTSUR interpolates upper air soundings to produce an MD file containing data for every 1000 feet between 18,000 and 29,000 feet and for every 2000 feet between 31,000 and 45,000 feet. The output data and units are pressure (mb), temperature (K), dew point (k), wind direction (degrees), wind speed (mps), and height (ft).

If you don't specify keyword OPT, you will receive data from 18,000 feet up including the TRO1, TRO2 and MAXW levels.

If keyword SIG is not used for history data, the significant file is assumed to immediately follow the mandatory file.

**Examples** 

#### **HGTSUR**

This entry interpolates an upper air sounding to standard altimeter settings using the current data and storing the results in the current MD file.

### HGTSUR 0 DMDF=4612

This entry interpolates 0 UTC upper air soundings for the current day to standard altimeter settings and stores the results in MD file 4612.

### HGTSUR 12 DAY=86023 SMDF=2317

This entry interpolates 12 UTC upper air soundings for day 23 of 1986 and stores the results in the current MD file. The mandatory upper air data used for the calculations is in MD file 2317; the significant data is in MD file 2318.

### HGTSUR 0 DMDF=7392 OPT=LOW

This entry interpolates the 0 UTC upper air sounding from the current day's mandatory upper air data for 1000 to 18,000 feet only and stores the results in MD file 7392.

# **HODO**

# Plots a wind sounding hodograph.

_					
_	_	_			-4
_	n	r	п	12	31

HODO station time day [keywords]

**Parameters** 

station 5-digit station ID (default=none)

time time of the observation, 0 or 12 UTC (default=current)

day year and day of the data, YYDDD (default=current)

Keywords

GRA= graphics frame number (default=current)

INIT= NO does not initialize the graphics color palette

YES initializes the color palette (default)

MDF= history MD file number; specify day when using this keyword

(default=real-time MD file)

SINC= speed increment between circles (default=calculated by

using maximum wind speed)

Remarks

A hodograph is a vertical profile of a wind sounding representing the changing wind shear with height. On the hodograph chart, wind direction is the azimuth from the origin of the coordinate system; wind speed (plotted in knots) is the radial distance from the origin. Each wind of the sounding is plotted at the appropriate distance along the direction azimuth; the line segment intersections represent significant or mandatory levels. The curve, or hodogram, between any two plotted points gives the shear between the two levels.

Wind directions are plotted such that a north wind is from top to bottom and west is from left to right. The plot is color coded as follows:

- boxes are level 1
- 1050 mb to 700 mb line segments are cyan
- 699 mb to 300 mb line segments are yellow
- 299 mb to 0 mb line segments are white

Graphics are automatically erased before each plot.

### **Examples**

### HODO 72374

This entry plots the most current sounding for station 72373, Winslow, Arizona.

## HODO 72655 12 VIRT=10

This entry plots a hodogram of station 72655 at 12 UTC and saves the plot in virtual graphics 10.

## HODO 72357 00 92183 SINC=20 INIT=NO MDF=2103

This entry plots a hodogram of station 72357 at 00 UTC on 92183. The data is stored in history MD file 2103 and plotted with set speed increments of 20 knots. The graphics color palette is not initialized.

# ISC

# Grids and contours isentropic data.

	rm	
	ги	ar

ISC parm level map file time [keywords]

**Parameters** 

DELP pressure difference between the current theta parm level and the next higher theta level, mb MIX mixing ratio, g/kg P pressure, mb

SY Montgomery streamfunction, (cm/sec)\*E7

level theta level, in Kelvin, previously generated by the ISENT command

MID Midwestern USA mapNA North America SAT satellite projection USA USA

State Post Office abbreviation

file MD file containing the isentropic data generated by the ISENT command

time time of the isentropic data, HH (default=current)

**Keywords** 

CINT= grid contour interval (default is parameter dependent)

COLOR= graphics color level; use positive numbers for solid lines and negative numbers for dashed lines (default=2)

DAY= year and day of the data, YYDDD (default=current)

GRIDF= grid file number (default=terminal number)

LAT= min max latitude bounds

LON= min max longitude bounds

Remarks

If keywords COLOR, CINT, LAT and LON are not specified in the command, the string table is searched for the keywords. If the results are unexpected, use TL to list the string table. A grid file is generated and its pointer set (same as the terminal number).

# **Examples**

### ISC P 310 MID 1000

This entry contours pressure on a 310 Kelvin isentropic surface for the current day and time over a Midwest map, from MD file 1000.

### ISC P 310 MID 1000 12 DAY=92114

This entry contours pressure on a 310 Kelvin isentropic surface for 12 UTC, day 92114 over a Midwest map, from MD file 1000.

# ISC SY 290 X 11280 00 LAT=25 37 LON=93 107 GRIDF=33 CINT=5 COLOR=-4

This entry contours Montgomery streamfunction over the state of Texas at 00 UTC as defined by the LAT and LON keywords, and stores the results in grid file 33. The contour interval is 5m<sup>2</sup>/s<sup>2</sup>. Contours are dashed in graphics color level 4.

# **ISENT**

Calculates theta surface levels for upper air data.

Format	ISENT	sfile dfile day time btha etha inctha [keyword]			
Parameters and wrote	sfile	source MD file number (default=current mandatory RAOB or IRAB file)			
	dfile	destination MD file number; must not exist before running ISENT (no default)			
	day	year and day of the upper air data, YYDDD (default=current)			
	time	time of the upper air observation, HH (default=0 UTC)			
	btha	beginning theta value (default=280 K)			
	etha	ending theta value (default=350 K)			
	inctha	increment of the theta value (default=10 K)			
Keyword	SIG=	history MD file number for significant data			
Remarks	pressure	num of 20 theta levels can be calculated. Theta levels contain (mb), mixing ratio (g/kg), Montgomery streamfunction ( $m^2/s^2$ ), change (mb) and u and v wind components (m/s).			
		When using history data, the significant data file should follow the mandatory data file or be specified by keyword SIG.			
	condition	To view data from the created MD file, use command MDX with a sort condition like the following: <b>SORT=TIME 12 THA 300</b> . This sort condition is for data at 12 UTC; the isentropic surface is 300 K.			
See Also	Use com	Use command MDX, ISC or ISP to plot or contour data.			

# **Examples**

#### **ISENT 250 1050**

This entry calculates the theta surface levels for all data in MD file 250 and stores the results in MD file 1050.

## ISENT 15 4000 92065 12 290 320 10

This entry calculates isentropic surfaces from MD file 15 and stores the results in MD file 4000, day 065, 1992, at 12 UTC. It begins with theta surface 290 and ends at 320 using 10° increments.

#### ISENT 2550 200 93010 00 X X 5 SIG=2551

This entry calculates isentropic surfaces from history data stored in MD files 2550 and 2551, the mandatory and significant data, respectively. The default theta range is specified (280-350K) but the theta values are computed every 5K.

# ISP

# Plots isentropic data.

-	-	-4

ISP parm level map file time [keywords]

Paramete	-

DN IIX LOT	plots the pressure difference between the current theta level and the next lower level, ml plots the station identification plots mixing ratio, g/kg plots pressure, mb plots pressure, pressure change, wind, mixing
IIX	plots mixing ratio, g/kg plots pressure, mb
	plots pressure, mb
LOT	plots pressure, pressure change, wind, mixing
	ratio and ID numbers
Y	plots Montgomery streamfunction, $(m^2/s^2)$
ſ .	plots the u wind component, m/sec
	plots the v wind component, m/sec
VIN	plots winds, m/sec
neta level ommand	, in Kelvin, previously generated by the ISENT
	/IN neta level

map

MID	Midwestern USA
NA	North America
SAT	satellite projection
USA	USA

State Post Office abbreviation

file

MD file containing the isentropic data generated by the ISENT command

time

time of the isentropic data, HH (default=current)

# Keywords

COLOR= graphics color level (default=3)

DAY=

year and day of the data, YYDDD (default=current)

LAT=

min max latitude bounds

LON=

min max longitude bounds

#### Remarks

If keywords COLOR, LAT and LON are not used in the command, the string table is searched for values. If the results are unexpected, use command TL to list the string table.

## **Examples**

## ISP P 310 WI 1000

This entry plots the pressure on a 310 Kelvin surface at stations in Wisconsin using the current day and time. The data is from MD file 1000.

#### ISP PLOT 310 MID 1000 12 DAY=92124

This entry plots the pressure, change in pressure, wind, mixing ratio and ID numbers in the Midwest on a 310 Kelvin isentropic surface. The data is from MD file 1000, 12 UTC, day 92124.

#### ISP MIX 290 NC 11500 0 DAY=93002 COLOR=3

This entry plots the mixing ratio values at upper air stations on the 290 theta level centered over North Carolina in graphics color level 3. The data is taken from MD file 11500 and is for 2 January 1993.

# LIST4D

Lists the contents of the 4-D trajectory analyses.

#### Remarks

LIST4D lists the contents of the analyses generated by the VAS4D command.

Revised 6/95

# **MDR**

Grids manually digitized radar data.

Format

MDR [keywords]

**Keywords** 

DATA= ALL places zeros in a 125 nm radius around each

reporting radar site (default=missing value code)

GRID=

grid number to write the decoded MDR data into

(default=next available)

GRIDF= grid file number to store the MDR data (default=current)

Remarks

MDR searches the weather text file and decodes the current hour's MDR data. VIP levels 1 to 6 are written into an 85 x 115 grid. If you enter DATA=ALL, VIP levels of 0 are written for areas reporting no echoes. VIP levels of 0 are only included for sites that report echoes or no echoes (N.E.).

MDR data can only be decoded for the current hour.

See Also

Commands MDRPLT and MDRIMG call MDR if the current hour's data was not previously decoded into the real-time MDR grid file or current grid file.

**Examples** 

**MDR** 

This entry decodes the current hour's MDR data and writes it to the next available grid in the current grid file.

MDR GRID=29 GRIDF=1892 DATA=ALL

This entry decodes the current hour's radar data and writes the VIP levels to grid 29 in grid file 1892. VIP levels of 0 are written to echo free regions within a 125 nautical mile radius of the radar site.

MDR GRID=39

This entry decodes the current hour's radar data and writes the VIP levels to grid 39 in the current grid file.

# **MDRIMG**

Displays a U.S. image from manually digitized radar data.

**Format** 

MDRIMG area frame [keywords]

**Parameters** 

area number for the image (no default)

frame

frame number for display; if not specified, the image is not

displayed

Keywords

GRID= grid number to plot (no default for real-time grid file;

default=next available for any other grid file number)

GRIDF=

grid file number (default=real-time grid file if available;

otherwise the terminal number)

SAT=

sarea darea frame

generates a polar stereographic satellite image projection that can be displayed on the opposite frame and viewed

with the N key

sarea

satellite area on the disk

darea

scratch area number to remap sarea into a

polar stereographic projection

frame

image frame number for display

OPP displays the image on the opposite

frame

Remark

The SAT keyword remaps a satellite image into the MDR image projection (polar stereographic) and can be overlaid with the N key.

Example

MDRIMG 3000 1 GRID=15 SAT=101 3001 33

This entry generates a radar image from real-time MDR grid 15 in area 3000 and displays this image on frame 1. It uses satellite image 101 to create a polar sterographic image in area 3001 corresponding to the MDR image and displays this image on frame 33. If frame 33 is opposite 1, you can view both images by pressing the N key.

# **MDRPLT**

Plots manually digitized radar data.

**Format** 

MDRPLT map [keywords]

**Parameter** 

map MID Midwestern USA

NA North America

SAT satellite projection

USA USA polar stereographic projection (default)

State Post Office abbreviation

**Keywords** 

COLOR= graphics color level (default=3)

DATA= ALL places zeros in a 125 nm radius around a

reporting radar site (default=missing value code)

DAY= year and day of the data, YYDDD (default=current)

GRA= graphics frame number (default=current)

GRID= grid number to plot (default=search on current day

and hour)

GRIDF= grid file number (default=real-time file, if available,

otherwise the terminal number)

**GWIDTH**= graphics line width, in pixels (default=1)

**HOUR**= hour of the data, HH (default=current)

ID= plots a map centered on a station ID (no default)

LAT= min max minimum and maximum latitude extents

LON= min max minimum and maximum longitude extents

LSIZE= label height, in pixels (default=8)

PANEL= graphics panel quadrant; the range is 1 to 4

(default=full screen)

#### Remarks

When requesting current data, MDRPLT grids the most current hour's data. For old data, MDRPLT searches the grid file for the requested day and time. If no grid is found, MDRPLT makes a grid for the most current hour's data.

Use the DATA=ALL keyword to determine which radars across a region actually reported.

Grids can only be created with the current hour's data.

You can use keywords LAT and LON to specify the map projection.

# **Examples**

#### **MDRPLT**

This entry plots the current MDR on a USA polar stereographic projection.

#### MDRPLT USA HOUR=12

This entry plots MDR values on a USA polar stereographic projection for the current day at 12 UTC.

### MDRPLT LAT=35 45 LON=90 100

This entry plots MDR values on the specified map for the current day and hour.

#### MDRPLT USA DATA=ALL GRIDF=44

This entry plots current hour MDR values with zeros on a USA map and files that information in the next available grid in grid file 44.

# MDRPLT ID=MSN

This entry plots the current hour MDR values reported around Madison.

Revised 6/95

# Plots a 24-hour surface meteorogram.

ш	

MG station time day [keywords]

**Parameters** 

station 3- or 4-character station ID

time

hour of the last data plotted on the graph; the range is 0 to

23 (default=current)

day

year and day of the data, YYDDD (default=current)

Keywords

INIT=

NO does not initialize the graphics colors

YES

initializes the graphics colors (default)

MDF=

history MD file number; specify parameter day when using this keyword; if the string table for the schema type is empty, MDF defaults to SYSKEY; if you don't specify an MD file number, MDF defaults to the current

real-time MD file number specified by SYSKEY

Remarks

MG initializes the graphics color levels and erases the graphics before plotting. It plots temperature, dew point, altimeter setting, wind speed and direction, weather, and cloud cover for a 24-hour period.

The cloud cover symbols are:

- scattered 1 small cloud
- broken 2 clouds
- overcast 1 large cloud
- clear no clouds

Wind speed and direction indicators are:

- direction wind barb's angle
- speed sustained and gust speeds are listed below the barb
- calm diamond shaped symbol

The altimeter setting is plotted with its range labels, depending on the minimum and maximum altimeter setting for a given day and time period.

### **Examples**

#### MG MSN

This entry plots data for the past 24 hours for Madison, Wisconsin. The day and time default to the current data.

### MG MSN 0 91331

This entry plots data from 91330 0 UTC to 91331 0 UTC for Madison.

# MG SEGU 12 93014 INIT=NO MDF=22114

This entry plots data from 12 UTC 93013 to 12 UTC 93014 for Guayaquil, Ecuador. MD file 22114 is searched for the data; the graphics colors are not initialized when the meteorogram is drawn.

# **MGXS**

day

Plots a meteorogram cross section.

_		1.5
	-	+
	П	141

MGXS bid eid time day [keywords]

**Parameters** 

bid3-letter station ID of the beginning station to plot

3-letter station ID of the ending station to plot eid

hour of the data to display, HH (default=current) time

year and day of the data, YYDDD (default=current)

**Keywords** 

GRA= graphics frame number (default=current)

ID= list of the station IDs to plot

INIT= NO does not initialize the graphics color palette

YES initializes the palette with GU REST (default)

MDF= history MD file number; you must specify the day

parameter when using this keyword (default=real-time MD file)

WID= width of the corridor used to select a station between bid

and eid, in miles; if you specify keyword ID, a corridor

width is not used (default=30 miles)

Remarks

The number of plotted stations will vary due to the proportional spacing between stations.

The wind direction is designated by the angle of the barb. Speed is designated by the length of the barbs.

MGXS plots the altimeter setting in millibars.

The cloud cover symbols are:

- scattered 1 small cloud
- broken 2 clouds
- overcast 1 large cloud
- clear no clouds

#### **Examples**

#### MGXS DFW BRO

This entry uses the current day and time for the plot, stations DFW through BRO. It initializes the color palette and selects stations from a 30-mile corridor.

#### MGXS MSN DET 14 92120

This entry plots 14 UTC data for day 92120, stations MSN through DET. The stations plotted between MSN and DET are selected from a 30-mile corridor according to their spacing.

### MGXS ID=JFK DCA GSB ATL MIA

This entry plots all the listed stations for the current time and day.

# **MKMAND**

Derives upper air mandatory levels from significant levels.

**Format** 

MKMAND id1 id2...idn [keywords]

**Parameters** 

id1...n 5-digit station ID

ALL all stations in the MD file

Keywords

DAY=

Julian day of the data (default=current)

DMD =

destination MD file, schema RAOB or IRAB

(default=SMD+1)

SMD=

source MD file, schema RSIG or IRSG

(default=from MDU SET)

TIME=

time of the data (default=0 UTC)

Remarks

If <u>all</u> mandatory level observations for a station are missing, MKMAND creates a new MD file containing computed mandatory level data using the existing significant level observations. All mandatory level observations for the station must be missing (no mandatory level data available). The destination file must have a column header.

**Examples** 

MKMAND 72451 72456 SMD=21 DMD=2466 DAY=90031 TIME=0 This entry calculates missing 0 UTC mandatory level data for station 72451 (Dodge City, Kansas) and 72456 (Topeka, Kansas) from the significant level data found in MD file 21.

MKMAND ALL SMD=21 DMD=2465 TIME=12 DAY=90031 This entry calculates mandatory levels from the significant level data for all stations found in MD file 21 and places the results in MD file 2465.

# MR

# Plots a 4-day upper air meteorogram.

	_		-4
г	o	rm	aι

MR station time day [keywords]

**Parameters** 

station 5-digit station ID

time

observation time, 0 or 12 UTC; the four previous days

are plotted (default=current)

day

year and day of the data, YYDDD (default=current)

Keywords

GRA=

graphics frame number (default=current)

INIT=

NO

does not initialize the graphics color palette

YES initializes the graphics color palette with

GU REST (default)

MDF =

md1 md2 md3 md4 md5

MD file numbers (in any order) for each day in the 5-day period; you must specify the day parameter

(default=real-time MD files)

Remarks

MR erases the graphics before plotting and initializes the graphics color levels. The time and day entered are plotted on the lower right of the screen. MR plots include the following for a 4-day period at 850, 700, 500 and 300 mb.

- temperature in Celsius
- dew point in Celsius, 850 and 700 mb, dashed line
- height of the mandatory pressure levels, in meters
- wind speed in mps
- wind direction indicated by barb angles

Graphics are automatically erased before each plot.

### **Examples**

MR 72451

This entry plots a meteorogram for station 72451 beginning with the current time.

MR 72645 12 92200 MDF=7488 7489 7490 7491 7492 This entry plots upper air data for station 72645 (Green Bay) from 12 UTC, day 92196 to 12 UTC, day 92200.

MR 72645 0 91192

This entry plots a meteorogram for station 72645 from 0 UTC, day 91188, to 0 UTC, day 91192.

# NMCL of the Mid more stail cuttoe and

Lists NMC grids.

The ADDE command GRDLIST may be used in place of NMCL.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Formats** 

NMCL LIST

NMCL parm level time vt model [keywords]

**Parameters** 

LIST lists available models and their grid file locations

parm parameter to list

ALL lists every product (default)

level pressure level; for example, 880

ALL all levels (default)
MAXW maximum wind

MSL mean sea level pressure

SFC surface TRO tropopause

time ALL for 0 and 12 UTC model run time (default)

o for 0 UTC model run time for 12 UTC model run time

valid time for the run: 0, 6, 12, 18, 24, etc. (default=ALL)

model ALL searches all models (default)

ECMF European Center for Medium Range Weather

Forecasting

ETA ETA coordinate model

MRF medium range forecast model with GFDL

physics

NGM nested grid model

ROI regional optimum interpolation analysis

SST sea surface temperature analysis

Keywords

DAY= year and day of the model run, YYDDD (default=current)

GRIDF= grid file number to search (default=real-time NMC grid file)

Remarks

Two days of data are stored on the SSEC McIDAS-MVS system.

# **Examples**

# **NMCL**

This entry lists every NMC grid for the current day. This command entry's output may be thousands of lines long.

#### NMCL T 850 12 12 MRF

This entry lists the real-time medium-range forecast NMC temperatures at 12 UTC, for 12 hours.

#### NMCL Z X 0 24 NGM

This entry lists the 24-hour forecast height grids for all levels from today's 0 UTC nested grid model.

#### NMCL ALL 500 0 0 ROI MDF=16015 DAY=93015

This entry lists all analyses available for the regional optimum interpolation analysis (ROI) at 500 mb for the 0 UTC run. The data is stored in history MD file 16015 for day 93015.

9-34

# **NMCX**

Contours or plots NMC grids.

The ADDE command GRDDISP may be used in place of NMCX.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Format** 

NMCX parm level time vt model option parm2 level2 time2 vt2 model2 [keywords]

**Parameters** 

parm parameter to plot; all standard NMC parameters or one of the following derived parameters: ABV, DSH, DST, DVG, GEO, SPD, STR, VOR, WNF, WNV (no default)

level pressure level; for example, 850 (no default)

MAXW maximum wind level
MSL mean sea level pressure

SFC surface TRO tropopause

time 0 for 0 UTC model run time

for 12 UTC model run time (no default)

valid time for the run: 0, 6, 12, 18, 24, etc. (no default)

model ECMF European Center for Medium Range Weather

Forecasting

ETA Coordinate model

MRF medium range forecast model with GFDL physics

NGM nested grid model

ROI regional optimum interpolation analysis

SST sea surface temperature analysis (no default)

option derived parameters option: ADD, AVG, DIV, MPY,

RMS, SUB (no default)

parm2 second parameter for the derived option; all standard NMC

parameters or one of the following: ABV, DSH, DST, DVG,

GEO, SPD, STR, VOR (no default)

level2 any mandatory level (default=level)

MAXW maximum wind level

MSL mean sea level pressure

SFC surface TRO tropopause

	time2	0	for 0 UTC model run time, HH
		12	for 12 UTC model run time, HH (default=time)
	vt2	valid t	ime for the run: 0, 6, 12, 18, 24, etc. (default=vt)
	model2	ECME	European Center for Medium Range Weather Forecasting
		ETA	ETA coordinate model (default=model)
		MRF	medium range forecast model with GFDL physics
		NGM	nested grid model
		ROI	regional optimum interpolation analysis
		SST	sea surface temperature analysis (default=model)
Keywords	CINT=	contou	r interval (default=2)
	CMAP=	graphi	cs color level for the map (default=1)
	COLOR=		cs color level for the contours; use positive numbers id, negative numbers for dashed (default=2)
	Levy ou Time	AA THIN LES	CEARS
	DASH=	NEG	dash negative contours only
		POS	dash positive contours only
	DAY=	year a	nd day to plot, YYDDD (default=current)
	ELE=	min m	ax graphics TV element bounds
i, etc. (no default) dium Ronne Wenther	GOUT=		grid file number for the derived parameters lt=terminal number)
Name of Spinster assess	GRA=	graphi	cs frame number (default=current)
	GRIDF=	grid fil	e number to search (default=real-time NMC grid file)
		image	frame number (default=current)
	LAT=	min m	ax latitude bounds
	LIN=	min m	aax graphics TV line bounds
Non; all standard NMC.	LINT=	contou	r label interval (default=1)
	LON=	min m	ax longitude bounds
	LSIZE=	height	of the contour labels, in pixels (default=8)
	MAG=		ing factor that multiplies the plotted values by AG (default=grid extents)

MAP= MID, USA, NA, State Post Office abbreviation, SAT, NONE, DEF (default=grid extents)

PAN= graphics frame panel number; the range is 0 to 4 (default=0, full screen)

PLOT= YES plots grid point values (default for parm WNF

or WNV)

NO plots contours (default for parms other than

WNF or WNV)

PRO= MERC Mercator projection (default)

CONF polar stereographic or Lambert conformal

projection

SCALE= conformal projection scale, a ratio or number of TV lines

(default=linmax linmin)

SLAT= lat1 lat2 standard latitudes for conformal projections

(default=60)

SLON= standard longitude for conformal projections

(default=computed)

UNIT= units in which to plot or contour the parameter

(default is parameter dependent)

See Also

See Appendix C for the definitions of the meteorological parameters used

by this command. VOR and ABV units are 10\*\*-5/sec.

**Examples** 

NMCX T 700 12 24 NGM

This entry contours the 24-hour 700 mb temperature forecast from the

12 UTC NGM run.

NMCX Z 500 0 18 MRF SUB Z 1000 MAP=MID CINT=60

This entry contours the 18-hour 1000 to 500 mb thickness forecast from

the 0 UTC MRF run, centered over a map of the Midwest.

NMCX VOR 500 12 24 ETA ADV MAP=USA CINT=50

This entry contours the 24-hour 500 mb vorticity advection forecast from

the 12 UTC ETA run over a USA map.

# SAO

# Lists SA data.

**Formats** 

SAO DEFINE REG= ID=

SAO DELETE REG=

SAO LIST option

SAO LIST REG=

SAO RENAME oldname newname

SAO id1 id2...idn nhours type [keywords]

**Parameters** 

DEFINE

defines a new station or region

DELETE

deletes a station or region

LIST

lists IDs

RENAME

renames a region

 $idl \dots n$ 

station or regional identifier; for regional identifiers,

enter: SAO LIST REGIONS

nhours

number of hours of the observations; maximum is 48

(default=3)

type

C civil format

D decoded

R remarks

T text (default)

option

COUNTRIES lists all currently defined country IDs

REGIONS

lists all currently defined regional IDs

oldname

ID of the region to rename; maximum of 4 characters

newname

new ID of the region; maximum of 4 characters

**Keywords** 

CAT=

C clouds

F frozen

P pressure

R rain

T thunder

W wind

(default=ALL)

CEIL= lists stations with a ceiling less than or equal to CEIL, in feet

CO= country ID; maximum of 4 characters

DAY= year and Julian day, YYDDD (default=current)

ID= station ID; maximum of 4 characters

REG= region ID; maximum of 4 characters

TIME= time of the last observation (default=current)

VIS= lists stations with visibility less than or equal to VIS, in miles

WIND= lists stations with wind speed greater than or equal to WIND,

in knots

Remarks

Use keyword CAT only with the R (remarks) option.

### **Examples**

#### SAO MSN X X

This entry lists the past three hours of SAs for Madison in a text format.

### SAO WI FL TX 20 D

This entry lists the past 20 hours of SAs for all station IDs in Wisconsin, Florida and Texas in a decoded format.

#### SAO LIST COUNTRIES

This entry lists the country abbreviations.

# SAO DEFINE REG=MIDW ID=WI IL MN MI IA

This entry defines a region to include all ID stations in Wisconsin, Illinois, Minnesota, Michigan and Iowa.

#### SAO DELETE REG=MIDW

This entry deletes the region MIDW from the regions file.

### SAO MSN ORD HOU 24 D WIND=10

This entry lists the decoded SAs for Madison, Chicago and Houston for the past 24 hours where the winds are greater than 10 knots.

#### SAO TN MO 1 R CAT=R F

This entry lists all the remarks issued in the past hour from Tennessee and Missouri that have information about rain or fog.

# SAO LBB CDS AMA ABI WIND=20 CEIL=20000 VIS=10

This entry lists only those SAs from Lubbock, Childress, Amarillo and Abilene in which the winds are greater than or equal to 20 knots, the ceiling is 20,000 feet or less and the visibility is 10 miles or less.

# SC

# Grids and contours surface data.

<b>-ormats</b>
----------------

SC parm map time [keywords] SC p1-p2 map t1-t2 [keywords]

**Parameters** 

parm	ABV	absolute vorticity
	ADV	advection
	CIGH	height of the ceiling (100 feet); for ISFC only
	DVG	divergence (10 <sup>-6</sup> sec <sup>-1</sup> )
	GUS	wind gust (meters/second)
	MIX	mixing ratio (g/kg)
	PCP	precipitation (inches)
	PRE	sea level pressure (mb); for ISFC only
	PSL	altimeter setting converted to millibars
	SNO	snow cover (inches)
	SPD	wind speed (meters/second)
	STR	streamline
	T	temperature (°C)
	TD	dew point (°C)
	THA	theta (K)
	THAE	theta E (K)
	VIS	visibility (miles)
	VOR	vorticity (10 <sup>-6</sup> sec <sup>-1</sup> )
	ZCH	height of the ceiling (100 feet); for SVCA only
	ZCL	height of the first non-ceiling cloud deck (100 feet); for SVCA only
	ZCL1	height of the first non-ceiling cloud deck (100 feet); for ISFC only
	ZCL2	height of the second non-ceiling cloud deck (100 feet); for ISFC only
	ZCM	height of the second non-ceiling cloud deck (100 feet); for SVCA only
	ZS	station elevation (meters)
map	MID	Midwestern USA
	NA	North America
	SAT	satellite projection
	USA	USA

time hour; defaults to the previous hour if the current time is less than 10 minutes past the hour (default=current)

State Post Office abbreviation

	p1 - p2	parameter	difference used in contouring; subtract $p2$ from $p1$
	t1 - t2	time differ	ence used in contouring; subtract $t2$ from $t1$
Keywords	CINT=	contour in	terval (default is parameter dependent)
	COLOR=		olor level; use positive numbers for solid lines ve numbers for dashed lines (default=2)
	DAY=	d1 - d2	year and day; use two values when contouring differences, YYDDD (default=current)
	GRA=	graphics fr	ame number
	GRIDF=	destination	n grid file number (default=terminal number)
	LAT=	min max	latitude extents (default=from map parameter)
	LON=	min max	longitude extents (default=from map parameter)
			ISFC or SVCA schema MD file number; use two values when contouring differences (default=last digit of the current Julian day)
	UNIT=	M contour (default de	rs values in American units rs values in metric units termined by SYSKEY word 900) ord is valid for temperature and dew point only.

### Remarks

If you do not specify keywords CINT, COLOR, DAY, GRA, GRIDF, LAT, LON, MDF or UNIT in the command, the string table is searched for strings of the same names. If those strings exist, SC uses their values. If keyword or string MDF is used, its value is stored and accessed in the string named SVCA. If the command gives unexpected results, use command TL to list the string table or **TD ALL** to delete it.

Parameter advection (ADV) or divergence (DVG) is done by appending ADV or DVG, e.g., TADV, SPDDVG.

# See Also

Use the SP command to plot surface data. Use command IGTV to replot grids created by SC.

### **Examples**

### SC STR SAT 12 MDF=1000

This entry contours streamlines at 12 UTC from history file 1000 in a satellite projection.

#### SC T MID

This entry contours the temperature over the Midwest in graphics color level 2 for the current day and time.

#### SC PCP GRA=5 COLOR=7 LAT=20 40 LON=85 105

This entry contours precipitation in graphics color level 7 on graphics frame 5. It uses a map with limiting latitudes of  $20^{\circ}$  and  $40^{\circ}$  N and longitudes of  $85^{\circ}$  and  $105^{\circ}$  W.

# SC PSL MID 18-18 MDF=7500-7501 DAY=90010-90009

This entry contours the 24-hour sea level pressure change from 18 UTC, day 90009, to 18 UTC, day 90010.

To generate derived parameters such as vorticity advection (VORADV), first create a vorticity grid as follows:

#### SC VOR USA

Watch the text screen for the location of the U and VOR grids, then enter this command substituting the correct grid numbers for *u-grid* and *vor-grid*.

IGG MAKE u-grid ADV vor-grid

# SHEAR

time

# Calculates vertical shear.

**Format** 

SHEAR time [keywords]

**Parameter** 

time of the upper air observation (default=latest time)

**Keywords** 

DAY= year and Julian day of the data, YYDDD (default=current)

DMDF= destination MD file for the height data (default=current)

SIG= history MD file for the significant data

SMDF= source MD file containing the upper air data (default=current)

Remarks

SHEAR calculates the vertical shear at 1000-foot intervals for all upper air stations.

If the keyword SIG is not used for history data, the significant file is assumed to immediately follow the mandatory file.

Output data and units are pressure (mb), shear (kts/ft), direction (degrees) and height (ft).

**Examples** 

#### SHEAR

This entry calculates the vertical shear at 1000-foot intervals using the current data and stores the results in the current MD file.

#### SHEAR 0 DMDF=6842

This entry calculates the vertical shear for 0 UTC data for the current day and stores the results in MD file 6842.

#### SHEAR 12 DAY=92063 SMDF=4961

This entry calculates the vertical shear for 12 UTC for day 92063 and stores the results in the current MD file. The mandatory data used for the calculations is in MD file 4961; the significant data is in MD file 4962.

# SHIPC

Grids and contours ship and surface data.

**Format** 

SHIPC parm map time [keywords]

**Parameters** 

parm MIX mixing ratio (g/kg)

PSL altimeter setting at sea level and/or sea level

pressure (mb)

SPD wind speed (meter/sec)

STI sea surface temperature

STR streamline

T temperature

TD dew point temperature

map

MID Midwestern USA

NA North America

SAT satellite projection (default)

USA USA

State Post Office abbreviation

time

hour or HH:MM:SS; time defaults to the previous hour's if the current time is less than 10 minutes past the hour

(default=current)

Keywords

CINT= contour interval (default=parameter dependent)

**COLOR**= graphics color level, negative for dashed lines (default=2)

DAY= year and Julian day, YYDDD (default=current)

GRA= graphics frame number (default=current)

**GRIDF**= grid file number (default=terminal number)

LAT= min max minimum and maximum latitude bounds

LON= min max minimum and maximum longitude bounds

SHIP= ship MD file number, ISHP schema (default=current)

SURF= SVCA MD file number, ISFC or SVCA schema (default=current)

UNIT= A American units

M metric units

(default taken from SYSKEY)

#### Remarks

Parameter advection (ADV) or divergence (DVG) is done by appending ADV or DVG, e.g., TADV, PSLDVG.

If you do not specify keywords COLOR, CINT, LAT, LON, SVCA, UNIT, DAY and SHIP in the command, the string table is searched for them. If the results are unexpected, use command TL to list your string table or TD ALL to delete it. All parm parameters without units default to SYSKEY. When using history files, you can only use files with ISHP, ISFC and SVCA schemas.

SHIPC contours the altimeter setting at sea level for land reports and sea level pressure for ship reports.

#### **Examples**

# SHIPC T NC

This entry contours temperatures covering North Carolina and the adjacent course in graphics color level 2 for the most recent hour.

# SHIPC T X 19 CINT=4 COLOR=-2 GRA=5 LAT=31 48 LON=85 108 UNIT=A

This entry contours temperatures at 19 UTC with contour intervals every 4° F in dashed lines on graphics frame 5 for the area 31° to 48° N and 85° to 108° W.

Plots surface and ship data.

SHIPP parm map time [keywords]

**Parameters** 

CLDcloud cover; the range is 0 to 3 for surface data parm where 0 is clear and 3 is overcast, and 0-9 for ship

data where 0 is clear and 9 is obscured

ID station identification

MIX mixing ratio (g/kg)

PLOT plots station model:

**PSL** 

TDCLD

altimeter setting at sea level and/or sea level PSL

wx

pressure (mb)

SPD wind speed (m/s)

STI sea surface temperature

T temperature

TD dew point temperature

WIN wind, DDFF, FF (m/s) meteorological flags

> Barb =  $5 \text{ m/s} (\sim 10 \text{ kts})$  $Flag = 25 \text{ m/s} (\sim 50 \text{ kts})$

MID Midwestern USA map

> NA North America

SAT satellite projection (default)

USA **USA** 

State Post Office abbreviation

time

hour or HH:MM:SS; defaults to the previous hour if the current time is less than 10 minutes past the hour (default=latest major synoptic time: 0, 6, 12 or 18 UTC)

**Keywords** 

COLOR= graphics color level (default=3)

DAY =year and Julian day, YYDDD (default=current)

GRA= graphics frame number (default=current)

LAT= min max latitude extents

LON= min max longitude extents

SHIP= ship MD file number, ISHP schema (default=current) SURF=

surface MD file number, ISFC or SVCA schema

(default=current)

UNIT=

A American units

M metric units

(default taken from SYSKEY)

# Remarks

SHIPP only plots ship data from the ISHP schema; surface data from both the ISFC and SVCA schemas can be used.

If you don't specify keywords COLOR, LAT, LON, DAY, UNIT and GRA, the string table is searched for the keywords. If unexpected results occur, use command TL to list the string table. All *parm* parameters without units default to SYSKEY. When using history files, you can only use files with ISHP, ISFC and SVCA schemas.

SHIPP plots the altimeter setting at sea level for land reports and sea level pressure for ship reports.

# **Examples**

### SHIPP TD

This entry plots the dew point temperature for the most recent hour in graphics color level 3.

### SHIPP STI X 18 LAT=0 40 LON=30 70

This entry plots sea surface temperatures at 18 UTC covering the area from  $0^{\circ}$  to  $40^{\circ}$  N and  $30^{\circ}$  to  $70^{\circ}$  W.

# SHIPP T SAT 14 COLOR=1 GRA=5 UNIT=A

This entry plots the temperature on a satellite image at 14 UTC in graphics color level 1 on graphics frame 5 with the temperature in American units.

# SHIPP MIX WI 12 COLOR=2 UNIT=A SHIP=2493 SURF=2494 DAY=90270

This entry plots the mixing ratio over Wisconsin in graphics color level 2 at 12 UTC for day 90270 in American units.

# SKEWT

Plots a sounding on a skew T thermodynamic diagram.

**Formats** 

SKEWT station time [keywords] SKEWT OUTL [keywords]

**Parameters** 

station 5-digit station ID (e.g., 72645 is Green Bay) or a sequence number in a satellite retrieval file

time observation time, HH (default=nearest RAOB, 0 or 12)

OUTL displays a skew T diagram without sounding

Keywords

COLOR= graphics color level of the sounding data (default=3)

DAY= year and Julian day, YYDDD (default=current)

GRA= graphics frame number (default=current)

MDF= MD file number of the mandatory level data

(default=leat digit of the current Julian day plus 10)

(default=last digit of the current Julian day plus 10)

MIX= YES draws mixing ratio lines (default)

NO omits mixing ratio lines

OLAY= YES draws an overlay

NO no overlay (default)

PTOP= top pressure level on the diagram rounded to multiples

of 50 mb (default=100)

RANGE= min max Celsius temperature range of the diagram

(default=-90 40)

ROW= row number of the data in RAWI schema

(default=first occurrence of the data)

SIG= MD file number of significant level data (default=current)

TYPE= RAWI uses rawinsonde schema

VAS uses VAS created data

UNIT= FT plots height in feet on the left axis

MB plots pressure in millibars on the left axis (default)

M plots height in meters on the left axis

#### Remarks

Graphics are automatically erased before each plot. Heights are recomputed for hydrostatic consistency.

Any number of overlays may be plotted, but successive wind barbs and headers will overwrite the previous overlay's wind barbs and headers due to space limitations.

Dew point temperature is not plotted when dew point depression (temperature minus dew point temperature) rounds to a whole number that exceeds 30.


### Examples

#### **SKEWT 72645**

This entry plots a skew T diagram for Green Bay, WI, for the current time and day, erasing the graphics before plotting.

#### **SKEWT 72403 12**

This entry plots a skew T diagram for station 72403 (Washington/Dulles) at 12 UTC. A sample output is shown below.



Sample SKEWT Diagram

The number below the GMT label is the day and time of the sounding, in UTC. ID is the WMO station identifier. The parcel used in calculating the stability parameters is derived from the average thermodynamic properties (temperature and moisture) found in the lowest 100 mb, ground-based boundary layer. This parcel is used in determining parameters EQUIP, FMAX, CVT and LI. At 12 UTC, the parcel's temperature is warmed  $2^{\circ}$  K to account for daytime heating. This modified parcel, in turn, determines the above parameters. See *Appendix D* for the stability parameter definitions.

# SKEWT OUTL RANGE=-40 25

This entry plots a skew T diagram without the station plot, from -40° to  $25^{\circ}$  Celsius.

To plot two soundings on one diagram, enter these two commands:

# SKEWT 72655 X PTOP=400

This entry plots a skew T diagram for station 72655 at the current time. The highest pressure plotted is 400 mb.

### SKEWT 72655 3 OLAY=Y COLOR=4

This entry plots a skew T diagram for station 72655 at 3 UTC on the same diagram in graphics color level 4.

# SL

# Lists surface station data.

	_			4~
_	()	rm	12	

SL units station blime etime inc [keywords]

SL btime etime inc

SL btime etime

SL SET MDF= DAY=

SL RESET

units

#### **Parameters**

A lists values in American units

M lists values in metric units; see the Remarks (default)

3- or 4-character station ID or state Post Office abbreviation; station

can be one or more stations

btimebeginning observation time of the station (default=current),

or the beginning time of the available data information

listed (default=lists the current time's data availability)

etime ending observation time of the station, or the ending

time of the available data information listed (default=btime)

inctime increment for the time range, HH (default=1)

SET directs SL to read from the specified history MD file and

day; see the Remarks

resets the MD file to use a real-time MD file; do this RESET

after using a history MD file; see the Remarks

# Keywords (General)

DAY=

year and Julian day, YYDDD (default=current)

DIR=

wind direction; 0 to 360°

GUS=

wind gusts

MDF=

surface history MD file number

(default=last digit of the current day)

PCP=

precipitation total

PSL=

altimeter setting in millibars

SNO=

snow cover

	SPD=	wind speed
	<b>T</b> =	temperature
	TD=	dew point temperature
	VIS=	visibility
	WX=	weather, 1 to 8 characters
Keywords (ISFC schema only)	CC1=	first non-ceiling cloud coverage; the range is 0 to 3 where 0 is clear, 1 is scattered, 2 is broken, 3 is overcast
	CC2=	second non-ceiling cloud coverage; the range is 0 to 3
CIGC		ceiling cloud coverage; the range is 0 to 3
	CIGH=	ceiling cloud height
	CO=	2-letter country code; lists all reporting stations in the selected country; command CCODE lists the codes
	PRE=	sea level pressure, in mb
	PTYPE=	PRE listing of sea level pressure PSL listing of altimeter setting (default)
	ZCL1=	height of the first non-ceiling cloud deck
	ZCL2=	height of the second non-ceiling cloud deck
Keywords (SVCA schema only)	ССН=	high cloud coverage; the range is 0 to 3 where 0 is clear, 1 is scattered, 2 is broken, 3 is overcast
	CCL=	low cloud coverage; the range is 0 to 3
	CCM=	middle cloud coverage; the range is 0 to 3
	ZCH=	high level cloud height
	ZCL=	low level cloud height
	ZCM=	middle level cloud height
		And the second second

#### Remarks

If you use keyword CO, data from all reporting stations in that country is listed. It works only with the ISFC schema MD files.

For information on history files and output, enter: SL HELP. If SL does not work on your workstation, clear your string table with TD ALL.

The output units of the parameters are shown below.

Parameters	American	Metric
wind speed	knots	m/s
wind gusts	knots	m/s
visibility	miles	km
cloud height	feet	meters
precipitation, snow	inches	cm d
temperature	°F	°C
dew point	°F	$^{\circ}\mathrm{C}$

When you specify *units*, its value is stored in a string named SLUNIT. The SET option creates strings named SVCA and DAY which are set to the values specified by keywords MDF and DAY. Since subsequent SL commands read these three string values, you only need to specify them when changing their values. The RESET option deletes strings SVCA and DAY, and resets string SLUNIT to its default value so that subsequent SL commands use the default MD file, day and units.

You can specify a range of values for all keywords except CO, DAY, MDF, PTYPE and WX.

When search keywords (e.g., DIR and TD) are used, the units of the specified values are determined by the unit's parameter. Only reports matching the search keyword values are listed. For example, SL A X 0 23 T=-50 -10 GUS=30 60 CO=CN lists all Canadian reports with temperatures between -50° and -10° Fahrenheit and wind gusts between 30 and 60 miles per hour.

#### **Examples**

#### $\mathbf{SL}$

This entry lists the current time's data availability.

# SL MSN 12 18 2

This entry lists the surface station data for Madison, Wisconsin, from 12 to 18 UTC at 2-hour increments.

#### SL SET MDF=1000 DAY=94300

This entry points to history MD file 1000 and lists its data for day 94300. All SL commands run now will access MD file 1000 until an SL RESET is entered.

#### SL ORD 15 10 DAY=94001 94002

This entry lists the surface data for Chicago's O'Hare Airport from 15 UTC, day 94001, to 10 UTC, day 94002.

#### SL A WI

This entry lists surface data in American units for all Wisconsin stations for the current time.

#### SL 12 23 WX=TRW

This entry lists all stations for the current day with thunderstorms between 12 and 23 UTC.

#### SL M MSN DSM 12 15

This entry lists the reports for Madison and Des Moines between 12 and 15 UTC in metric units.

### SL 12 15

This entry lists surface data availability from 12 to 15 UTC.

#### SL 6:

This entry lists surface data availability from 6 UTC to the current time.

#### SL 18 CO=AU MDF=7500 DAY=93100

This entry lists the surface data for all reporting stations in Australia at 18 UTC, day 93100. MD file 7500 must be ISFC schema.

# SP

# Plots surface data.

_		
$\mathbf{E}_{\mathbf{A}}$	rm	ats
		aLS

SP parm map time [keywords] SP p1-p2 map t1-t2 [keywords]

**Parameters** 

parm CIGH height of the ceiling, 100 feet; ISFC only
CLD cloud cover; the range is 0 (clear) to 3 (overcast)
GUS wind gust, in m/s
ID station identification
MIX mixing ratio (g/kg)
PCP precipitation, in inches
PLOT plots station model in the format:

T PSL
WX \* (wind flag)
T CLD
ID

PRE sea level pressure, in mb; ISFC only
PSL altimeter setting, in millibars
SNO snow cover, in inches
SPD wind speed, in m/s
T temperature (°C)

TD dew point temperature (°C)

THA theta (K)
THAE theta E (K)
VIS visibility, in miles

WIN wind, DDFF, FF (m/s) meteorological flags

Barb =  $5 \text{ ms}^{-1}$  (~10 kts); Flag =  $25 \text{ ms}^{-1}$  (~50 kts)

WX weather text WXS weather symbols

ZCH ceiling height, 100 feet; SVCA only

ZCL first non-ceiling cloud deck height, 100 feet; SVCA only
 ZCL1 first non-ceiling cloud deck height, 100 feet; ISFC only
 ZCL2 second non-ceiling cloud deck height, 100 feet; ISFC only
 ZCM second non-ceiling cloud deck height, 100 feet; SVCA only

ZS station elevation, in meters

map MID Midwestern USA

NA North America SAT satellite projection

USA USA

State Post Office abbreviation

time

hour; defaults to the previous hour if the current time is less than 10 minutes past the hour (default=current)

p1 - p2 parameter difference used in plotting; subtract p2 from p1

t1 - t2 time difference used in plotting; subtract t2 from t1

Keywords

COLOR= graphics color level (default=3)

DAY= d1 - d2 year and day, YYDDD; use two values when

plotting differences (default=current)

GRA= graphics frame number (default=current)

LAT= min max minimum and maximum latitude extents

LON= min max minimum and maximum longitude extents

LSIZE= label size for the parameter plotted (default=8)

MDF= f1 - f2 ISFC or SVCA surface history MD file number;

use two values when plotting differences (default=last digit of the current Julian day)

UNIT= A displays values in American units

M displays values in metric units

(default is determined by SYSKEY word 900)

Remarks

If you do not specify keywords COLOR, DAY, GRA, LAT, LON and MDF in the command, the string table is searched for strings of the same names. If those strings exist, SP uses their values. If keyword or string MDF is used, its value is stored and accessed in the string named SVCA. If the command gives unexpected results, use the command TL to list the string table or **TD ALL** to delete it.

**Examples** 

SP T MID

This entry plots temperatures (°C) over the Midwest for the current day and time in graphics color level 3.

SP WIN LAT=20 40 LON=80 100 COLOR=1

This entry plots winds in graphics color level 1 with latitude bounds 20° to 40° N, longitude bounds 80° to 100° W, for the current day and time.

SP PLOT SAT 18 DAY=94300

This entry plots a station model over a satellite projection at 18 UTC, day 94300.

SP T-TD WI

This entry plots the current dew point depression for Wisconsin.

# SP T WI 12-12 MDF=2-1 DAY=93102-93101 UNIT=A

This entry plots the 24-hour temperature change in degrees Fahrenheit from 12 UTC day 93101, to 12 UTC day 93102.

#### SP SNO MN 12 UNIT=M

This entry plots the snow depth over the state of Minnesota on the current day in cm.

Revised 6/95 9-57

# STAB AND LABORATION TO BE

# Generates stability indices.

**Format** 

STAB sfile dfile time day [keywords]

**Parameters** 

sfile source MD file number of the mandatory data

dfile

destination MD file number for the computed stability

parameters

time

time of the observation, 00, 06, 12, 18 UTC only

(default=latest observation)

day

year and Julian day of the observation, YYDDD

**Keywords** 

SIGMDF=

MD file number for the significant data

TYPE=

CTF use for sfile created from NMC CTF files

Remarks

STAB generates and saves stability indices for all stations in an MD file.

The units for precipitable water are in millimeters.

See Also

Use command STABIL or MDX to plot parameters. Any of the keys listed

with command MDL can be plotted or contoured.

**Examples** 

STAB 1000 1001

This entry generates stability indices from MD file 1000 and stores the results in MD file 1001, using the current day and time.

STAB 34 6512 0 93216 SIGMDF=6516

This entry generates stability indices from the mandatory upper air data in MD file 34 and the significant data in MD file 6516 and stores the results in MD file 6512. The time is 0 UTC; the day is 93216. To plot the Lifted Indices over the U.S., enter: MDX LI SORT=DAY 93216 TIME

0 MAP=USA OUT=PLO SOU=MDF MDF=6512

# **STABIL**

Plots stability indices.

**Formats** 

STABIL MAKE sfile dfile time day

STABIL PLOT map file

**Parameters** 

MAKE generates an MD file to hold the stability indices

PLOT plots the stability indices on the graphics

sfile source MD file number with input data

(default=current IRAB MD file)

dfile destination MD file number for the stability indices

time time of the observation; use 00, 06, 12 or 18 UTC

(default=12)

day year and day of the observation, YYDDD (default=current)

map MID Midwestern USA

USA USA

NA North America
SAT satellite projection

State Post Office abbreviation

file MD file number containing the stability indices

Remarks

STABIL plots stability indices in a station model format with the Lifted Index plotted in the upper-left corner, the Total Totals in the lower-left corner, precipitable water in the upper-right corner and SWEAT index in the lower-right corner. The units for precipitable water are in millimeters.

See Also

The UL command lists additional stability indices.

**Examples** 

**STABIL MAKE 2000 2001** 

This entry generates the stability parameters for the current day and time using the observations in RAOB file 2000, and places the results in MD file 2001.

#### STABIL PLOT MID 2001 DEV=C

This entry plots the stability parameters over the Midwest on the text screen and stores the results in MD file 2001.

## STG

time

### Plots an 8-hour space-time graph.

_					
	O	n	1	9	٠

STG bid eid time day [keywords]

**Parameters** 

bid 3-letter station ID of the beginning station to plot

eid 3-letter station ID of the ending station to plot

hour of the latest data to plot, HH (default=current)

day year and day of the data, YYDDD (default=current)

Keywords

GRA= graphics frame number (default=current)

ID= list of the station IDs to plot

INIT= NO does not initialize the graphics color palette

YES initializes the palette with GU REST (default)

MDF= MD file number

WID= width of the corridor used to select stations between bid

and eid, in miles; if keyword ID is used, a corridor width

is not used (default=30)

Remarks

Command STG plots surface hourly observations, i.e., temperature, dew point, pressure, wind, wind gust and weather for an 8-hour period for multiple stations.

The number of plotted stations will vary due to proportional spacing between stations. The practical limit is 11 or 12. If too few stations are plotted, increase the corridor width using keyword WID. If too many stations are plotted, decrease the corridor width.

The wind direction is designated by the angle of the barb, and wind speed by the length of the barbs. Calm winds are designated by a plus sign (+).

Graphics are automatically erased before each plot.

STG plots the altimeter setting in millibars.

#### **Examples**

#### STG DFW BRO

This entry selects stations from a 30-mile wide corridor between DFW and BRO using the current day and time, and initializes the color palette.

#### STG MSN CLE 6

This entry plots data from 23 UTC of the previous day to 6 UTC of the current day. The stations plotted between MSN and CLE are automatically selected using a 30-mile wide corridor.

#### STG ID=MSN MKE ORD CLE

(alit a pub insurance-thanks) and level

This entry plots eight hours of data up to the current day and time for the four stations MSN, MKE, ORD and CLE.

# STUVE

Plots a Stuve thermodynamic diagram.

**Formats** 

STUVE OUTL [keywords]

STUVE station time [keywords]

**Parameters** 

OUTL displays a Stuve diagram without sounding

station 5-digit station identification number or a sequence number

within a satellite retrieval file

time RAOB time; enter 0, 03, 06, 09, 12, 15, 18 or 21 UTC

(default=0 or 12)

Keywords

COLOR= graphics color level of the plotted data

DAY= year and Julian day, YYDDD (default=current)

GRA= graphics frame number (default=current)

MDF= MD file number (default=current RAOB MD file)

MIX= YES draws mixing ratio lines (default)

NO does not draw lines

OLAY= YES overlays a sounding on the existing Stuve diagram

NO no overlay (default)

PTOP= top pressure level on the diagram, rounded to multiples of

50 mb (default=100 mb)

RANGE= min max minimum and maximum Celsius temperature

range of the diagram (default=-70° to 30° C)

ROW= row member of the data in RAWI schema (default=first

occurrence of the data)

SIG= MD file number containing the corresponding significant

level data (default=current day's file)

TYPE= VAS uses VAS created data

RAWI uses rawinsonde schema

UNIT=MB plots pressure in millibars on the left axis (default)

M plots pressure in meters on the left axisFT plots pressure in feet on the left axis

#### Remarks

Graphics are automatically erased before each plot. Heights are recomputed for hydrostatic consistency.

You can plot any number of overlays, but each successive wind bar and header will overwrite the previous overlay's wind bar and header due to space limitations.

Dew point temperature is not plotted when dew point depression (temperature minus dew point temperature) rounds to a whole number larger than 30.

#### **Examples**

#### STUVE 72645

This entry plots a Stuve diagram for station 72645 for the current day and time, erasing the graphics before plotting.

#### STUVE OUTL RANGE=-40 25

This entry plots a Stuve diagram without a station plot, from -40 $^{\circ}$  to 25 $^{\circ}$  Celsius, using the current MD file and time.

To plot two soundings on one diagram, enter the two commands below.

#### STUVE 72655 12

This entry plots a Stuve diagram at 12 UTC from the current MD file.

#### STUVE 72655 0 OLAY=Y COLOR=5

This entry plots a Stuve diagram at 0 UTC from the current MD file over the same diagram and changes the color to red.

# TAF

### Lists 24-hour TAF (Aerodrome) forecasts.

**Formats** 

TAF id1 id2...idn nfor [keywords]

TAF LIST option TAF LIST REG= TAF LIST CO=

TAF DEFINE REG= ID=
TAF DELETE REG=

**Parameters** 

LIST lists IDs in a region or country

**DEFINE** defines a new station or region

**DELETE** deletes a station or region

id station or region identifier

nfor number of forecasts to list; the maximum is 12

(default=most recent)

option REGIONS lists all currently defined region IDs

COUNTRIES lists all currently defined country IDs

**Keywords** 

CO= country ID, 4 characters maximum

ID= station ID

REG= region ID, 4 characters maximum

Remarks

If a station reports in a 4-character format even though it is a 3-character station, you must request it as a 4-character station. For example, the TAF for Milwaukee comes in as KMKE. To list the TAF for MKE, you must enter: **TAF KMKE**.

If you define a region for the TAF command, it is also defined for the FTL and FC commands.

Example

TAF LIST CO=IY

This entry lists the stations currently defined for Italy.

## **TEXT**

Lists weather text and observations.

The ADDE command WXTLIST may be used in place of TEXT.

See the ADDE section of the McIDAS-X or McIDAS-OS2 Users Guide for more information.

**Formats** 

TEXT name matchstring [keywords] "second match

TEXT DIR matchstring

TEXT AFOS matchstring

TEXT LIST circuit header

**Parameters** 

DIR lists a directory of WMO headers and their definitions

that match matchstring (default=all WMO headers)

AFOS lists AFOS headers that match matchstring and known

WMO headers (default=all AFOS headers)

LIST lists group names, headers and alias names

name WMO header, group name or alias name to search

matchstring primary matchstring to search for, 12-character limit;

if prefixed with @, searches for the string in the first

column; if prefixed with \*, searches for the string in

the header (default=most recent block)

"second match secondary matchstring to search for; 79-character

limit; this string may contain blanks

circuit name of the circuit; for example, DDS, IDS, PPS

header 2-character WMO header name (default=all)

Keywords

Your sive may be different.

BLOCK= YES prints the entire data block

NO does not print the data block (default)

CIR= circuit to search (default=all)

DAY= Julian day to begin the search, YYDDD

(default=current)

HEAD= YES lists the WMO header with the observation

NO does not list the WMO header (default)

NUM=

number of matches to list (default=1)

TIME=

header time, in whole hours, of the last observation

to list (default=current)

#### Remarks

WMO data can be accessed by specifying a group name, alias name, WMO header name or text string. System operations manages the assignment of group names, alias names and filing WMO headers. The TEXT LIST option lists your system's organization of groups, alias names and WMO headers.

A group name is two characters (typically a WMO header contained in that group). The group name is incorporated into the LW file name containing the WMO data. You can assign common names to groups by specifying an alias name, such as TORNADO for WMO header WF.

A group name may contain one or more WMO headers. For example, all WMO RAOB headers might be grouped under one name to organize searching. To assure you're listing the most recent reports, search for data using the group name or alias name rather than the header, since similar observations can be filed under more than one header.

If the LIST option finds a header under alias MISC, the search is faster if you specify the header rather than the group name (ZZ) or alias name (MISC). See the example below.

#### TEXT LIST DDS SF

This entry lists the group and alias name that the SF header is filed under on the DDS circuit. In this case, SF is filed under MISC. TEXT runs faster if you enter TEXT SF rather than TEXT MISC SF.

### Examples

This example is valid for files defined at SSEC. Your site may be different.

Suppose you want to look at part A radiosonde data for Green Bay, Wisconsin (station 72645). To find the data, first find its WMO header. Enter the commands below, in order.

#### TEXT DIR RAOB

does not list the WMO header (default

This entry lists the WMO headers whose definitions contain the string RAOB. Choose a header, UJ in this case, that stores the desired data. Use this header and matchstrings to access the data.

#### TEXT UJ TTAA "72645

This entry lists the most recent part A radiosonde observations (TTAA) for Green Bay, Wisconsin.

Another way to find the data is to use the extended WMO header as the primary matchstring. For example:

#### TXT FP FPUS5 "KMKE

This entry lists the most recent zone forecast (FPUS5) for Milwaukee.

#### TEXT DIR WH

This entry lists the header information for WH.

#### TEXT DIR WARNING

This entry lists all headers that list warning data.

#### TEXT AFOS AQI

This entry lists the AFOS catalog name and the known WMO headers for Air Quality Indices.

#### TEXT AFOS RIVER

This entry lists all AFOS catalog names with RIVER information and the known WMO headers.

#### TEXT MISC \*UZ NUM=3

This entry lists the first three matches in the MISC file containing the string UZ in its header.

#### TEXT SA @TOP TIME=15 NUM=4

This entry lists the four most recent SAs, starting at 15 UTC, that contain the string TOP beginning in the first column. In most cases, the output will list the 12, 13, 14 and 15 UTC SAs from Topeka, Kansas.

#### **TEXT SYNOPTIC 72641**

If the WMORTE command has set the SM WMO header alias to SYNOPTIC, this entry lists the first occurrence of 72641 in the SM index.

#### TEXT SM

This entry lists the most recent match filed under the SM header (a primary index). A match may be found in any of the following WMO headers since they are all secondary indices: SI, SM, SN, SS.

#### TEXT SS

This entry lists the most recent match found in the WMO header SS because SS is a secondary index.

## UC

### Grids and contours upper air data.

Formats	UC parm level map time [keywords]	
	UC p1-p2 l1-l2 map t1-t2 [keywords]	

Parameters parm ABV absolute vorticity (10<sup>-6</sup> sec<sup>-1</sup>)

DVG divergence (10<sup>-6</sup> sec<sup>-1</sup>)

MIX mixing ratio (g/kg)
P pressure (mb)
SPD wind speed (m/s)
STR streamline

T temperature (°C)

TD dew point temperature (°C)

THA theta (K)
THAE theta-E (K)
VOR vorticity (10<sup>-6</sup>sec<sup>-1</sup>)

Z height (m)

ZS station elevation (m); use only with SFC level

level MAXW maximum wind

SFC surface TRO1 tropopause 1 TRO2 tropopause 2

1000 - 100 mandatory levels in mb

map MID Midwestern USA
NA North America

SAT satellite projection

USA USA

State Post Office abbreviation

time hour (default=0 UTC if the current time is between 0 UTC and 1315 UTC; otherwise, default=12 UTC)

p1-p2 parameter difference used in contouring; subtract p2 from p1

11-12 level difference used in contouring; subtract 12 from 11

t1-t2 time difference used in contouring; subtract t2 from t1

#### **Keywords**

CINT= grid contour interval (default is parameter dependent)

COLOR= graphics color level; use negative numbers for dashed lines

and positive numbers for solid lines (default=2)

DAY= d1-d2year and day; use two values to contour

differences, YYDDD (default=current)

GRA= graphics frame number (default=current)

GRIDF= destination grid file number (default=terminal number)

LAT= min max minimum and maximum latitude extents

LON= min max minimum and maximum longitude extents

MDF= f1-f2 upper air history file number; use two values to

contour differences (default=last digit of the

current Julian day plus 10)

#### Remarks

Parameter advection (ADV) or divergence (DVG) is done by appending the parameter with ADV or DVG, e.g., TADV, ZDVG.

If you do not specify keywords COLOR, CINT, LAT, LON and MDF in the command, the string table is searched for them. If the results are unexpected, use command TL to list the string table. A grid file is generated and its pointer set to your terminal number.

The day and time default to the current day and time, not the last available data on the workstation.

Specify keyword DAY when using history data.

#### **Examples**

#### UC T 850 MID

This entry contours 850 mb temperatures over the Midwest for the current day and time in graphics color level 2.

### UC TD-TD 850 SAT 12-12 DAY=93021-93020 MDF=11-20 COLOR=-3 CINT=2

This entry draws dew point temperature differences between 12 UTC on 93020 and 12 UTC on 93021. The dew point temperatures on 93020 are subtracted from those on 93021. The keyword MDF lists the order of the respective MD files. The data is contoured in graphics color level 3 (dashed), with a contour interval of 2 over the current satellite image.

#### UC STR 500 SAT 12 COLOR=1

This entry draws streamlines at 500 mb on a satellite projection at 12 UTC in graphics color level 1.

Below is an example of vorticity advection.

#### UC VOR 500 USA 12

This entry draws contours of relative vorticity at 500 mb on a USA map for the current day at 12 UTC. Three grids (U, V and VOR) are filed in the current grid file. Assume U is in grid 1 and VOR is in grid 3.

Enter the following two commands.

#### IGG MAKE 1 ADV 3

This entry creates a fourth grid containing vorticity advection.

#### IGTV 4 100 USA DASH=NEG

This entry draws vorticity advection contours on a USA map, with a contour interval of 100. Negative values are dashed.

9-70 Revised 6/95

## UL

### Lists upper air data.

	_	-	-	-
_	O	rm	-	

UL AVA [keywords]

UL ANL station time [keywords]
UL LIST station time [keywords]
UL MAND station time [keywords]

#### **Parameters**

AVA lists the upper air data availability (default)

ANL lists the stability indices for the station

LIST lists mandatory and significant levels

MAND lists mandatory levels

station 5-digit station ID

time hour or HH:MM:SS (default=nearest 0 or 12 UTC)

#### **Keywords**

DAY =

year and day of the data, YYDDD (default=current)

MDF =

MD file number containing the history data (default=the last digit of the current Julian day plus 10)

- OPT=
- lists the mandatory levels with parcel analysis; does not recompute heights or perform interpolations
- lists mandatory and significant temperature levels; does not interpolate winds at significant temperature levels or perform parcel analysis
- 3 lists mandatory and significant temperature levels and significant wind levels; recomputes heights; computes wind pressure; does not perform parcel analysis
- 5 lists mandatory and significant temperature levels; interpolates winds at significant temperature levels; does not perform parcel analysis
  - lists mandatory and significant temperature levels and significant wind levels; makes interpolations for missing data and recomputes heights; computes parcel analysis (default)

PTEMP= YES

computes the potential temperature and mixing ratio

for each level

NO does not compute (default)

SIG= significant MD file number (default=10 plus the value of

MDF if MDF is between 10 and 19; otherwise, default=1

plus the value of MDF)

ZMAX= lists the data levels less than or equal to ZMAX; height is

in meters (default=all levels)

#### Remarks

The units for precipitable water are in millimeters.

Significant level winds and temperatures are never reported for the same level. Keyword OPT defaults to a full vertical interpolation. This means that when a significant level temperature is reported, the wind speed and direction at that level are interpreted; conversely, when a significant level wind is reported, the temperature and dew point at the wind level are interpolated. For no interpolation, use OPT=3.

The three keys in the significant level MD file schema (IRSG) are P1, P2 and P3. They are used for significant wind and temperature reports. If a significant wind is reported, P1 is the direction, P2 is the speed and P3 is the height. If a significant temperature is reported, P1 is the temperature, P2 is the dew point and P3 is the pressure.

The day and time default to the current day and time, not the last available data on the workstation. Specify keyword DAY when using history data.

#### **Examples**

#### UL

This entry lists the available upper air data for the entire day.

#### UL LIST 72645 12 OPT=3

This entry lists the mandatory and significant levels for station 72645, at 12 UTC on the current day. Temperature, dew point and wind data are not interpolated; OPT=3 displays the raw data from the RAOB code.

#### UL AVA MDF=6512 DAY=94250

This entry lists the available upper air data in MD file 6512, day 94250.

#### UL LIST 72747 0 DAY=90111 MDF=7550 SIG=7551

This entry lists the mandatory and significant levels for station 72747 at 0 UTC on day 90111. The mandatory level data is in MD file 7550, while the significant level data is in MD file 7551. Data is interpolated for significant levels.

## UP

### Plots upper air data.

_		
Fo	rm	ata
Гυ		als

UP parm level map time [keywords]
UP p1-p2 l1-l2 map t1-t2 [keywords]

**Parameters** 

parm IDN

5-digit station ID; the first two digits are dropped in the

PLOT option; IDs are plotted only for the surface level

MIX mixing ratio (g/kg)

PLOT plots station model in the format below; only the last three digits of the height and station ID are plotted

T Z
\* (wind flag)
IDN

TD

SPD wind speed, in m/s T temperature (°C)

TD dew point temperature (°C)

THA theta (K)
THAE theta E (K)

WIN wind, DDFF, FF(m/s) meteorological flags

Barb =  $5 \text{ ms}^{-1}$  (~10 kts); Flag =  $25 \text{ ms}^{-1}$  (~50 kts)

Z surface height, in meters ZS station elevation, in meters

level MAXW maximum wind

SFC surface
TRO1 tropopause 1
TRO2 tropopause 2

1000 - 100 mandatory levels, in mb

map MID Midwestern USA

NA North America
SAT satellite projection

USA USA

State Post Office abbreviation

time hour (default=0 UTC if the current time is between 0 UTC and 1315 UTC; otherwise, default=12 UTC)

p1-p2 parameter difference used in plotting; subtract p2 from p1

11-12 level difference used in plotting; subtract 12 from 11

t1-t2 time difference used in plotting; subtract t2 from t1

#### Keywords

COLOR= graphics color level (default=3)

DAY= d1-d2 year and day; use two values when plotting

differences, YYDDD (default=current)

GRA= graphics frame number (default=current)

LAT= min max minimum and maximum latitude extents

LON= min max minimum and maximum longitude extents

MDF = f1-f2 history file number; use two values to plot

differences (default=last digit of the current

Julian day plus 10)

#### Remarks

If you do not specify keywords COLOR, LAT, LON and MDF in the command, the string table is searched for them. If the results are unexpected, use command TL to list the string table. The day and time default to the current day and time, not the last available data on the workstation. Specify keyword DAY when using history data.

#### **Examples**

#### UP T 850 MID

This entry plots the current temperatures at 850 mb over the Midwest in graphics color level 3.

#### UP IDN SFC USA COLOR=4

This entry plots station numbers over the USA in graphics color level 4.

UP WIN 850 X 0 MDF=6512 LAT=30 45 LON=80 100 This entry plots winds at 850 mb, 0 UTC in MD file 6512. The latitude range is 30° to 45° N. The longitude range is 80° to 100° W.

#### UP Z 500-1000 USA

This entry plots the current 1000/500 mb thickness over the USA.

#### UP T-TD 850 USA

This entry plots the current dew point depression over the USA.

### UP Z 500 USA 12-12 MDF=15-14 DAY=92025-92024

This entry plots the 24-hour 500 mb height change from 12 UTC, day 92024, to 12 UTC, day 92025.

# VAS4D

Analyzes VAS data for a 4-D display of trajectories and moisture.

**Format** 

VAS4D itraj file nframe mix [keywords]

**Parameters** 

index of the trajectory analysis to make, the range is 1 to 10; use command LIST4D to list the indices

file

itraj

source MD file of the VAS data to analyze (default=1441)

nframe

number of frames in the sequence (default=4)

mix

value of the mixing ratio surface, in g/kg (default=5.0)

Keywords

FREQ=

Barnes analysis frequency (default=30)

HGT=

bottom top height extents, in meters

(default=0.0 12000.0)

LAT=

south north

latitude extents (default=26.0 49.0)

LON=

east west

longitude extents (default=75.0 112.0)

THA=

bottom top

theta extents (default=290.0 340.0)

Remarks

VAS4D analyzes VAS data for a time sequence display of wind trajectories and moisture surfaces. The display includes a topographical map (TOPO3D) and can be viewed in stereo.

**Examples** 

VAS4D 5

This entry analyzes the VAS data in MD file 1441 and prepares a 4-frame sequence of trajectories and moisture, using a 5.0 g/kg mixing ratio surface.

#### VAS4D 4 1610 5 4.0

This entry analyzes the upper air data from MD file number 1610 in index number 4 for 5 images of wind trajectories and the 4.0 g/kg mixing ratio surface.

# **WWLIST**

Lists weather watches.

**Format** 

WWLIST bwatch ewatch [keyword]

**Parameters** 

bwatch beginning watch number to list (default=lists all active

numbers)

ewatch

ending watch number to list

Keyword

FORM= ALI

ALL lists all portions of the watch (default=status only)

PRE lists the pre-watch information

PRI lists the primary watch description

UP lists the watch update

Remarks

If you do not specify keyword FORM, only the status (active, inactive or has not been issued) and the states/regions affected by the watch are listed.

**Examples** 

**WWLIST** 

This entry lists the status of all active watches.

WWLIST 521 532 FORM=PRE

This entry lists the pre-watch statements of watch numbers 521 through

532.

# **WWPLOT**

Plots weather watch boxes on a satellite image or polar stereographic map.

**Format** 

WWPLOT map [keyword]

**Parameter** 

map

map to plot watches on; valid maps are USA or state Post

Office abbreviation (default=SAT)

Keyword

WATCH= range of watches to plot (default=current active)

Remarks

Active watch boxes are plotted in solid lines; expired boxes are dashed.

If you specify a P.O. abbreviation and the entire box outline cannot be

plotted on the screen, none of the watch is drawn.

**Examples** 

**WWPLOT** 

This entry plots all active watch boxes using the image frame for

navigation.

WWPLOT USA WATCH=501 510

This entry draws a polar stereographic map of the U.S. and plots watch

boxes 501 through 510 on the map.

# **XSECT**

Displays a vertical cross section.

**Format** 

XSECT bid eid [keywords] "text

**Parameters** 

bidbeginning station ID number

eidending station ID number

"text

cross section title; up to 42 characters

Keywords

CINT= contour interval (default=see the Remarks) c1...cn

COLOR=  $l1 \dots ln$ contour color level (default=see the Remarks)

DAY= MD file Julian day, YYDDD (default=current)

ERASE= NO does not erase the graphics frame

> YES automatically erases the graphics frame (default)

FORM=

 $f1 \dots fn$ see the table in the Remarks for the defaults

DIR reported wind directions, 0 to 360° clockwise

from the north

MIX derived mixing ratios, g/kg

SPD reported wind speeds, m/s

SPDE derived wind speed projected normal to the cross

> section axis and enhanced by thermal information through the geostrophic wind equation, m/s

**SPDN** derived wind speed normal to the cross section

axis, m/s; see the Remarks

**SPDS** derived wind speed tangential to the cross

section axis, m/s

**SPDZ** derived vertical wind speed shear, 1/s

reported temperature, C

TD reported dew point temperature, C

THA derived isentropes, K (default)

U derived u-component of the reported wind

speed, m/s

 $\mathbf{v}$ derived v-component of the reported wind

speed, m/s

WIN wind barbs of the reported winds, kt

 $\mathbf{z}$ reported heights, m

GCOLOR=	backgroun	nd border and interior grid color level (default=1)	
GRA=	graphics frame (default=current)		
IDN=	id125	station ID numbers for the cross section	
LABEL=	YES NO	displays parameter labels (default) does not display parameter labels	
LAT=	end beg	latitude limits for the cross section (default=eid bid)	
LDASH=	l1ln -2 -1	contour dashing; used with keyword FORM all contours are dashed only negative contours are dashed no dashing (default=see the table in the Remarks)	
LINT=	label inter	val of the contours (default=see the Remarks)	
LON=	end beg	longititude limits for the cross section (default=eid bid)	
LSIZE=	label size	of the contours (default=see the Remarks)	
MAP=	NO YES	does not plot a map showing the cross section location (default) plots a map showing the cross section location	
MDF=	mand sig	mandatory and significant level MD file numbers; set $sig$ to 0 if only mandatory levels are needed; giving $sig$ a value is only valid when $mand$ is specified (default= see the Remarks)	
PAN=		uarter panel number: 0, 1, 2, 3, 4; specifying ord automatically sets keyword ERASE to NO	
PBOT=	bottom mandatory pressure level of the cross section (default=1050 mb)		
PTOP=	top mandatory pressure level of the cross section (default=100 mb)		
SMOOTH=	smoothing	factor (default=see the table in the Remarks)	
TIME=	MD file time, HH:MM:SS (default=most current)		

TITLE= title and ID label color level (default=3)

UNIT= units of the contours (default=see the table in the Remarks)

WIDTH= corridor half width in kilometers (default=±250 km)

#### Remarks

The first station specified with bid or the IDN keyword is on the left edge of the display; the last station specified is on the right edge. The stations selected with the LAT/LON keywords are displayed first on the left and last on the right, based on whether the longitudinal or latitudinal extent of the cross section is larger. Consequently, if you reverse the order for selecting stations, the orientation of the cross section is affected. Altering the order may also impact the intermediate station selections as stations are included/excluded in order from first to last.

The maximum number of stations is 25. When two stations projected along the cross section axis lie too close to each other to allow a solution for the contouring algorithm, the station farthest from the beginning of the cross section is excluded.

If more than 25 stations are selected with the IDN keyword, the program stops. If more than 25 stations are selected using *bid* and *eid* and LAT/LON, the program doesn't stop, but uses only the first 25 stations selected and lists appropriate error messages.

If a station report is missing a surface pressure or reports less than three levels of information, it is excluded. If a station provides a partial report, the missing levels are not included in the contouring analysis and that area of the cross section display is blank.

The MDF keyword has two parameters. The second parameter is only valid when the first parameter refers to an IRAB MD file. The second parameter is assumed to be its corresponding IRSG MD file. When only the mandatory IRAB levels are included in the vertical contouring, the second parameter must be set to zero.

You can specify the FORM keyword options in any combination and order. However, the sequence must be maintained when invoking any of the context specific keywords, i.e., CINT, LINT, COLOR, UNIT, LDASH, LSIZE or SMOOTH.

Graphics options conform to the IGTV standards.

If you use the PAN keyword, the keyword ERASE is set to NO unless you specify otherwise.

The orientation for SPDN and SPDS with respect to the cross section axis is the positive tangential direction. This direction is along the cross section axis going from the last station towards the first station with the positive perpendicular (normal) direction following a right-hand rule, i.e., positive to the right relative to the positive tangential direction. This scheme results in the mathematically appropriate sign which is appropriate for the cross section orientation but may not be equivalent to the physically intuitive sign that you anticipate. The SPDN and SPDS signs will vary with the cross section orientation although the contour patterns are very similiar.

XSECT checks for missing values and obviously bad data, e.g., negative temperatures. If the cross section output seems incorrect, run command SKEWT or UL on the suspect station soundings to check the input values.

The table below defines the defaults for the keyword FORM.

FORM	CINT	COLOR	LDASH	LINT	LSIZE	<b>SMOOTH</b>	UNIT
DIR	90	1	-2	1	6	20	deg
MIX	2	4	-2	1	6	20	g/kg
SPD	5	2	0	1	6	20	MPS
SPDE	5	2	-1 to varie	1	6	40	MPS
SPDN	5	2	-1 /	1	6	20	MPS
SPDS	5	2	-1	1	6	20	MPS
SPDZ	5	2	-1	1 model	6	40	1/s
T	5	5 (4 for SDA)	-1	2	6	20	C
TD	5	4	-1	2	6	20	C
THA	5	5 (4 for SDA)	-1	2	6	20	K
U	5	2	-1	2	6	20	MPS
V	5	3	-1	2	6	20	MPS
WIN	NA	7 (2 for SDA)	NA	NA	8	NA	Kt
$\mathbf{Z}$	1000	1	-1	5	6	20	M

#### **Examples**

#### XSECT 72747 72203

This entry displays an isentropic cross section from station reports lying within a 250 km corridor along a cross section axis from station 72747 to station 72203.

### XSECT 72747 72203 MAP=Y

This entry is the same as the first example, but it also displays a map in the upper-right corner which indicates the location of the cross section axis and the included stations.

#### XSECT 72747 72203 FORM=MIX THA SPD LDASH=0 X -2

This entry is the same as the first example, but it also overlays the mixing ratio cross section without dashing contours, the isentropic cross section dashing negative contours only and the isotach cross section dashing all contours.

XSECT 72747 72203 PTOP=400 WIDTH=150 FORM=MIX

This entry displays a mixing ratio cross section for a narrower corridor width along the same cross section axis as in the first example. It emphasizes the lower levels by limiting the top pressure level to 400 mb.

### XSECT 72747 72203 FORM=MIX THA SPD COLOR=1 2 3 CINT=X 5 10

This entry is the same as the second example, except the color level for the mixing ratio contours is set to 1, the isentropes to 2, and isotachs to 3. It uses the default contour interval for the mixing ratios. The isentropic contour interval is set at  $5^{\circ}$  K, while the isotach contour interval is set at 10 m/s.

# XSECT LAT=30 55 LON=100 FORM=SPD WIN UNIT=KT PBOT=500 PTOP=100 MAP=Y

This entry displays a cross section of wind speed in knots from 500 to 100 mb along 100° W from 30° to 55° N. Wind barbs are also displayed. Station selection occurs automatically.

# XSECT FORM=SPDZ SMOOTH=100 COLOR=4 IDN=72694 72681 72576 72562 MAP=Y LSIZE=10

This entry draws a cross section of vertical wind speed shear from Salem, Oregon, to North Platte, Nebraska, using the IDN keyword to specify the stations to include. The graphic displays a small map of the cross section location. The contours are in color level 4; the label size for the contours is 10 pixels. This entry also smooths the analysis by a factor of 100.

# Chapter 10. TOVS and VAS Retrievals

BSVA	Compares a grid and MD file brightness temperatures	10-1
CGVA	Compares values in two grids	10-3
CMMD	Compares values in an MD file	10-5
CMVA	Compares MD file values to grid and plot differences	10-8
CSVA	Fills the surface MD file for VAS processing	10-11
DELFG	Interpolates values between two grids	10-13
ESVA	Edits a surface report at the cursor location	10-14
EXVA	Displays a VAS retrieval profile	10-16
FGRID	Generates RFVA grids from an MD file	10-18
<b>GACTOV</b>	Generates GAC TOVS retrievals	10-19
GFUN	Generates coefficients for retrieval estimates	10-22
GPVA	Displays a VAS guess profile	10-24
GVVA	Lists a grid value at the cursor location	10-26
<b>GWVA</b>	Generates geostrophic winds for an MD file	10-27
HIRTBA	Displays HIRS area information	10-29
IDVA	Initializes VASTEXT documentation and VRET MD file row header	10-30
IUMCRP	Sets an MSU calibration reference parameter file	10-31
LOVA	Lists the VASTEXT documentation file	10-33
MAKVPE	Generates a color enhancement for VAS derived imagery	10-34
MSUL	Generates a limb corrected MSU area	10-36
<b>MSUTBA</b>	Displays MSU area information	10-37
PLVA	Plots VAS retrievals or surface data over a GOES satellite image	10-38
PTVA	Plots a scatter diagram of a data file	10-41
QUIKTI	Examines a raw TIP area in HRPT, LAC or GAC format	10-43
RFVA	Generates retrieval grids with recursive filter analysis	10-44
SCLG	Smooths grids with a selected wavelength filter	10-47
SFVA	Generates grids of surface parameters	10-48
SMOOTH	Smooths an image by averaging it with a 3 x 3 pixel block size	10-50
SNDVA	Generates an energy analysis of a vertical sounding	10-52
SPVA	Edits a VASTEXT documentation file	10-54
SVRG	Loads or saves the RGCOMP file	10-56
TIPTI	Prepares raw data in a TIP area for TOVS processing	10-57
TOON	Calculates the VAS radiance bias from keywords MDF and GMDF	10-59
TOVRET	Generates TOVS sounding retrievals	10-61
TOVS1B	Converts TOVS 1-B archive data to a raw TIP area	10-63
TXVA	Copies VASTEXT documentation to or from a VASTEXT file	10-64
UGVAS	Updates VAS guess grids and MD files	10-65
VDVA	Lists all channels within the cursor	10-66
VL	Lists a single VAS retrieval	10-67
VPVA	Sets the file pointer for VAS processing	10-69
VRVA	Retrieves VAS temperature/moisture profiles and image products	10-70
VRVF	Generates VAS image products for the MSI mode	10-72
XRVA	Edits values in the MD file at the cursor location	10-73

Issued 4/93

ii

Issued 4/93

# **BSVA**

Compares a grid of computed brightness temperatures with an MD file of observed brightness temperatures.

Format BSVA channel [keywords]

Parameter channel V01 to V12, for VAS channels 1-12

Keywords

ADD=
1 adds to the RGCOMP file
0 initializes a RGCOMP file (default)

ALL= 1 uses all MD file reports
0 uses the retrievals not flagged (default)

ERR= gross error check; if the difference between observed and calculated TBBs is greater than the entered value, TBBs

are not used in calculating the bias factor

GRID= grid number (no default)

GRIDF= grid file number (default=VASTEXT)

LAT= min max minimum and maximum latitude

(default=VASTEXT)

LON= min max minimum and maximum longitude

(default=VASTEXT)

MDF= MD file number (default=VASTEXT)

NCD= 1 avoids cloudy retrievals

0 includes cloudy retrievals (default)

ROW= MD file row number (default=VASTEXT)

TBB= 1 writes the bias vector as brightness temperature

0 writes the bias vector as radiance (default)

Remarks

Bias values are stored in the VASTEXT file. MD linkage is through VASTEXT or keyword MDF. Grid file linkage is through VASTEXT or keyword GRIDF.

#### Examples

#### BSVA V02 GRID=2 TBB=1

This entry obtains the grid file and MD file numbers from VASTEXT, compares grid 2 with the MD file, and writes the resulting bias vector as brightness temperatures.

#### BSVA V08 GRID=15 NCD=1

This entry obtains the grid file and MD file numbers from VASTEXT, compares grid 15 with the MD file, and writes the resulting bias vectors as radiances. It avoids cloudy retrievals.

# **CGVA**

# Compares values in two grids.

Format	CGVA gr	id1 grid2 [keywords]
Parameters	grid1	first grid number
	grid2	second grid number
Keywords	ADD=	<ul> <li>1 adds to the RGCOMP file</li> <li>0 initializes the RGCOMP file (default)</li> </ul>
	BIAS=	<ul> <li>o subtracts bias from the observations at gridpoint locations in grid1</li> <li>adds bias to the observations at gridpoint locations in grid1 (default=0)</li> </ul>
	COLOR=	graphics color level (default=1)
	ERROR=	nonzero sets the gross error check to use in comparing values from two grids (default=999999)
	GOUT=	<ul> <li>writes output grid, size same as grid1</li> <li>does not write output grid (default)</li> </ul>
	GRIDF=	grid file number (default=current)
	INC=	increment for skipping grid points in the first grid (default=1, skips all points)
	LAT=	min max minimum and maximum latitudes (default=0; latitudes from grid1)
	LON=	min max minimum and maximum longitudes (default=0; longitudes from grid1)
	LSIZE=	height of the plotted digit, in pixels (default=6)
	OFF=	lat lon latitude and longitude offset (default=0)
	PLOT=	<ul> <li>plots comparisons between grids at grid1 gridpoints</li> <li>does not plot (default)</li> </ul>

### Remarks

CGVA makes statistical comparisons between two grids and displays the results on the text screen or plots them. Grids do not have to be the same size.

Individual values for grid1 and grid2 are saved in the file RGCOMP. If you do not set the grid file with keyword GFILE, use IGU SET before executing CGVA. If grid2 is not used, only values from grid1 are plotted.

### **Examples**

#### CGVA 2 5

This entry compares the values in grid 5 to the values in grid 2 and displays the result on the text screen.

#### CGVA 1 3 GRIDF=4100 PLOT=1

This entry plots the differences between grids 1 and 3, both of which are in grid file 4100, on the graphics. The statistics are also displayed on the text screen.

## **CMMD**

### Compares values in an MD file.

**Format** 

CMMD option level [keywords]

**Parameters** 

option any parameter in the MD file schema (default=Z)

WIN wind vector comparison

level any mb level (default=500 when option is Z)

SFC surface level for parameters

**Keywords** 

ADD= ON adds matches to the RGCOMP file

OFF initializes the RGCOMP file (default)

COLOR= graphics color level of the plotted digit (default=1)

DATA= ALL accepts all data

FLAG accepts only flagged data (default)

DELP= pressure interval for matching the second (WIND) MD

file row, in mb (default=matches the nearest mandatory

pressure)

DIST= distance spacing for matching reports, in degrees

(default=.2)

ERR= gross error maximum for accepting the match

(default=999999)

GRA= graphics frame number for the plot (default=current)

LAT= min max minimum and maximum latitude extents

(default=VASTEXT)

LEV2= second level for thickness, level minus LEV2

LON= min max minimum and maximum longitude extents

(default=VASTEXT)

LSIZE = height of the plotted digit, in pixels (default=6)

MDF= file1 file2 retrieval MD file numbers; the first file is the

verification standard; both files default to

VASTEXT

NRPT= number of repeat groups for VWIN files (default=1)

PAR= a different parameter for the second MD file

(default=WIN)

PLOT= ON plots on the graphics frame

OFF does not plot (default)

ROW= row1 row2 retrieval MD file row number from the

respective MDNR; row2 defaults to

VASTEXT; row1 has no default

SHR= minimum vertical shear for the wind match, in mps

(default=0)

SOURCE TOVS McIDAS TOVS processing (default=VAS or

CIMSS TOVS, depending on User Common)

WTYPE= type1 type2 wind type for the respective MD file

SP single pixel CC correlation

Remarks

CMMD compares data at coincident locations. For example, it can compare satellite retrievals with radiosondes or cloud wind vectors with rawinsondes. A particular parameter (e.g., 500 temp) from two MD file rows is compared over an area specified by latitude/longitude limits. Each data in the first row serves as the standard against which any data in the second row within a match distance is compared. Many values in the second row may be compared with a single value in the first. Statistics relevant to the set of comparisons are printed on the text screen. Use keyword PLOT to plot individual comparisons. The set is saved in a terminal-dependent file named RGCOMP which permits the concatenation of sets, e.g., for more than one time period.

See Also

Use command VPVA to set the VAS file pointer and command TXVA to make the VAS text available. Use command PTVA to obtain statistics for the concatenated set, plot a scatter diagram, and edit the sample to remove unrepresentative values, thereby improving your results.

### **Examples**

#### CMMD ROW=2

This entry compares the values of 500 mb heights between MD file row 2 and the MD row in the VASTEXT file. Both MD file rows are in the VASTEXT MD file. This entry also initializes RGCOMP and stores the comparison values there.

CMMD SPD 300 MDF=16 16 ROW=5 0 PLOT=ON COLOR=3 This entry compares 300 mb wind speeds at 12 GMT to those at 00 GMT for MD file 16. The 12-hour change in wind speed is plotted on the graphics frame in graphics color level 3.

#### CMMD T 500 ROW=1 6 ADD=ON

This entry compares 500 mb temperatures in row 1 to those in row 6 for the MD file named in the VASTEXT file. The values are added to the existing data in the RGCOMP file.

Issued 4/93 10-7

# **CMVA**

Compares MD file values to grid and plot differences.

Format	CMVA option	level [keywords]		
		the graphics from in graphies of		
Parameters	option	any parameter in the MD file schema (default=Z)		
	level	any mb level (default=500 mb if option is Z)		
		SFC surface level for the parameters		
Keywords	ADD=	<ul><li>adds the data comparison to the RGCOMP file</li><li>initializes the RGCOMP file (default)</li></ul>		
		o initializes the NGCOMI life (default)		
	ALL=	1 uses all MD file reports		
		0 does not use all reports (default)		
	BIAS=	if < 0, adds the bias value to the observed MD file value	ue:	
		if > 0, subtracts the bias value (default=0)		
	COLOR=	graphics color level (default=2)		
	COLON-	graphics color level (default-2)		
	CSORT=	parameter to sort on		
	DELP=	pressure tolerance around LEV; for the VWIN file		
		(default=0)		
	EDIT=	TOSS edits the values in the MD file if the value		
	2211	differs from grid by TOSS; TOSS is limited		
		to 2.5 RMS difference of all reports		
		(default=sigma of MD-NGNG value)		
	ERR=	gross error check used when comparing MD and grid	file	
		values (default=999999)		
	GRID=	grid number (default=0)	ě	
	GILID-	grid number (desaute 5)		
	GRIDF=	grid file number (default is from IGU SET)		
	LAT=	min max minimum and maximum latitudes for the		
		MD file reports (default=VASTEXT file)		
	LEV2=	upper pressure level for the thickness difference plot;		
	LE V. 2-	this value is subtracted from <i>level</i> (default=0)		

LON=	min max	minimum and maximum longitudes for the MD file reports (default=VASTEXT file)
LSIZE=	height of	the plotted digit, in pixels (default=6)
MDF=	MD file n	umber (default=VASTEXT file)
MESS=	YES NO	plots all records else do not clutter (default) does not plot all records
NRPT=	number o	f the repeat group for VWIN files (default=1)
PAN=	panel for	data plotting; the range is 1 to 4
PLOT=	•	differences on the graphics not plot (default)
ROW=	MD file ro	ow number (default=VASTEXT file)
SOURCE=	TOVS	McIDAS TOVS processing (default=VAS or CIMSS TOVS, depending on User Common)
STA=	YES	plots the statistics on the graphics; you must choose the location
	AUTO	plots the statistics on the current cursor location
	NO	does not plot statistics (default)
VSORT=	lower up	per sorts value limits
WGT=		alue (NGNG+1) above which the comparison is efault=0, does not read the weight grid)

#### Remarks

Before starting, set the grid file using IGU SET.

CMVA compares parameter values of a specified level between an MD file and a grid file. It displays the statistical comparison on the text screen and can plot the difference on a graphics frame.

Values are saved in the file RGCOMP. MD linkage is through VASTEXT file keywords. Grid linkage is through IGU SET or keywords. MD file values (ID number, MOD flag, latitude, longitude, retrieval type) are selected through MD file keys sort.

If you are plotting MD file and grid thicknesses, the second positional parameter should be the lowest pressure to assure MD thickness > 0.

#### **CMVA**

This entry compares the height at 500 mb between the VASTEXT MD file and the VASTEXT grid file and displays the statistics on the text screen.

### CMVA T 350 PLOT=1

.0 Campainted CIM orusins of organized bound and bloods tataments of

This entry plots the 350 mb temperature differences between the VASTEXT MD file and the default grid file.

## CMVA Z 500 GFILE=4110 GRID=12 ADD=1 PLOT=1

This entry plots the 500 mb height differences between the retrievals and grid 12 of grid file 4110. It stores the ID numbers and height values from both the retrieval and grid in the RGCOMP file, adding this information after any previously stored data.

# CMVA T 500 LEV2=850 MDF=4181 ROW=13 GRID=22 PLOT=1

This entry plots the 850 to 500 mb thickness differences between MD file 4181, row 13, and grid 22 of the default grid file. The RGCOMP file is initialized using thickness values from each data source and the MD file ID number (ID number meaning report 10, report 51, etc.).

# **CSVA**

# Fills the surface MD file for VAS processing.

Format	CSVA file [keywords]		
Parameter	file	MD file number for the data output	
Keywords	ADD=	row number to add data to in the RSVC file (default= use new row with number corresponding to keyword TIME)	
	AUTO=	use the first valid row of the input MD file (default=0)	
	BUOY=	YES uses a buoy data MD file as the input MD file NO does not use the file (default)	
	DAY=	Julian day of the input surface data, YYDDD (default=VASTEXT file)	
	ISFC=	YES goes to the current ISFC data NO does not go the current ISFC data (default)	
	ISHP=	YES goes to the current ISHP data NO does not go the current ISFC data (default)	
	LAT=	min max minimum and maximum latitude extents, in whole degrees (default=VASTEXT file)	
	LON=	min max minimum and maximum longitude extents, in whole degrees; West is positive, East is negative (default=VASTEXT file)	
	MDF=	MD file number of the data source (default=current SVCA file)	
	SHIP=	YES uses a ship data MD file as the input file NO does not use the ship data MD file (default)	
	SOURCE=	TOVS to process TOVS data (default=VAS or CIMSS TOVS, depending on User Common)	
	SVCA=	YES goes to the current SVCA data NO does not go the current SVCA data (default)	

SYN=

YES

goes to the current SYN data

NO

dose not go to the current SYN data (default)

TIME=

hour of the input surface data (default=VASTEXT file

time, truncated)

Remarks

CSVA fills an MD file (schema RSVC) with special parameters (1000 mb height, mean sea level temperature and surface dew point depression) from conventional surface data (schema SVCA) for use in VAS. The status flag in the VASTEXT file must be set to 1 (see SWVA).

**Examples** 

**CSVA 2000** 

This entry calculates the 1000 mb height, mean sea level temperature and surface dew point from the current SVCA file and stores the results in MD file 2000.

CSVA 1112 TIME=13

This entry loads MD file 1112 with surface data at 1300 GMT appropriate to the area defined by the VASTEXT file.

# **DELFG**

Interpolates values between two grids.

**Format** 

DELFG grid1 grid2 dgrid ngrid [keywords]

**Parameters** 

grid1 first grid number (default=0)

grid2

second grid number (default=0)

dgrid

destination grid number (default=next available)

ngrid

number of grids to interpolate (default=1)

Keywords

DEL=

increment for interpolating (grid1+DEL\*(grid2 - grid1))

(default=0)

GRIDF= in out input and output grid file numbers

(default=LUC(6))

Remarks

Values are written into a third grid.

**Examples** 

DELFG

This entry interpolates the current grid's values.

DELFG 4129 4130 4140 DEL=.5

This entry interpolates to the midpoint between grids 4129 and 4130

and writes the values into grid 4140.

# **ESVA**

Edits a surface report at the cursor location.

**Format** 

ESVA [keywords]

**Keywords** 

DD= surface dew point depression value, Kelvin \* 100

1 deletes the value

MDF=

retrieval MD file number (default=VASTEXT or CIMSS

TOVS)

PSL=

altimeter setting, in mb (default=0)

1 deletes the value

ROW=

retrieval MD row number (default=VASTEXT or CIMSS

TOVS)

SIZE=

size of the plotted value

TSFC=

converts this surface temperature to sea level, Kelvin \* 100

(default=0)

1 deletes the value

TSL=

temperature value at mean sea level, Kelvin \* 100

1 deletes the value

Z100 =

1000 mb height value, in meters (default=0)

1 deletes the value

Remarks

ESVA only works on retrieval surface MD files, schema RSVC.

To delete values, make the keyword value 1. Otherwise, the values of keywords are substituted. If no report exists in the cursor, one is added; all reports within the cursor are affected, so make the cursor small.

### ESVA TSL=1

This entry deletes all TSL values within the cursor.

### ESVA TSL=28300 DD=1 Z100=85

This entry deletes all DD values within the cursor. It changes the TSL values to 283°K and the Z100 values to 85 meters.

### ESVA PSL=1010 MDF=6713 ROW=1

This entry changes the value of PSL in row 1 of retrieval surface MD file 6713 to 1010 mb.

# **EXVA**

Displays a VAS retrieval profile.

**Format** 

EXVA retrieval-1 retrieval-2 [keywords]

**Parameters** 

retrieval-1

number of the first retrieval (default=0)

retrieval-2

number of last retrieval (default=0)

**Keywords** 

DIST=

search radius for finding the retrieval MD file report, in

degrees latitude (default=0.50)

MDF=

MD file number (default=VASTEXT file)

PAR=

 $\mathbf{T}$ temperature profile

TD

dew point profile (default=temperature and

dew point)

ROW=

MD file row number (default=VASTEXT file)

SOURCE=

TOVS for McIDAS TOVS processing (default=VAS or

CIMSS TOVS, depending on User Common)

Remarks

This program examines retrieval profiles in terms of temperatures and temperature differences between the retrieval and first guess profile.

Either the cursor location on the satellite image is used to find the nearest retrieval, or the number (or range of numbers) of specific retrievals is used for selection from the retrieval MD file (schema VRET). Final retrieval temperatures, from surface to 200 mb, as well as the differences between the retrieval and first guess temperatures are displayed in Kelvin\*100 on the text screen for levels from the surface to 200 mb. Retrieval MD file and row numbers are linked through the VASTEXT file.

### **EXVA**

This entry displays the temperature and dew point profile for the cursor location.

#### EXVA 135 137

This entry lists the temperature and dew point profiles for retrieval numbers 135, 136 and 137.

#### EXVA 67 MDF=6880 ROW=2 SOURCE=TOVS

This entry lists the temperature and dew point profiles for retrieval number 67 using row 2 of MD file 6680, which contains TOVS retrieval data.

Issued 4/93

# **FGRID**

Generates RFVA grids from an MD file.

**Format** 

FGRID [keywords]

**Keywords** 

array to indicate channel usage, 11 entries (default=0) EX=

increment (default=VASTEXT) INC=

min max latitude range (default=VASTEXT) LAT=

min max longitude range (default=VASTEXT) LON=

function MD file (default=VASTEXT) MDF=

RF=RF factor (default=1.0)

MD file row number (default=VASTEXT) ROW=

nonzero means do not do temperature grids (default=0) TEM=

Remarks

Use FGRID to generate derived product imagery.

**Examples** 

**FGRID** 

This entry generates RFVA grids using the VASTEXT parameters.

FGRID TEM=1

This entry generates RFVA grids using the VASTEXT parameters; it does not generate temperature grids.

FGRID MDF=3129 ROW=7 LAT=25 35 LON=80 90

This entry generates RFVA grids from row 7 of MD file 3129 covering

25° to 35°N and 80° to 90°W.

# **GACTOV**

### Generates GAC TOVS retrievals.

F	0	rı	m	a	t
•	•	• •	•••	_	•

GACTOV harea marea rfile row gfile sgridf zgrid tgrid dgrid [keywords]

**Parameters** 

harea HIRS area number (no default)

marea MSU area number (no default)

rfile retrieval MD file number (no default)

row retrieval MD row number (no default)

gfile guess MD file; required only if GSS=G (no default)

sgridf surface grid file number; required only if SFC=0

(no default)

zgrid surface z grid number; required only if SFC=0 (no default)

tgrid surface t grid number; required only if SFC=0 (no default)

dgrid surface d grid number; required only if SFC=0 (no default)

**Keywords** 

BEG= line ele beginning line and element (default=cursor position, except in the background)

BOX= square retrieval box size, must be an odd number; maximum is 7 (default=3)

BUG= 1 text screen for debugging diagnostics

2 printer for debugging diagnostics (default=0)

CLOUD= 1 does not calculate cloud height

0 calculates cloud height (default)

COEF= coefficient file option for GSS=R; any valid coefficient file,

up to 8 characters (default=synthetic)

DMS= MSU/HIRS search radius, in degrees (default=3)

FIX=	<ul> <li>fixed retrieval location, no call to PICCLR</li> <li>no fixed retrieval location (default)</li> </ul>					
FOV=	1 single sample retrieval (default=0)					
GAM=	matrix conditioning parameter (default=1)					
GSS=	C uses climatology as the guess data R uses regression as the guess data G uses grid as the guess data (default)					
НІМА=	Y raises the highest permissible ground level N does not raise the ground level (default)					
IRF=	<ul> <li>initializes the row header and zero retrieval counter</li> <li>does not initialize the row header and zero retrieval counter (default)</li> </ul>					
MWO=	1 output MSU and HIRS retrieval, channels 1-3 (default=0)					
OFF=	maximum difference in seconds between HIRS and MSU start times (default=60)					
PLT=	Z plots 500 mb heights S SFC skin temperature T total of totals O total ozone NO does not plot (default)					
SFC=	<ul> <li>1 no surface data input</li> <li>0 includes surface data input (default)</li> </ul>					
SIZ=	line ele line and element extent of the RTVL area (default=1040 56)					
SPC=	line ele line and element spacing of the retrievals (default=BOX BOX)					
TOP=	L low topography resolution H high topography resolution (default)					
TUNFIL=	root name of the tuning file (default=TOVTUN)					

#### Remarks

Run this procedure in the background with REGION=4000k. The foreground version is TOVRET.

The last four positional parameters may be omitted if SFC=1.

The fifth positional parameter may be omitted if GSS=C or R.

named trail respectively a real property and resident

# **Example**

GACTOV 6672 6673 6681 2 6687 6703 1 2 3 GSS=G SFC=0 TOP=L PLT=Z

This entry generates sounding retrievals from HIRS area 6672 and MSU area 6673. It uses retrieval MD file 6681, row 2, guess MD file 6687, and surface grid file 6703, grids 1, 2 and 3. It reads the low resolution topography file and plots 500 mb heights.

# **GFUN**

Generates coefficients for retrieval estimates.

F	O	r	n	1	a	t
	v			ш		•

GFUN [keywords]

**Keywords** 

BIAS= if nonzero, uses the bias vector in VASTEXT (default=0)

ESFC = t m

noise estimates for surface temperature and

moisture (default=2 1)

EX=

n1...n11 noise estimates for each of the 11 bands

GMDF=

guess MD file number (default=VASTEXT)

INC=

analysis grid increment, degrees\*10 (default=1)

LAG=

LAG angle for sunrise, in degrees (default=20°)

LAT=

min max minimum and maximum latitudes

(default=VASTEXT)

LON=

min max minimum and maximum longitudes

(default=VASTEXT)

MDF=

MD file number (default=VASTEXT)

ROW=

MD row number (default=VASTEXT)

SAT=

satellite number, McIDAS GOES convention

(default=VASTEXT)

SFC=

1 does not use surface analysis

0 uses surface analysis (default)

TERM=

terminal number (default=local)

Remarks

GFUN computes coefficients required to produce retrieved estimates of temperature and precipitable water. Coefficients are written to an MD file with schema VSIM. A VAS first guess MD file is required.

See Also

See commands LOVA and SPVA for inspecting and setting VASTEXT

file pointers.

**GFUN** 

This entry generates the coefficients for retrieval estimates using the VASTEXT parameters.

#### GFUN INC=10 SFC=1

This entry generates coefficients using VASTEXT parameters and 1 degree increments, without surface analysis.

Issued 4/93 10-23

For option 2. Otherways accounts the cover profile at D file (columns

# **GPVA**

Displays a VAS guess profile.

#### **Formats**

GPVA C surface lat lon file [keywords] GPVA P surface lat lon file [keywords] GPVA X surface lat lon file [keywords]

#### **Parameters**

C displays the climatology guess profile

P displays a particular profile, such as Green Bay radiosonde

X displays the MD file guess profile as defined in *file*; if *file* is not defined, the VASTEXT file profile is used (default)

surface X uses the surface grids defined in the VASTEXT file (default)

1 does not use surface analysis

latitude of the guess \* 100 (default=cursor location)

lon longitude of the guess \* 100 (default=cursor location)

file MD file number for the guess; do not use this parameter for the C and P options (default=VASTEXT file)

### **Keywords**

GRID= z t d 1000 mb geopotential height grid number; sea level temperature grid number; dewpoint depression grid number (default=VASTEXT)

SGRIDF= surface grid file number (default=VASTEXT)

TERM= terminal number for reading the VASTEXT file (default=local)

### Remarks

This program displays the VAS guess profiles of temperature, dew point and mixing ratio at one position on the text screen.

For option X, this program accesses the guess profile MD file (schema VGSS) created by GSVA. Alternative options are to display a climatological guess or a radiosonde profile to be used as a guess. Information necessary to provide the radiosonde profile is linked through VASTEXT entries.

## **GPVA**

This entry displays the current VASTEXT guess MD file profile on the text screen using the cursor location.

# GPVA P X 4000 9000

This entry displays the radiosonde profile from the radiosonde station closest to  $40^{\circ}N$  latitude,  $90^{\circ}W$  longitude.

# **GVVA**

Lists a grid value at the cursor location.

**Format** 

GVVA grid [keyword]

**Parameter** 

grid

grid number to examine

Keyword

GRIDF= grid file number (default set by MDU SET)

**Example** 

GVVA 7 GRIDF=1024

This entry lists the values in grid 7 of grid file 1024.

# **GWVA**

Generates geostrophic winds for an MD file.

**Format** 

GWVA grid level [keywords]

**Parameters** 

grid grid number

level

pressure level of the winds if they are written into the

MD file, in mb (default=0, no winds saved)

Keywords

COLOR= graphics color level of the wind barb (default=1)

DELT= number of hours between grid and NGOLD (default=0)

GRID= grid number of the previous analysis; used for isallobaric or

ageostrophic option (default=0)

MDF= MD file number (default=VASTEXT file)

PLOT= 1 plots ship wind barbs

0 does not plot barbs (default)

ROW= MD file row number (default=VASTEXT file)

TYPE= AG ageostrophic

G geostrophic

GR gradient (default)

IS isallobaric

Remarks

GWVA generates dynamic winds from gridded geopotential data. For isallobaric or ageostrophic estimates, enter two grids separated by DELT number of hours.

Wind vectors are generated at retrieval locations using a previously generated height grid (see BNVA). Wind results (if LEV≠0) are stored in the retrieval MD file currently listed in the VASTEXT file. The old grid is used only for the isallobaric and ageostrophic options.

GWVA 35

This entry generates the gradient winds from grid 35 but does not store the results.

## GWVA 19 850 COLOR=2 PLOT=1

This entry generates the 850 mb gradient winds from grid 19 in graphics color level 2 and stores them in a retrieval MD file.

### GWVA 29 X TYPE=G

This entry generates the geostrophic winds from grid 29, but does not store them.

# **HIRTBA**

# Displays HIRS area information.

**Format** 

HIRTBA area line ele

**Parameters** 

HIRS area number area

line

HIRS image line number, 1-based (default=0)

ele

HIRS image element number, 1-based (default=0)

Remarks If the line and/or element number is zero, the cursor position is used. The displayed information consists of line, element, latitude, longitude, local and solar zenith angle, low and high resolution land/sea tags and topography, channel 1-19 brightness temperatures and channel 20 radiance.

**Examples** 

HIRTBA 6673 29 47

This entry displays information on line 29, element 47 of HIRS area 6673.

**HIRTBA 6676** 

This entry displays information on area 6676 using the pixel indicated by the cursor.

# **IDVA**

Initializes the VASTEXT documentation file and VRET MD file row header.

**Format** 

IDVA file row [keywords]

**Parameters** 

file MD file number (default=0)

row

MD file row number; the range is 1 to 16 (default=0)

**Keywords** 

AUTO= 1 runs without a corresponding TV image

O does not run without a corresponding TV image

(default)

IBOX= line ele line and element size of the retrieval box

(default=5 5 for 16 km resolution data; 11 11

for 8 km resolution data)

LAT= min max minimum and maximum latitude extents, in

whole degrees (no default)

LON= min max minimum and maximum longitude extents;

West is positive; East is negative (no default)

Remarks

Set the VAS pointer to select VAS or TOVS processing, as well as the appropriate sounder area if necessary. If MDRR is specified, the row header is initialized to zero.

**Examples** 

**IDVA** 

This entry initializes the VASTEXT file using the values from the currently displayed image.

IDVA 1101 1

This entry initializes MD file 1101 (schema VRET), row 1 header, and writes the VASTEXT file entries using the currently displayed image.

IDVA 1101 5 LAT=25 55 LON=70 110 AUTO=1

This entry initializes MD file 1101 (schema VRET), row 5 header. It determines the beginning and ending points within the specified lat/lon bounds for which data exists and writes them to the VASTEXT file in both satellite and earth coordinates. It also writes the other words of the VASTEXT file.

# **IUMCRP**

Sets an MSU calibration reference parameter file.

_					
_	-	-	m	9	•
	u			•	

**IUMCRP** ss date type (loc value loc value . . .) [keywords]

**Parameters** 

sensor source number SS

date year and day, YYDDD (default=current)

CAVG type average of the instrument counts for a channel

> CLIM lower and upper limits of the instrument

> > counts for a channel

CSIG standard deviation of the instrument counts

for a channel

LOOK examines the record only; does not update the file brightness temperature of the calibration target

TARG

1 to 8 for CAVG loc

> 1 to 4 for CLIM 1 to 8 for CSIG

none for LOOK

1 for TARG

value

new value for the parameter; none for the LOOK option

# **Keywords**

MORE= YES if making more changes to the same new record

> NO if not making more changes (default)

NULL= record number to delete; positional parameters are ignored

(no default)

SORT= sorts the updated file (default); if MORE=YES, YES

you must enter SORT=YES

NO does not sort the updated file

### Remarks

The calibration reference parameter file contains limits on certain parameters used to calibrate MSU data. These limits are kept for each satellite. If the satellite's parameters tend to drift over time, many time-stamped records may be created for one satellite.

IUMCRP should only be used if, when running the TIPTI command, many messages are issued warning that limits are being exceeded. These messages refer to the *type*, *loc* and *value* parameters in IUMCRP.

### Example

In running TIPTI for NOAA-11 (McIDAS satellite 61), the message below appears repeatedly.

CL: .15213E+4 .GT.CLIM(2): .15E+4

This indicates that a calibration parameter has drifted higher than it used to be. To examine the appropriate record, enter:

#### **IUMCRP 61 X LOOK**

This entry displays all the parameter values for that record. To set a new upper limit, enter:

#### IUMCRP 61 X CLIM 2 1600

This entry changes the second CLIM value from 1500 to 1600.

# LOVA

Lists the VASTEXT documentation file.

**Format** 

LOVA

See Also

Use command VPVA to select the VAS data pointer before executing LOVA.

Example

**VPVA 4180** 

This entry sets the VAS pointer to sounder area 4180.

LOVA

This entry lists the current options for processing sounder area 4180

on the text screen.

# **MAKVPE**

images.

Generates a color enhancement for VAS derived imagery.

Format	MAKVP	E type bk1 bk2 bk3 bk4 [keywords]		
Parameters	type	<ol> <li>VAS precipitable water vapor label (default)</li> <li>VAS lifted index label</li> <li>VAS total totals index label</li> <li>VAS sea surface temperature scale label</li> <li>standard IR temperature scale label</li> </ol>		
	bk1	breakpoint between beige and blue pseudocolors (default=10)		
	bk2	breakpoint between blue and yellow pseudocolors (default=17)		
	bk3	breakpoint between yellow and red pseudocolors (default=24)		
	bk4	end of the red range breakpoint (default=31)		
Keywords	BW=	<ul> <li>0 color image enhancement (default)</li> <li>1 black and white image enhancement</li> </ul>		
	COLOR	= graphics color level (default=-1, blank)		
	GRA=	graphics frame number (default=current)		
	LINE=	TV line for the graphics label (default=465)		
Remarks	as preci	Macro MAKVPE is designed for use with VAS derived imagery such as precipitable water vapor or stability index. Gray levels 1 to 36 are pseudocolored; all other levels (37 to 63) are black and white cloud		

#### **MAKVPE**

This entry generates a color enhancement for VAS precipitable water vapor sounding imagery.

### MAKVPE 1 6 12 18 24 COLOR=4

This entry generates a color enhancement for VAS precipitable water vapor sounding imagery, with breakpoints at gray levels 6, 12, 18 and 24. The water vapor scale is plotted over a background in graphics color level 4.

### MAKVPE -1 LINE=20

This entry generates a standard IR temperature scale at the top of the screen.

# **MSUL**

Generates a limb corrected MSU area.

**Format** 

MSUL sarea darea

**Parameters** 

sarea

source MSU area without limb correction applied

darea

destination MSU area with limb correction

Remarks

MSUL immediately images MSU data for meteorological nowcasting. Areas without limb correction are used for sounding retrievals.

See Also

For MSU areas created by TIPTI and converted by MSUL, use command AAMAP or a similar remapping tool to create images with North up and East to the right.

Example

MSUL 6672 6681

This entry reads MSU area 6672, applies limb correction to the data and stores the results in area 6681.

# **MSUTBA**

Displays MSU area information.

**Format** 

MSUTBA area line ele [keyword]

**Parameters** 

area number

line image line number, 1-based (default=0)

ele image element number, 1-based (default=0)

Keyword

HEAD= YES displays area header data

NO does not display area header data (default)

Remarks

If an element number is not specified, information on the entire line is displayed. If neither line nor element is specified, the cursor position is used.

The displayed information includes line, element, time, latitude, longitude, surface type and elevation, and temperatures in bands 1 to 4. If a limb corrected MSU area is used, the data for band 5 (surface only contribution) is also displayed.

**Examples** 

MSUTBA 6674 9 6 HEAD=YES

This entry displays information on the pixel in line 9, element 6 of area 6674. It also displays the header information in area 6674.

MSUTBA 6677

(all TX The Variation of the Property

This entry displays information on area 6677 using the pixel indicated by the cursor.

# **PLVA**

Plots VAS retrievals or surface data over a GOES satellite image.

Format	PLVA optio	n level [keywords]
Parameters	option	parameter name (Z, T, etc.) to plot; use MDO to list VRET or RSVC schema MD file parameters (default=Z)
	level	mb level of the parameter (default=500 if option is Z)  SFC surface  DIFF TBB differences
Keywords	ALL=	<ul> <li>plots all MD file values including the rejected values</li> <li>does not plot all values (default)</li> </ul>
	COLOR=	graphics color level (default=1)
	CSORT=	parameter to sort on; cannot be a repeated parameter
	CTYPE=	wind types to sort on (RAOB, GRID, IR, etc.) MDF uses the VWIN schema
	DELP=	pressure tolerance around <i>level</i> for the VWIN file (default=0)
	DIST=	latitude/longitude spacing of degrees for matching reports in time (default=0.2)
	GRA=	plots on this graphics frame (default=current)
	LAT=	min max minimum and maximum latitudes for plotting (default=VASTEXT file)
	LEV2=	uses the second level if a thickness plot is desired; it should a be lower mb level (default=0)
	LON=	min max minimum and maximum longitudes for plotting (default=VASTEXT file)
	LSIZE=	height of the letters, in pixels (default=6)

MDF= retrieval or surface MD file number; schema VRET or

RSVC (default=VASTEXT file)

NRPT= number of the repeat group for VWIN files

PAN= graphics panel; the range is 1 to 4

PRO= SAT satellite projection
MERC Mercator projection

Mercator projection

RANGE= first last first to last report to plot (default=every

report)

ROW= MD file row number (default=VASTEXT file)

ROW2= second (early) MD file row number for forming

differences in time (default=VASTEXT file)

SCALE= integer scaling, 10 \*\* scale (default=2)

SOURCE TOVS for McIDAS TOVS processing (default=

VAS or CIMSS TOVS, depending on User

Common)

VSORT= lower upper lower and upper limits to sort on

Remarks If MD keywords are not used, MD linkage is set through VASTEXT

file entries.

LAT/LON extents, if not entered via keywords, are taken from the

VASTEXT file. Change the values with command IDVA.

Examples PLVA

This entry plots the height at 500 mb over the current satellite image

using the VASTEXT file for MD file and row numbers.

PLVA T 500

This entry plots retrieval 500 mb temperature values with the

VASTEXT file and other defaults.

PLVA RH3 X MDF=2615 ROW=1

This entry plots upper level (band 10) layer relative humidity values

from MD file 2615, row 1.

PLVA TDIF 700

This entry plots the difference of retrieval minus first guess values for

700 mb temperatures.

#### PLVA V06 DIFF

This entry plots the difference of calculated (from retrieval) brightness temperature minus observed brightness temperature values for band 6, with the VASTEXT file and other defaults.

#### PLVA Z 300 LEV2=500

This entry plots retrieval thicknesses between 300 and 500 mb with VASTEXT and other defaults. Note that the higher elevation is the second positional parameter; otherwise negative thicknesses are plotted.

# **PTVA**

Plots a scatter diagram of a data file.

# **Format**

PTVA option interval square [keywords]

### **Parameters**

option 0 plots a scatter diagram on the graphics without editing (default)

1 edits the points in a scatter diagram

interval axis interval; must be divisible by 5 (default=50)

square 1 uses the same interval extents on the x and y axes to make the graph square (default=0)

## Keywords

RANGE= n1 n2 first and last records for the plot

TERM= nonzero forces no terminal dependence

XVAL= record position of the x parameter; the range is 2 to 5 (default=2)

YVAL= record position of the y parameter; the range is 2 to 5 (default=3)

#### Remarks

PTVA displays the regression equation for the best fit line as well as the mean, TMS and correlation coefficient relating to the data on the text screen.

To edit data, run PTVA <u>twice</u>. First run it with *option*=0, so data to be plotted is taken from the statistics file RGCOMP and written into the data file VRTEMP. Then to delete some data, run PTVA with *option*=1. Deletions are made only on VRTEMP, not the original data set.

For option=1, data is edited with the cursor. To edit, press the space bar to delete each report, and type R END to end the process. You can edit up to 200 reports at a time. Once the points are deleted and R END typed, a new point plot and best fit line are drawn. Option 1 can be repeated to continue editing, but results are destroyed by the first execution with option 0.

### PTVA

This entry plots a scatter diagram and best fit line of the data file RGCOMP on the graphics without editing.

#### PTVA 1

This entry edits the desired data points with the cursor, after which the VRTEMP file is updated. A new scatter diagram and best fit line are drawn on the screen.

# **QUIKTI**

Examines a raw TIP area in HRPT, LAC or GAC format.

**Format** 

QUIKTI area [keyword]

**Parameter** 

area

raw TIP area number

Keyword

TIME=

start stop time to start and stop reading the TIP area

lines (default=reads all lines)

Remarks

Use this command to decide where to start command TIPTI. QUIKTI

does not perform parity checking; TIPTI does.

Example

QUIKTI 783

The 2 section street denit of the calledy Lasy Cabelle force spore

This entry examines raw TIP area 783 for good data.

# **RFVA**

Generates retrieval grids with recursive filter analysis.

**Format** 

RFVA parm level [keywords]

**Parameters** 

parm

parameter to grid; Z, T, etc.

level

any mb level

surface SFC

DIFF TBB differences

**Keywords** 

ALL=

nonzero, includes edited reports

BIAS=

value to subtract from the observations

CSORT= parameter to sort on; cannot be a repeat parameter

CTYPE= wind types to sort on, e.g., RAOB, GRAD, IR, VIZ, etc.;

maximum of 6

DELP=

pressure tolerance around level (default=0)

EDIT=

removes quality control

0 flags record in the MD file

ERR=

gross error check (real units); fit to first pass sigma < err <

999999

GGRIDF=guess grid file number (default=VASTEXT sounder area)

GMDF=

guess MD file number (default=VASTEXT)

GRID=

guess grid number (default=0, for no first guess)

GRIDF= output grid file (default=current)

GSS=

G uses VGSS MD file for first guess

INC=

increment in degrees\*10

LAT=

min max minimum and maximum latitude extents

(default=VASTEXT)

LEV2=

second level for thickness (level minus LEV2)

LON= min max minimum and maximum longitude extents
(default=VASTEXT)

MDF= MD file for the data (default=VASTEXT)

NCD= 1 nonzero excludes cloudy soundings

NODAT= 1 nonzero forces no data, guess only

NRPT= number of repeat groups for VWIN files

PW= cloud height assignment type, e.g., PW, APW, PW58,

PWHI, PWWI (default=PW)

R0= large scale radius filter (default=500 km)

RANGE= first last first to last report to use (default=every

report)

RF= subdensity fit factor (default=0.5, RAOB or 1.5, SAT)

RL= small scale radius filter (default=100 km)

ROW= MD file row number (default=VASTEXT)

SFC= 1 nonzero for no surface guess option

SOURCE TOVS McIDAS TOVS processing (default=VAS or CIMSS TOVS, depending on User Common)

T0= large scale tolerance filter (defaults to sigma < err <

2\*sigma)

TL= small scale tolerance filter (default=T0/6)

VSORT= lower upper sort value limits

WGS= weight factor 0-1 for guess (default=1)

WGT= 1 nonzero writes grid of pass weights; pass 1 is first argument, 2 is second

Remarks

RFVA generates a grid from an MD file.

#### **Examples**

RFVA TD 850 INC=10 GSS=G

This entry generates grids for the dew point at 850 mb.

RFVA T SFC LAT=40 50 LON=75 105 MDF=6672 ROW=1 GSS=G GMDF=6677 SOURCE=TOVS

This entry generates grids for surface temperatures in a box bounded by 40° and 50° North latitude, 75° and 105° West longitude. It uses the TOVS retrieval data in row 1 of MD file 6672, and the guess data in MD file 6677.

## **SCLG**

Smooths grids with a selected wavelength filter.

**Format** 

SCLG grid wavelength [keywords]

**Parameters** 

grid grid number to smooth

wavelength

wavelength to be filtered, in km (default=2000 km)

Keywords

GRID=

smoothed output grid number (default=first available

grid)

GRIDF=

grid file number (default=User Common value set by

IGU SET)

RSDL=

convergence residual in whole units

(default=0.1\*SIGMA)

SD=

saves the residual field in the next grid available after the smoothed grid, as well as the smoothed

0 does not save the residual field (default)

Remarks

The grid is smoothed into a "smoothed" and residual component. Residual is all wavelengths less than the wavelength indicated.

**Examples** 

SCLG 10

This entry smooths grid 10 using a wavelength of 2000 km for

filtering.

SCLG 25 500

This entry smooths grid 25 in the grid file set by IGU SET, using a

500 km wavelength for filtering.

## **SFVA**

Generates grids of surface parameters.

**Format** 

SFVA parm file [keywords]

**Parameters** 

parm DD dew point temperature

PSL sea level pressure TSK surface temperature

TSL temperature at mean sea level

U u wind component V v wind component Z100 1000 mb heights

file

output grid file for the surface data

Keywords

EDIT=

does not automatically edit the final gridded surface data

0 flags edited data in the the data MD file (default)

ERROR=

gross error tolerance (default=twice the standard

deviation)

**GGRIDF=** 

guess grid file number (default=VASTEXT)

GINC=

increment for selecting guess reports, in grid lengths

GMDF=

guess MD file number for the surface data

(default=VASTEXT)

GRID=

guess grid number (default=0, no first guess)

GSS=

G use the guess MD file, schema VGSS, as the first

guess grid

INC=

grid increment, in degrees \* 10 (default is determined

by LAT and LON extents)

LAT=

min max minimum and maximum latitude extents

(default=VASTEXT file)

LON=

min max minimum and maximum longitude extents

(default=VASTEXT file)

NODAT= 1 stores the guess grid as the final surface grid; no analysis was made using the surface MD file (default=0)

R0= large scale smoother (default=500 km)

RF= subdensity fit factor (default=1)

RL= small scale smoother (default=10 km)

ROW= row number in the surface MD file for TOVS

(no default)

RS= R0 to RL reduction factor (default=0.5)

SMDF= surface MD file number for TOVS (no default)

WGS= weight to give guess, relative to data (default=1 equal

weight)

#### See Also

See command CSVA to fill the VAS surface MD file (schema RSVC). See commands IGU, IGG and IGTV for accessing, listing and contouring grids.

#### **Examples**

#### **SFVA DD 1050**

This entry generates a grid of dew point temperatures and stores it in grid file 1050.

#### SFVA Z100 1111 GSS=G

This entry generates a grid 1000 mb heights using the guess MD file first guess option, and places it in grid file 1111.

#### SFVA Z100 1111

This entry is the same as the one above, except no first guess is used for the Barnes analysis.

## **SMOOTH**

Smooths an image by averaging it with a  $3 \times 3$  pixel block size.

**Format** 

SMOOTH sarea darea [keywords] "text

**Parameters** 

sarea source area to smooth (no default)

darea

destination area for the smoothed data (default=sarea)

"text

text to replace the memo portion of the area directory; displayed with command LA AREA FORM=EXP

Keywords

NP=

number of passes for smoothing; the practical range is 1 to

3 (default=1)

RAN=

v1 v2 range of pixel values to include in smoothing

(default=1 50)

Remarks

MAKVPE is designed for VAS-derived images such as precipitable water or lifted indexes. Values in the range 1 to 150 are assumed to be derived values; 151 to 255 are assumed to be clouds.

Area size cannot exceed 1500 elements. When NP=2, the result is center-weighted 5 x 5 block size. When NP=3, the result is center weighted 7 x 7 block size. Pixels out of range (keyword RAN=) are not changed or included in the weights.

The weights are listed below. The center point = (sum of (weight\*value))/(sum of weights).

Weights for 1 pass:					W	Weights for 2 passes:							
0	Ö	0	0	0	0	0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	1	2	3	2	1	0
0	0	1	1	1	0	0	0	2	4	6	4	2	0
0	0	1	1	1	0	0	0	3	6	9	6	3	0
0	0	1	1	1	0	0	0	2	4	6	4	2	0
0	0	0	0	0	0	0	0	1	2	3	2	1	0
0	0	0	0	0	0	0	0	0	0	0	0	0	0

Weights for 3 passes:

1 3 6 7 6 3 1 3 9 18 21 18 9 3 6 18 36 42 36 18 6 7 21 42 49 42 21 7 6 18 36 42 36 18 6 3 9 18 21 18 9 3 1 3 6 7 6 3 1

#### **Examples**

#### SMOOTH 5000 "SMOOTHED IMAGE

This entry smooths the image in area 5000, replacing the memo portion of the area directory with the message SMOOTHED IMAGE.

## SMOOTH 5710 5721 NP=2 "SMOOTHED VERSION OF AREA 5710

This entry smooths the image in area 5710 with two passes and places it in area 5721. The message SMOOTHED VERSION OF AREA 5710 is placed in the memo portion of the area directory.

#### SMOOTH 5711 RAN=1 255

This entry smooths the image in area 5711 and writes it back to area 5711 using the entire range of data.

## **SNDVA**

Generates an energy analysis of a vertical sounding.

**Format** 

SNDVA file1 file2 time date [keywords]

**Parameters** 

file1 upper air MD file number

file2 ENGY MD file number

time time of the sounding data, HH:MM:SS or HHMMSS

day year and day of the sounding data, YYDDD

**Keywords** 

COL= number of the column to process (default=ALL)

IROW= row number of the input to override the day-time search

OROW= row number for the output (default=MDRR)

SIG= significant level MD file associated with file1

TYPE= CTF CTF type file

Remarks

Various thermodynamic parameters, such as buoyant energies and stability parameters, are calculated from vertical profiles (satellite or radiosonde) and stored in MD file ENGY.

SNDVA uses a one-dimensional updraft model to compute or plot the following information from sounding data.

- (u,v) components of the horizontal wind at each level
- saturation vapor pressure and relative humidity at each level
- virtual temperature of the environment and of a lifted parcel at each level
- value of the minimum wet-bulb potential temperature, height at which it is reached, and wind direction and speed at that height
- average magnitude of the shear vector and average turning of the wind in two layers: surface to 3 km and 3 to 10 km

- mean wind from 3 to 10 km
- height, pressure, temperature and mixing ratio at the lifting condensation level
- density, potential temperature and wet-bulb potential temperature at each level
- · mixing ratio of liquid water for the parcel at each level
- height at which the wet-bulb temperature is 0°C
- lifted index
- vertical velocity profile for the convective cloud
- mean Richardson number between the cloud base and 10 km

#### Example SNDVA 13 83 12 86203 SIG=23

This entry analyzes the vertical sounding in MD files 13 and 83 at 12 GMT for day 86203. The significant level data is in MD file 23.

## **SPVA**

TGRID=

TIME=

### Edits a VASTEXT documentation file.

Format	SPVA [keyw	ords]				
Keywords	AREA=	visible area number; corresponds to a sounder file				
	DAY=	sensor source, year and Julian day, SSYYDDD				
	DGRID=	grid number of the surface dew point depression analysis				
	GMDF=	number of the VAS first guess MD file, schema VGSS				
	GRIDF=	number of the grid file for the VAS first guess fields				
	GROW=	number of the wind first guess file				
	LAT=	min max minimum and maximum latitude range (no default)				
	LON=	min max minimum and maximum longitude range (no default)				
	MDF=	number of the VAS retrieval MD file, schema VRET				
	NRET=	number of retrievals; NRET is reset in the retrieval MD file row header (default=0)				
	PGRID=	grid number of the sea level pressure analysis				
	ROW=	row number of the VAS retrieval MD file				
	SGRIDF=	number of the grid file for VAS surface analysis				
	SMDF=	number of the VAS retrieval surface MD file, schema RSVC				
	SROW=	row number of the VAS retrieval surface MD file				

analysis (TSL)

hour\*10000

grid number of the mean sea level temperature

WGMDF= row number of the wind first guess MD file

WMDF= number of the wind MD file

WROW= row number of the wind MD file

ZGRID= grid number of the 1000 mb height analysis (Z100)

Remarks Command SPVA enters values into the VASTEXT documentation file.

Use it to set or change keyword values.

See Also To check the current VASTEXT file, see command LOVA.

Examples SPVA ROW=4
This entry sets the VAS retrieval surface MD file row number to 4.

The MD file number stays the same.

SPVA GMDF=1121 SMDF=1111 SROW=13 SGRIDF=1111 ZGRID=4 TGRID=5 DGRID=6

This entry sets the VAS first guess MD file to 1121, the VAS retrieval surface MD file to 1111, row 13, and the surface analysis to grids 4 through 6 in grid file 1111.

## **SVRG**

Loads or saves the RGCOMP file.

**Formats** 

SVRG IN file

SVRG OUT file

**Parameters** 

IN receives a file

OUT saves a file

file name of the saved file

Remarks

SVRG loads or saves the RGCOMP file used for statistical

comparisons.

Example

SVRG IN CMH1

This entry returns the file CMH1 into the terminal dependent group.

## TIPTI

Prepares raw data in a TIP area for TOVS processing.

Format TIF

TIPTI sarea harea marea [keywords]

**Parameters** 

sarea

source TIP area number

harea

destination area for processed HIRS data

marea

destination area for MSU data

Keywords

DATA=

HRPT

sarea contains HRPT data

GAC LAC sarea contains GAC data sarea contains LAC data

(default=determined internally)

LINE=

beg end

line extents to examine in the TIP area

(default=determinated internally)

PARITY=

OFF

does not perform parity error checking

(default)

ON

performs parity error checking

SS=

sensor source number for the NOAA satellite

(default=determined internally)

TIME=

start stop time to start and stop reading TIP area lines

(no default)

YEAR=

year of the data (default=year of the raw TIP data)

Remarks

TIME= and LINE= are mutually exclusive; use one or the other. If no beginning line or starting time is specified, processing begins with the first line. Similarly, if no ending line or stopping time is specifed, processing ends with the last line.

The normal procedure for TOVS retrievals is: TIPTI, PREPTI, LIMBTI, RETATI.

#### **Example**

TIPTI 783 6672 6673 TIME=23:45 00:15

This entry processes raw TIP area 783 from 23:45 of the starting day to 00:15 the following day (30 minutes of coverage). It places the HIRS data in area 6672, and the MSU data in area 6673.

## **TOON**

Calculates the VAS radiance bias from keywords MDF and GMDF.

Format	TOON g	ridf file [keywords]					
Parameters	gridf	grid file to store the grids of TBB; it is deleted, then recreated (no default)					
	file	VAS context file number (VASTEXT); it is read, then altered (no default)					
Keywords	BAND=	flag array for bands to tune (default=0,1,1,1,1,0,0,0,0,1,0)					
	EDIT=	99 avoids editing EDIT allows editing (default)					
	INC=	increment of the analysis (default=20)					
	LAT=	min max minimum and maximum latitude range (default=VASTEXT)					
	LON=	min max minimum and maximum longitude range (default=VASTEXT)					
	MDF=	MD file number containing the TBB observation to use (default=VASTEXT)					
	NCH=	upper limit on the channel number to analyze (default=6)					
	ROW=	in out MD file row numbers containing the TBB observations, input and output (default=VASTEXT)					
	TBB=	1 determines the bias in Kelvin					

0

#### Remarks

TBB is the observed brightness temperature. TBC is the calculated brightness temperature. TOON assumes that TBC is calculated. The bias vector is written into VASTEXT and printed.

determines the bias with radiance values

#### **Examples**

#### TOON 1001 38

This entry calculates the VAS radiance bias from keywords MDF and GMDF, VASTEXT file 38, and stores it in grid file 1001.

#### TOON 2800 26 MDF=1108 GMDF=1000

This entry calculates the VAS radiance bias from VASTEXT file 26, MD file 1108, and MD guess file 1000 and stores it in grid file 2800.

#### TOON 6721 16 LAT=30 50 LON=70 110

This entry calculates the VAS radiance bias from the VASTEXT MDF and GMDF file 16 using the area from 30° to 50° North latitude and 70° to 110° West longitude and stores the result in grid file 6721.

### TOVRET

Generates TOVS sounding retrievals.

_				
	-	•	-	•
	п	11		

TOVRET harea marea rmd row gmd gridf zg tg dg [keywords]

**Parameters** 

harea HIRS area created by command TIPTI

marea MSU area created by command TIPTI

rmd retrieval MD file number

row retrieval MD row

gmd guess MD file number; required only if GSS=G

gridf surface grid file number

zg geopotential height grid number

tg temperature grid number

dg dew point depression grid number

**Keywords** 

BEG= line ele line and element of the starting position

(default=0 in background, cursor position in

foreground)

BOX= square retrieval box size, must be odd number; maximum

of 7 (default=3)

CLOUD= 0 performs cloud height calculation (default)

1 does not perform cloud height calculation

COEF= LW file of regression coefficients when GSS=R (no default)

DMS= MSU/HIRS search radius, in degrees (default=3)

FIX= 0 no fixed retrieval location (default)

1 fixed retrieval location, no call to PICCLR

FOV= 0 multiple sample retrieval (default)

1 single sample retrieval

GAM= matrix conditioning parameter (default=1)

GSS= C climatology guess R regression guess

G guess grid (default)

HIMA= Y raise to the highest permissible ground level

N does not raise the ground level (default)

IRF= 1 initializes the row header and zero retrieval counter

0 does not initialize (default)

MWO= 1 outputs MSU and HIRS bands 1-3 retrieval

0 suppresses output (default)

OFF= maximum difference between HIRS and MSU start times,

in seconds (default=60)

PLT= Z plots 500 mb heights

S plots surface skin temperature

T plots total of totals

O plots total ozone

(default=does not plot)

SFC= 1 no surface data input

0 surface data input (default)

SIZ= line ele line and element size of the retrieval area

(default=108 56)

SPC= line ele line and element spacing of the retrievals

(default=BOX BOX)

TOP= L low resolution topography

H high resolution topography (default)

TUNFIL= root name of the tuning file (default=TOVTUN)

Remarks

If SFC=1, you can omit keywords GAM, IRF, HIMA and CLOUD.

Example

TOVRET 6673 6674 6689 1 6687 6686 1 2 3 BEG=2 2 GSS=G PLT=Z IRF=1

This entry generates TOVS retrievals using HIRS area 6673 and MSU area 6674, and places the results in row 1 of MD file 6689. It uses guess MD file 6687 and surface grid 6686, in which grid 1 contains 1000 mb geopotential heights, grid 2 contains sea level temperatures, and grid 3 contains sea level dewpoint depressions. The process starts at line 2, element 2, plots 500 mb heights, and initializes the MD row header and retrieval counter.

## TOVS1B

Converts TOVS 1-B archive data to a raw TIP area.

**Format** 

TOVS1B HIRSfile MSUfile area

**Parameters** 

HIRSfile input LW file of the HIRS 1-B data

MSUfile input LW file of the MSU 1-B data

area

output area of the raw TIP data

Remarks

If no HIRS file is specified, no HIRS data goes in the TIP area. Similarly, if no MSU file is specified, no MSU data goes in the TIP area. Be aware of this when using these TIP areas to create HIRS and/or MSU areas with command TIPTI.

**Examples** 

TOVS1B HIRS87261 X 6672

This entry creates TIP area 6672 from HIRS LW file HIRS87261. The next step is to run:

TIPTI 6672 6673 X

Note that no MSU area is created by command TIPTI.

TOVS1B X MSU85138 6674

This entry creates TIP area 6674 from MSU LW file MSU85138. The next step is to run:

TIPTI 6674 X 6675

This entry creates MSU area 6675, but does not create a HIRS area.

TOVS1B HIRSIBIN MSUSIBIN 6675

This entry creates TIP area 6675 from both a HIRS LW file and MSU LW file. Use command TIPTI to create a HIRS area or MSU area, or both.

## **TXVA**

Copies VASTEXT documentation to or from a VASTEXT file.

#### **Formats**

TXVA bfile efile TXVA file IN TXVA file OUT

#### **Parameters**

bfile beginning VASTEXT number to list

efile ending VASTEXT number to list

file VASTEXT file number

IN brings the VASTEXT file to the terminal from inventory

OUT writes text from the terminal to the VASTEXT file

#### Remarks

The inventory is a large file containing many VASTEXT files. Check the inventory file contents before <u>writing</u> text to make sure nothing is overwritten. For example, if you intend to use TXVA 10 OUT, first do TXVA 10 IN to see if a previous user stored a VASTEXT file there.

#### **Examples**

#### TXVA 1 IN

This entry brings text (VASTEXT) 1 to the terminal from inventory; this text replaces the original VASTEXT for that terminal.

#### TXVA 5 OUT

This entry stores the text (your current VASTEXT) in position 5 of the inventory.

#### **TXVA 1 6**

This entry displays a brief inventory of entries 1 through 6 of the large inventory file on the text screen.

## **UGVAS**

row

Updates VAS guess grids and MD files.

**Format** 

UGVAS row [keywords]

**Parameter** 

row number that corresponds to the time period used for the update; for example, if row is 4, data from row 4 or

before is used for the update

**Keywords** 

GMDF= MD file number containing the guess (default=1442; 1445)

GRIDF= grid file to store the first guess grids (default=1442 or 1445;

1442 for rows 1 to 5 of the MD file for VAS data, 1445 for

rows 6 to 10)

INC= grid increment for the analyses, \*10; for example, INC=20

specifies a grid increment of 2 (default=10)

LAT= min max latitude bounds (default=25 45)

LON= min max longitude bounds (default=60 95)

MDF= MD file number containing the VAS data (default=1441)

Remarks

The latitude and longitude bounds used are 5 degrees larger than the

input bounds.

Grid file 1440 is a scratch file.

**Examples** 

**UGVAS 5** 

This entry updates VAS guess grids and MD files from row 5 or before.

UGVAS 4 MDF=1441 GMDF=1442 GRIDF=1445 LAT=25 45 LON=60 95 INC=10

This entry generates grids in grid file 1445 from the latest retrievals (in MD file 1441, row 4) and first guess MD file 1442. The grids are used as the first guess for row 5 of the VAS retrieval. This entry uses a box with latitude 25 45, longitude 60 95, and a grid increment of 1 degree.

### **VDVA**

option

Lists all channels within the cursor.

**Format** 

VDVA option line ele diag

**Parameters** 

B brightness temperature and navigation parameters

(default)
F filters in use

N navigation parameters only

R radiance and navigation parameters

S spin budget

line line number (default=cursor location)

ele element number (default=cursor location)

diag nonzero gives additional information on calibration and raw data counts

Remarks

See Also

This command can check an individual sounding for unreasonable brightness temperatures or other values.

(Letterstander) at the Letter

Set the sounder area pointer with command VPVA before invoking

VDVA.

**Examples** 

**VDVA** 

This entry lists on the text screen all available brightness temperatures (Kelvin\*100) and navigation information at the cursor location.

ITM have ables assumed

VDVA S 0 0 1 DEV=P

This entry prints the spin budget, calibration, and raw data count

values at line and element 0,0.

#### Lists a single VAS retrieval.

**Formats** 

VL [keywords]

VL AVA [keywords]

**Parameter** 

AVA lists the data available for the specified MD file

**Keywords** 

ALL= includes edited soundings in the search

GRA= graphics frame number (default=current)

LAT= latitude of the retrieval to list (default=cursor center)

LON= longitude of the retrieval to list (default=cursor center)

MDF= MD file number with VAS data (default from MDU SET)

PTOP= lowest pressure level to list (default=100)

ROW= row number in the MD file; when AVA is used, ROW takes

two values to specify a range of MD file rows

(default=last row in the file)

SKEW= 1 plots a Skew T instead of listing data

> OL plots a Skew T with overlay (OLAY) option

SLOP= search radius in degrees latitude to find report (default=1.0)

Remarks

The latitude and longitude are determined by the cursor position if

you don't enter them as keywords.

**Examples** 

VL

This entry lists VAS retrieval data from a preset MD file for within 1.0 degree of the cursor location.

#### VL MDF=1101 ROW=2

This entry lists the data from MD file 1101, row 2, searching for the data closest to the cursor lat/lon position within 1 degree.

VL MDF=5703 ROW=1 LAT=40.5 LON=89.3 SLOP=2.2 This entry lists the data from MD file 5703, row 1, searching for the data closest to the specified lat/lon within 2.2 degrees.

#### VL SKEW=1

This entry plots the Skew T from the last available row in the current MD file, with the data closest to the cursor position (1 degree slope).

#### VL AVA MDF=5696

This entry lists the data availability for all rows in MD file 5696.

## **VPVA**

Sets the file pointer for VAS processing.

**Format** 

VPVA area

**Parameter** 

area > 0 sounder area file number for VAS processing (default=current)

0 lists the current pointer

-1 turns off the pointer and resets for TOVS processing

**Examples** 

**VPVA** 

This entry sets the pointer to the current VAS sounder area file number.

**VPVA 1305** 

This entry sets the pointer to sounder area 1305 for VAS processing.

## **VRVA**

Retrieves VAS temperature/moisture profiles and image products.

Format	VRVA [ke	eywords]					
Keywords	ARA=	wv li tot area numbers for product images, water vapor, lifted index and totals (default=0 0 0)					
	AUTO=	runs without image using the parameters from VASTEXT (default=0)					
	BEG=	line ele beginning of the retrieval area (default=upper- left corner of the image)					
	BIAS=	<ul><li>1 if nonzero, uses the bias vector in VASTEXT</li><li>99 uses the bias and gamma in the DARA statement</li></ul>					
	BOX=	square retrieval box size, in SFOV units (default=11)					
	END=	line ele end of the retrieval area in image coordinate units (default=VASTEXT values)					
	GAM=	value*100 to stabilize the matrix before inversion (default=100)					
	GAUSS=	99 overrides the Gaussian water vapor basis functions					
	GSS=	G gridded first guess (default) C climatology first guess					
	ICB=	1 file calculated brightness temperature from the first guess; file dwell sound; does not perform retrieval					
	IMCL=	image threshold for the cloud (default=6 K)					
	ITEM=	sets the temperature basis function numbers; the range is 1 to 11 (default=2 3 4 5 6)					
	IWAT=	sets the water vapor basis function numbers; the range is 1 to 11 (default=4 5 7)					
	SFC=	<ul><li>1 does not use surface analysis</li><li>0 uses surface analysis (default)</li></ul>					

SKIN= skin temperature change permitted (default=4.0 K)

SPC= line ele retrieval spacing, in SFOV units (default=BOX

BOX)

TERM= terminal number (default=current)

(Inthesiab) and non-bindesital

Remarks

This program generates the VAS retrievals from the appropriate setups, e.g., surface data, first guess surface T, TD, PSL, and first guess from GSVA.

See Also

See commands LOVA and SPVA for inspecting and setting the VASTEXT file pointers.

### **VRVF**

Generates VAS image products for the MSI mode.

**Format** 

VRVF [keywords]

**Keywords** 

ARA= wv li tot area numbers for water vapor, lifted index

and totals (default=0 0 0)

AUTO= runs without image using the parameters from

VASTEXT (default=0)

BEG= line ele beginning of the retrieval area

BIAS= if nonzero, uses the bias vector in VASTEXT (default=0)

BOX= square retrieval box size, in SFOV units (default=11)

END= line ele end of the retrieval area (default=VASTEXT)

FGRIDF= function grid file (no default)

IMCL= image threshold for the cloud used in the derived image

(default=8 K)

INVER= temperature inversion tolerance in the cloud filter

(default=-4)

NGRID= initial grid number (default=1)

SKIN= skin temperature change permitted (default=4.0 K)

SPC= line ele retrieval spacing, in SFOV units

(default=BOX BOX)

TERM= terminal number (default=local)

**Examples** 

**VRVF** 

This entry generates VAS image products using the current settings.

VRVF AUTO=1 AREA=4384 4385 FGRIDF=5923 NGRID=15 This entry retrieves the VAS profiler without an image using the parameters from VASTEXT. The original coefficients are from grid file 5923, starting with grid 15. It writes the precipitable water image into area 4384 and the lifted index into area 4385.

## **XRVA**

Edits values in the MD file at the cursor location.

**Formats** 

XRVA parm level XRVA [keywords]

**Parameters** 

parm

parameter name from the MD file schema

(default=entire record)

level

pressure level to delete, in mb (default=all levels)

Keywords

MDF=

MD file number (default=VASTEXT)

NRET=

retrieval number (default=0)

ROW=

MD row number (default=VASTEXT)

Remarks

Use keyword NRET to edit a single retrieval; otherwise, reports within the cursor are edited. Only reports with MOD=0 are deleted. To edit within the cursor, press the spacebar to delete, then type REND to terminate the execution. Cursor size may vary between deletions, i.e., after XRVA responds with GO.

Use of this command is restricted to VAS retrieval and surface MD files (schemas VRET and RSVC). Linkage is through MDU SET and the VASTEXT file.

Keywords MDF and ROW are required for McIDAS TOVS processing.

#### **Examples**

#### **XRVA**

This entry prompts a GO response on the text screen. Now, locate report(s) in the cursor and press the spacebar as many as 40 times to edit values; wait for a GO message between each spacebar press.

#### R END

This entry displays red Xs on the image where reports were deleted. The MD file is packed.

#### XRVA NRET=10

This entry deletes all data for report number 10.

**XRVA Z100** 

This entry deletes all values of Z100 within the cursor.

**XRVA T 500** 

This entry deletes all 500 mb temperature values within the cursor.

# **Chapter 11. Cloud Drift Winds**

Automatically selects targets for automatic motion vector tracking	
Automatically performs wind calculations from a target file	11-2
Calculates cloud heights	11-5
Deletes or lists AUTOWINDCO targets at the cursor location	11-6
Deletes or changes the wind vector in a motion vector file	11-7
Sets up data files for use with command MW	11-8
Reformats guess grids into an MD file	
Initializes the motion vector status file	11-11
Initializes an AUTOWINDCO status file	
Lists targets from the current data set target file	
Lists winds from a motion vector MD file	
Computes cloud drift winds and heights	
Plots targets from the current data set target file	11-17
Plots wind speed and direction from the VWIN MD file	11-18
Positions the cursor at the target location	11-20
Lists quality control statistics for winds	11-21
Plots displacement of the first guess wind vector	11-22
Manually selects targets for AUTOWINDCO	
Reformats guess wind grids into an MD file	
Contours streamlines from MD file schema VWIN	
Sets up data inputs for AUTOWINDCO	11-26
Lists and changes the status of motion vector keywords	
Checks the motion vector status	
Lists and changes the status of motion vector keywords	11-33
Lists motion vector numbers	11-35
	Calculates cloud heights  Deletes or lists AUTOWINDCO targets at the cursor location Deletes or changes the wind vector in a motion vector file Sets up data files for use with command MW  Reformats guess grids into an MD file Initializes the motion vector status file Initializes an AUTOWINDCO status file Lists targets from the current data set target file Lists winds from a motion vector MD file Computes cloud drift winds and heights Plots targets from the current data set target file Plots wind speed and direction from the VWIN MD file Positions the cursor at the target location Lists quality control statistics for winds Plots displacement of the first guess wind vector Manually selects targets for AUTOWINDCO Reformats guess wind grids into an MD file Contours streamlines from MD file schema VWIN Sets up data inputs for AUTOWINDCO Lists and changes the status of motion vector keywords Checks the motion vector status Lists and changes the status of motion vector keywords

Issued 4/93

### **AUTTAR**

Automatically selects targets for automatic motion vector tracking.

**Format** 

AUTTAR [keywords]

**Keywords** 

ADD= nonzero to add targets to the LW file (default=0)

ALL= YES gets every possible target

NO does not get every possible target (default)

AREA= area number for target selections (default is from WSAUTO)

COLOR= graphics color level to plot target locations if PLOT is not

zero (default=3)

ESIZ= element size of the target selector box (default is from

WSAUTO)

LSIZ= line size of the target selector box (default is from WSAUTO)

MAX= maximum acceptable brightness value (default is from

WSAUTO)

MIN= minimum acceptable brightness value (default is from

WSAUTO)

PLOT= nonzero to plot the target locations (default=1)

**Examples** 

**AUTTAR** 

This entry uses the current AUTOWINDCO parameter file for default values and initializes the target file before writing.

AUTTAR ALL=YES ADD=1

This entry finds all possible targets and adds them to the already existing target file. All other parameters are read from the current parameter file.

## **AUTWIN**

Automatically performs wind calculations from an AUTOWINDCO target file.

**Format** 

AUTWIN [keywords]

**Keywords** 

ALL= YES gets every possible target

NO does not get every possible target (default)

ARA1= first input area number

ARA2= second input area number

ARA3= third input area number

CH= cloud height assignment type (default=AFG)

ELAG= element lag size, in pixels (default=15)

ESIZ= element size of the target selector box (default=2)

GMD= first guess temperature MD file

GSS= first guess temperature profile (default=G)

HARA= area number for the height assignment

INIT= YES initializes the output wind MD file (default)

NO does not initialize the output wind MD file

INPT= YES inputs reference target selections

NO does not input reference target selections (default)

LIST= YES lists the output directory (default)

NO does not list the output directory

LLAG= line lag size (default=15)

LSIZ= line size of the target selector box (default=2)

MAX= maximum acceptable brightness value (default=24)

MF= output wind MD file

MIN= minimum acceptable brightness value (default=9) OUT= YES outputs vector information at the end of the job NO does not output vector information at the end of the job (default) PCB= pressure at cloud bottom PCT= pressure at cloud top, mb PLOT= YES plots wind vectors on the graphics NO does not plot wind vectors on the graphics (default) PMAX= maximum acceptable cloud pressure (default=5) PMIN= minimum acceptable cloud pressure (default=1) PW= wind level pressure QCU= quality control u criterion (default=5 mps) QCV= quality control v criterion (default=5 mps) ROW= destination row number from the output wind file (default=1) STAT= does not output vector statistics (default) outputs statistics to the text screen outputs statistics to the printer TC= cloud temperature, K TH= cloud thickness setting, mb WGMD= first guess wind MD file WM =CC tracks clouds using cross-correlation EN tracks clouds using Euclidian normal correlation  $\mathbf{LP}$ tracks clouds using correlation (default)  $\mathbf{SP}$ tracks clouds using single pixel ZCB= height at cloud bottom

See Also

ZCT=

Before starting the job, use command AUTTAR or SELTAR to select targets and command WSAUTO to check the automatic motion vector status file.

height at cloud top

#### **Examples**

#### AUTWIN

This entry calculates winds using the parameters in the current data set but does not plot wind vectors or print statistics.

AUTWIN OUT=YES STAT=2 PLOT=YES LLAG=20 ELAG=20 This entry calculates wind vectors, outputs vector information and statistics, and plots vectors on the graphics screen using lag values of 20.

# AUTWIN PLOT=YES ARA1=4064 ARA2=4065 ARA3=4066 HARA=4067

This entry calculates wind vectors and plots them on the graphics screen using areas 4064 through 4065 for input, and area 4067 for the height assignment. Values for all other parameters are read from the current data set parameter file.

# **CLOUDH**

Calculates cloud heights.

**Format** 

CLOUDH file

**Parameter** 

file VAS first guess MD file number (default=climatological data)

Remarks

Place the cursor over the cloud and type CLOUDH for estimated cloud heights. If the current frame contains a visible image, load the corresponding IR on the opposite frame; heights are estimated from IR temperatures or VAS guess MD file data.

See Also

If command MW is running, type a plus (+) to list cloud heights. In McIDAS-OS2, type: Alt +. In McIDAS-X, type a plus (+) and press Enter.

**Examples** 

CLOUDH

This entry calculates the cloud height inside the cursor using IR temperatures and climatological or forecast/analysis data.

CLOUDH 6512

This entry calculates cloud heights using the temperature profile data from MD file 6512.

## **DELTAR**

Deletes or lists AUTOWINDCO targets at the cursor location.

**Formats** 

DELTAR DEL [keyword]
DELTAR LIST [keyword]

**Parameters** 

DEL

deletes the selected target (default)

LIST

lists the selected target

Keyword

DSN=

data set name of the target file to use (default=current)

Remarks

This program allows you to manually delete AUTOWINDCO targets

from the current data set target file.

Example

**DELTAR** 

This entry deletes the target at the cursor location from the current

data set.

### DV

Deletes or changes the wind vector in a motion vector file.

**Formats** 

DV CHA [keywords]
DV DEL [keywords]

**Parameters** 

CHA changes the values assigned to a wind; you can use any keyword from schema VWIN (see the first example)

DEL deletes the wind from the wind file (default)

Keywords

COL= beg end column range to edit from the raw input

(default=1 to the maximum)

FLAG= quality control error flag number (see QCWIND); only

vectors with this error flag are deleted

LEV= high low pressure level range to delete (default=0 to 1050)

LSIZE= size of the plotted vector/flag, in pixels (default=8)

MDF= wind MD file number (default=current)

ROW= row number to edit

Remarks

Winds are selected by the cursor position. Move the cursor to the wind location and type a period (.) to delete or change the vectors within the cursor. Press two periods to exit DV.

**Examples** 

DV

This entry deletes the vectors within the cursor from the wind file.

DV CHA PW=500 TC=245 PCT=450 TH=100

This entry changes the wind level pressure to 500 mb, cloud top temperature to  $245^\circ$  K, cloud top pressure to 450 mb and thickness to 100 mb.

DV LEV=180 210

This entry deletes the winds within the pressure interval 180 to 210.

## **GESWIN**

Sets up data files for use with command MW.

**Format** 

GESWIN wfile gfile wgfile [keywords]

**Parameters** 

wfile

wind file to write generated winds into with command

MW (default=VASTEXT)

gfile

VGSS LFM guess MD file number for temperature

profile predictions (default=VASTEXT)

wgfile

WGSS LFM guess MD file number for wind predictions

(default=VASTEXT)

**Keywords** 

FCST=

0 uses the 0Z LFM forecast analysis for wind guess

12 uses the 12Z LFM forecast for wind guess (default)

GRIDF=

grid file number for the temperature profile

(default=VASTEXT)

**WGRIDF=** 

grid file number for the first guess wind profile

(no default)

Remarks

Use the macro GESWIN when you have VAS data available for cloud

drift winds. This program is optional for tracking clouds.

**Examples** 

**GESWIN** 

This entry deletes and regenerates the specified MD files, and writes wind vectors into an MD file using the VASTXT defaults and the 12Z

LFM forecast for the wind guess.

GESWIN 6512 WGRIDF=6500 FCST=0

This entry writes wind vectors into MD file 6512, using the VASTEXT defaults, grid file 6500 as the guess wind profile grid file, and the OZ

LFM forecast for wind guess.

## **GSVA**

Reformats guess grids into an MD file.

**Format** 

GSVA gfile grid file inc tgrid tinc [keywords]

**Parameters** 

gfile guess grid file number (no default)

grid first grid of the guess grids (default=1)

file MD file number of the output array (no default)

inc latitude and longitude increment, in degrees \* 10

(default=20)

tgrid first grid of the earlier set for time interpolation

(default=0)

tinc fractional time increment from the earlier time, e.g., for

interpolating between 12Z and 00Z respectively, 18Z

uses a value of .5 (default=0)

**Keywords** 

LAT= min max latitude range (default=VASTEXT)

LON= min max longitude range (default=VASTEXT)

SOURCE TOVS for McIDAS TOVS processing (default=VAS

or CIMSS TOVS, depending on User

Common)

TYPE= N northern hemisphere grid type (default)

S southern hemisphere grid type

Remarks

GSVA fills an MD file (schema VGSS) with guess temperatures and moisture profiles from grids of guess temperatures and moisture; these may be analyses, forecasts, etc. Grids in the grid file need not be in a specific order or form a complete set. If you perform time interpolation (e.g., between two forecast grids), check that earlier and later grids are both in the same grid file and not interleaved.

### **Examples**

#### GSVA 1250 X 2500

This entry fills MD file 2500 with the data from file 1250 beginning with grid 1.

### GSVA 1121 23 2610 LAT=25 40 LON=80 100

This entry establishes the guess profiles in MD file 2610 using the grids in file 1121 and beginning with grid 23. It generates profiles every degree from 25 to 40°N and 80 to 100°W. These bounds will change if the guess grid dimensions are less than 25 to 40°N and 80 to 100°W.

#### GSVA 1122 23 2611 X 1 .5

This entry establishes the guess profiles in MD file 2611 using time interpolation. It starts with grid 1 (e.g., valid at 1200 GMT) for the earlier set and grid 23 (e.g., valid at 00Z GMT) for the later set. Thus, MD file 2611 is valid at 1800 GMT.

### IW

Initializes the motion vector status file.

### Remarks

Use command WS to modify the values initialized by IW. If command MW is running, use a minus sign (-) to edit keyword values. In McIDAS-OS2, type: Alt -. In McIDAS-X, type a minus sign (-) and press Enter.

The table below lists the default values of the keywords.

Keyword	Default	Definition	
CH	Α	cloud height assignment type	
ELAG	5	element lag size	
GMD	OFF	first guess temperature MD file	
GSS	CLIM	first guess temperature profile	
LLAG	5	line lag size	
LSIZ	8	size of the wind vector	
OUT	ON	vector output information	
PCB	OFF	pressure cloud bottom	
PCT	OFF	pressure setting	
PW	OFF	pressure wind level	
QCU	5	quality control u criterion	
QCV	5	quality control v criterion	
TC	OFF	temperature setting	
TH	OFF	thickness setting	
TYPE	VIS	spectral band	
VG	FLAG	vector graphics plot	
WGMD	OFF	first guess wind MD file	
WM	LP	tracking metric	
ZCB	OFF	height at the bottom of the cloud	
ZCT	OFF	height at the top of the cloud	

## **IWAUTO**

Initializes an AUTOWINDCO status file.

**Formats** 

IWAUTO INIT dataset R
IWAUTO RESTORE dataset

**Parameters** 

INIT initializes the data set with the default values

RESTORE uses the specified data set for subsequent commands

R overwrites the existing data set for the INIT option

(default=no overwrite)

dataset LW file containing the AUTOWINDCO parameters;

must be 11 characters or less

Remarks

The data set name is stored in the string table as AUTOWIND; it is used to create the AUTOWINDCO parameter and target LW files. The parameter file name is the data set name with the number 1 appended to it. The target file name is the data set name with the number 2 appended to it. Thus, a data set named WINDS has its parameters stored in the LW file WINDS1 and its targets stored in the LW file WINDS2.

See Also

The IWAUTO command is the first command performed in the AUTOWINDCO program. The second is WSAUTO.

**Examples** 

IWAUTO INIT JETSTREAM

This entry sets the data set name to JETSTREAM and initializes the parameter file with the default values.

IWAUTO RESTORE WESTWIND

This entry makes the WESTWIND data set current. All subsequent AUTOWINDCO commands use this data set.

# **LISTAR**

Lists targets from the current data set target file.

**Format** 

LISTAR beg end [keyword]

**Parameters** 

beg beginning record to list (default=1)

end ending record to list (default=2000)

Keyword

DSN= name of the data set containing the targets (default=current)

Remarks

Targets are for AUTOWINDCO. If beg is less than or equal to zero,

only the number of targets is returned.

**Examples** 

LISTAR

This entry lists the targets in the current target file.

LISTAR 20 40 DSN=JETSTREAM

This entry lists records 20 through 40 of data set JETSTREAM.

### LISWIN

Lists winds from a motion vector MD file.

**Format** 

LISWIN CUR ALL [keywords]

**Parameters** 

CUR lists the contents within the cursor only

ALL

lists vector pairs, triples, etc.

Keywords

COL=

beg end column range to list

MDF=

wind MD file number (default=current)

ROW=

beg end row range to list

Remarks

You must exit command MW before using LISWIN. Use LISWIN to

list vectors from a motion vector MD file, schema VWIN.

**Examples** 

This entry lists all single vector pairs in the current MD file on the

text screen.

LISWIN CUR ALL ROW=6 12

This entry lists all vector pairs within the cursor that are in rows 6 to

12 of the current MD file.

### MW

### Computes cloud drift winds and heights.

_	_	_	 _	
_	О			т

MW [keywords]

**Keywords** 

CH= A assigns cloud heights automatically using

climatology (default)

AFG assigns cloud heights automatically using first

guess grids

M assigns cloud heights manually

ELAG= cursor element lag size, in pixels (default=5)

GMD= temperature profile from the NMC first guess retrieval MD

file, schema VGSS; use with CH=AFG for automatic cloud

tracking (default=VASTEXT)

GSS= CLIM climatology is first guess (default)

G temperature and/or wind profile is first guess

LLAG= cursor line lag size, in pixels (default=5)

LSIZE= size of the plotted flag/arrow, in pixels (default=8)

MDF= MD file number to write wind measurements into, schema

VWIN (default=MD file selected in the last MW execution)

OUT= ON lists wind computations on the text screen while

tracking clouds (default)

OFF does not list winds

PCB= pressure at cloud bottom (default=0)

PCT= pressure for cloud tops, mb

PW= wind pressure, mb (default=0)

QCU= u-component quality control criterion (default=5 mps)

QCV= v-component quality control criterion (default=5 mps)

TC= temperature for cloud tops, K

TH= thickness for clouds, mb

VG= ARRO arrows represent wind speed and direction

FLAG wind barbs represent wind speed and direction

(default)

WGMD = u and v wind profile from the NMC first guess wind MD

file, schema WGSS; use with CH=AFG for automatic cloud

tracking (default=VASTEXT)

WM= CC tracks clouds using cross-correlation

> EN tracks clouds using Euclidian normal correlation

LP tracks clouds using correlation (default)

SP tracks clouds using a single pixel

ZCB= height at cloud bottom (default=current status file)

ZCT= height at cloud top (default=current status file)

### Remarks

Keyword values for MW are remembered for the next cloud tracking session unless a file is newly initialized. Simultaneously click both mouse buttons to exit MW. Use the minus sign (-) to edit keyword values while running MW.

Select clouds for wind measurements by pressing the right mouse button. Pressing the button advances the image frame by one frame, changes the cursor size and color and performs a wind measurement. Pressing the left mouse button advances one image frame, having the same effect as Alt A. The combined features of the mouse enable you to track clouds with one hand.

Press the right mouse button to make wind measurements. Press the left mouse button to advance one image frame.

Random image loops cannot be used with MW; frames must be consecutive and ascending. Use command LB or LS to set the image loop for MW.

### **Example**

#### MW

This entry sets up the motion vector system for cloud tracking. Winds are written into the current MD file, schema VWIN.

## **PLTTAR**

Plots targets from the current data set target file.

**Format** 

PLTTAR color [keywords]

**Parameter** 

color graphics color level for plotting targets (default=1)

**Keywords** 

DSN=

name of the data set containing the targets

(default=current)

LAT=

min max

minimum and maximum latitudes

(default=all)

LON=

min max

minimum and maximum longitudes

(default=all)

Remarks

Targets are for AUTOWINDCO.

**Examples** 

PLTTAR

of feddingles (or the plat (defaulted to

This entry plots the current targets on a graphics frame in graphics

color level 1.

PLTTAR 5 LAT=37:00:00 40:00:00 LON=94:36:36 102:00:00

This entry plots the targets from the current data set using graphics

color level 5, bounded roughly by the borders of Kansas.

# **PLTWIN**

Plots wind speed and direction from the VWIN MD file.

Format	PLTWIN	file option	type [keywords]		
Parameters	file MD file number containing the winds (default=current)				
	option	ID P T W	plots the wind ID number or station plots pressure plots temperature plots winds (default)		
	type	ALL CO2 FG IR VIS WV09 WV10	plots all winds (default) plots carbon dioxide winds plots first guess winds plots IR winds plots visible winds plots band 9 water vapor winds plots band 10 water vapor winds		
Keywords	ALL= 1 plots all records or wind barbs (default for W option) 0 does not clutter records; does not work for W option (default for options P, T, ID)				
	COL=	beg end	column range for the plot (default=1 50)		
	COLOR=	-	color level of the plotted digit (default=1, 2, 3, respond to the default pressure level ranges for LEV)		
	FLAG=	plots winds with the appropriate QC flag (default=0)			
	LEV=	pressure level range for the plot (default 399 mb, 400 to 699 mb, and 700 to 1050 r which correspond to the three default cold for keyword COLOR)			
	LSIZE=	height of the plotted digit, in pixels (default=8)			
	PLOT=	<ul> <li>lists winds on the text screen (default)</li> <li>plots wind dddss on the graphics; see the Remar</li> <li>plots wind barbs on the graphics</li> <li>plots wind vectors on the graphics</li> </ul>			

PRO= SAT satellite projection (default)

MERC Mercator projection CONF conformal projection

ROW= beg end row number or range for the plot (default=1 20)

SIG= significant level wind MD file

SPEED= 1 plots winds in mps

2 plots winds in knots (default)

ST= state or station identifier for the ISFC or IRAB data

(default=ALL)

TIME= time for the ISFC or IRAB data (default=image time)

UNIT= C temperature in Celsius

F temperature in Fahrenheit (default)

K temperature in Kelvin

#### Remarks

PLTWIN plots wind speed, direction, pressure and temperature from motion vector files (schema VWIN) or any MD file containing winds. The output on the graphics is in the form dddss (direction and speed).

### **Examples**

#### **PLTWIN**

This entry plots all winds in the current MD file on the graphics frame. Wind speed is plotted in knots.

#### PLTWIN 6512 ROW=1 2 COL=1 10

This entry plots all winds in MD file 6512, rows 1 and 2, columns 1 to 10. Both pairs are plotted.

#### PLTWIN 6513 COLOR=5 LEV=300 800

This entry plots the winds in MD file 6513 between 300 and 800 mb, in graphics color level 5.

#### **PLTWIN 6514**

This entry lists all winds in MD file 6514.

## **POSTAR**

Positions the cursor at the target location.

**Format** 

POSTAR target

**Parameter** 

target

target number (default=1)

Remarks

Target numbers are from AUTOWINDCO target files.

Example

POSTAR

This entry positions the cursor at the first target of the current data

set.

# **QCWIND**

Lists quality control statistics for winds.

Format	QCWIN	D [keywords]		
Keywords	COL=	column range (default=from key CMAX)		
	DEV=	<ul> <li>C displays output on the text screen (default)</li> <li>N no output</li> <li>P displays output on the local printer</li> <li>S displays output on the system printer</li> </ul>		
	MDF=	destination MD file (default=current)		
	QCU=	u component maximum error, in m/s (default=5)		
	QCV=	v component maximum error, in m/s (default=5)		

row number (default=1)

### Remarks

This program compares each sequence of winds for user-selected quality specifications. Winds not meeting these criteria are flagged with one of the error codes below.

Error Code	Definition
10	u acceleration error
20	v acceleration error
30	u and v acceleration error
40	cloud height error
50	height and u acceleration error
60	height and v acceleration error
70	height and u, v acceleration error
100	overflow error
200	maximum correlation on boundary of image match surfaces
300	overflow and boundary error

### **Example**

### **QCWIND**

ROW=

This entry lists the quality control statistics for all winds in the current MD file using the defaults set with command IW.

## R

Plots displacement of the first guess wind vector.

#### Remarks

To plot the first guess wind displacement vector while command MW is running,

Type: R Press: Enter

or

Press: Alt R

The squares plotted on the graphics indicate the proper cursor position for generating a wind matching the guess wind. To force the manual measurement to match the guess wind, follow the squares with the cursor center and press the space bar while in single pixel. The first guess wind is stored in the wind MD file along with the measured wind.

## **SELTAR**

Manually selects targets for AUTOWINDCO.

**Format** 

SELTAR [keywords]

**Keywords** 

COLOR= graphics color level of the target indicator (default=1)

INIT=

nonzero to initialize the current target file (default=0)

Remarks

This program also allows you to augment targets selected with the

program AUTTAR.

using the first grid of the latest grid set. The VASTEXT file defaults

**Example** 

**SELTAR** 

This entry adds the current cursor location to the current target file.

## **WGVA**

Reformats guess wind grids into an MD file.

#### **Format**

WGVA gfile grid file nw se inc tgrid tinc

#### **Parameters**

gfile u and v wind profile guess grid file number

grid first grid of the latest set of guess grids (default=1)

file u and v wind profile MD file number

nw latitude and longitude of the northwest corner of the

MD file; the range is 0 to 360 (default=VASTEXT)

se latitude and longitude of the southeast corner of the

MD file; the range is 0 to 360 (default=VASTEXT)

inc latitude and longitude increment, in degrees \* 10

(default=20)

tgrid first grid of earlier guess grids for time interpolation

tinc fractional time increment from earlier time, e.g., for

interpolating between 12 and 0Z respectively, 18Z

uses a value of .5

#### Remarks

Parameters gfile, grid and file are used by macro GESWIN.

#### See Also

Use command GSVA to reformat temperature profiles.

### **Examples**

#### **WGVA**

This entry reformats the guess wind grids from the current grid file using the first grid of the latest grid set. The VASTEXT file defaults are used for latitude and longitude which increment by 10 degrees; the time increment is .5.

### WGVA 9410 6 4400

This entry reformats guess wind grids from grid file 9410, starting with grid 6, into MD file 4400.

### WINC

### Contours streamlines from MD file schema VWIN.

**Format** 

WINC tpress bpress [keywords]

**Parameters** 

tpress top at

top atmospheric pressure, mb (default=0)

bpress.

bottom atmospheric pressure, mb (default=1050)

Keywords

COLOR= graphics color level (default=1)

FLAG= number of a quality control flag, e.g., 100, 200, 300, etc.

(default=0)

MAP=

MID Midwestern USA

NA North America

SAT satellite projection (default)

USA United States
Post Office abbreviation

TIME=

vector time, HH:MM:SS (default=current)

Remark

To point to an MD file, use: MDU SET file.

**Examples** 

WINC

This entry contours all nonflagged winds from the VWIN MD file over

the satellite image in graphics color level 1.

WINC 100 300 COLOR=2 MAP=USA

This entry contours the streamlines of 100 to 300 mb winds in graphics color level 2, over the USA in a Mercator projection.

# **WINDS**

# Sets up data inputs for AUTOWINDCO.

Format	WINDS a	rea1 area2 area3 harea [keywords]				
Parameters	area1	first input area (no default)				
	area2	second input area (no default)				
	area3	third input area (no default)				
	harea	input area for the height assignment (default=area1)				
Keywords	DARA=	a1 a2 a3 destination subareas for area1, area2, area3, harea (default=WSAUTO file)				
	FCST=	0 uses the 0Z analysis for the forecast 12 uses the 12Z analysis for the forecast (default)				
	GMDF=	= VGSS LFM guess MD file number (default=WSAUTO file)				
	GRIDF=	grid file for the temperature profile (default=VASTEXT)				
	INIT=	YES YES deletes and generates a new wind MD file and initializes the guess MD files (default) YES NO deletes and generates a new wind MD file NO YES initializes the guess MD files				
		NO NO does not delete or generate a new wind  MD file or initialize the guess MD files				
	LLNW=	lat lon latitude and longitude of the northwest corner of of the image (default=VASTEXT)				
	LLSE=	lat lon latitude and longitude of the southeast corner of the image (default=VASTEXT)				
	MDF=	wind MD file number (default=WSAUTO file)				
	MOVE=	YES moves source areas to destination areas (default) NO does not move source areas to destination areas				
	OVER=	nonzero to write into TERMFILE (default=0)				
	PART=	part of the image to begin with (default=1)				

ROW= destination row for the wind input (default=WSAUTO

file)

WGMDF= WGSS LFM guess MD file number (default=WSAUTO

file)

WGRIDF= grid file for the first guess wind profile (no default)

Remarks

This program uses a combination of command line parameters and the current data set and VASTEXT parameters to set up areas and guess MD files for an AUTOWINDCO run. It is especially useful when using large areas or the background AUTOWINDCO method.

Example

WINDS 4816 4817 4818 4816 ROW=2 INIT=NO YES
This entry copies areas 4816 through 4818 into the default
destination subareas, and sets up new guess MD files and WSAUTO
variables to put new wind calculations into an existing wind MD file
starting with row 2.

### WS

Lists and changes the status of motion vector keywords.

**Formats** 

WS CHA [keywords] WS LIST [keywords]

**Parameters** 

CHA

changes the keyword values

LIST

lists the motion vector status (default)

**Keywords** 

CH=

assigns cloud heights automatically using

climatology (default)

assigns cloud heights automatically using first AFG

guess grids

 $\mathbf{M}$ 

assigns cloud heights manually

ELAG=

cursor element lag size, in pixels (default=5)

GMD=

temperature profile from the NMC first guess retrieval MD

file, schema VGSS; use with CH=AFG for automatic cloud

tracking (default=VASTEXT)

GSS=

CLIM uses climatology as first guess (default)

uses temperature and/or wind profile as first guess

LLAG=

cursor line lag size, in pixels (default=5)

LSIZE=

size of the plotted flag/arrow, in pixels (default=8)

MDF=

MD file number to write wind measurements into, schema

VWIN (default=MD file selected in the last MW execution)

OUT=

ON

lists wind computations on the text screen while

tracking clouds (default)

does not list winds OFF

PCT=

pressure for cloud tops, mb

QCU=

u-component quality control criterion (default=5 mps)

QCV=

v-component quality control criterion (default=5 mps)

TC=

temperature for cloud tops, K

TH= thickness for clouds, mb

VG= ARRO arrows represent wind speed and direction

FLAG wind barbs represent wind speed and direction

(default)

WGMD= u and v wind profile from the NMC first guess wind MD

file, schema WGSS; use with CH=AFG for automatic cloud

tracking (default=VASTEXT)

WM= CC tracks clouds using cross-correlation

EN tracks clouds using Euclidian normal correlation

LP tracks clouds using correlation (default)

SP tracks clouds using single pixel

Remarks

Do not use WS while command MW is running; your keyword values will not change. Use the minus (-) command.

See Also

Command IW initializes the motion vector status file.

**Examples** 

WS

This entry lists the wind motion vector system status.

WS CHA CH=M TH=180 PCT=500 TC=255

This entry changes the status to manual cloud tracking, thickness to 180 mb, cloud pressure to 500 mb and cloud temperature to 255K.

## **WSAUTO**

Checks the motion vector status.

**Formats** 

WSAUTO CHA [keywords] WSAUTO LIST [keywords]

**Parameters** 

CHA

changes the keyword values

LIST

lists the motion vector status (default)

Keywords

ALL=

YES

gets every possible target

does not get every possible target (default) NO

ARA1=

first input area number

ARA2=

second input area number

ARA3=

third input area number

CH=

assigns cloud heights automatically using A

climatology (default)

assigns cloud heights automatically using first AFG

guess grids

 $\mathbf{M}$ 

assigns cloud heights manually

ELAG=

element lag size, in pixels (default=15)

ESIZ=

element size of the target selector box (default=15)

GMD=

first guess temperature MD file

GSS=

first guess temperature profile (default)

CLIM climatology

HARA=

input area number for the height assignment

INIT=

initializes the output wind MD file (default) YES

NO does not initialize

INPT=

YES inputs reference target selections

NO

does not reference target selections (default)

LIST=

YES NO

lists the output directory (default)

does not list the output directory

LLAG= line lag size (default=15)

LSIZ= line size of the target selector box (default=20)

MAX= maximum acceptable brightness value (default=240)

MDF= output wind MD file

MIN= minimum acceptable brightness value (default=90)

OUT= YES outputs vector information at the end of the job

NO does not initialize the output wind MD file

(default)

PCB= pressure at cloud bottom

PCT= pressure at cloud top, mb

PMAX= maximum acceptable cloud pressure (default=500)

PMIN= minimum acceptable cloud pressure (default=100)

PW= wind level pressure

QCU= quality control u criterion (default=5 mps)

QCV= quality control v criterion (default=5 mps)

ROW= destination row number from the output wind file

(default=1)

TC= temperature for cloud tops, K

TH= cloud thickness setting, mb

WGMD= first guess wind MD file

WM= CC tracks clouds using cross-correlation

EN tracks clouds using Euclidian normal correlation

LP tracks clouds using correlation (default)

SP tracks clouds using single pixel

ZCB= height at cloud bottom

**ZCT=** height at cloud top

#### Remarks

All defaults are the present values from the motion vector status file. To see these values,

Type: WSAUTO Press: Enter

The output will halt halfway through the list. To continue, press the space bar. To suppress the halt, use STOP=1.

When you finish this command function, you can run the target selector programs (AUTTAR, SELTAR) and utility programs (DELTAR, LISTAR, PLTTAR, POSTAR), and run the wind generation program (AUTWIN) as a background job. Each command is documented in this chapter.

### **Examples**

### **WSAUTO**

This entry lists the current parameters if the AUTOWINDCO system is initialized, or the system defaults if AUTOWINDCO is not initialized.

WSAUTO CHA ARA1=2929 ARA2=2930 ARA3=2931 HARA=2929 MDF=1301

This entry changes the default parameters for the current data set to the specified values. **Format** 

# - (Minus)

[keywords]

Lists and changes the status of motion vector keywords while command MW is running.

Keywords	СН=	A	assigns cloud heights automatically using climatology (default)
		AFG	assigns cloud heights automatically using first
			guess grids
		M	assigns cloud heights manually
	ELAG=	cursor el	ement lag size, in pixels (default=5)
	GMD=	MD file,	ture profile from the NMC first guess retrieval schema VGSS; use with CH=AFG for automatic acking (default=VASTEXT)
	GSS=	CLIM	uses climatology as the first guess (default)
		G	uses temperature and/or wind profile as the

LLAG= cursor line lag size, in pixels (default=5)

first guess

LSIZE= size of the plotted flag/arrow, in pixels (default=8)

MDF= MD file number to write wind measurements into, schema VWIN (default=MD file selected in the last MW execution)

OUT= ON lists wind computations on the text screen while tracking clouds (default)
OFF does not list winds

PCT= pressure for cloud tops, mb

QCU= u-component quality control criterion (default=5 mps)

QCV= v-component quality control criterion (default=5 mps)

TC= temperature for cloud tops, K

TH= thickness for clouds, mb

VG= ARRO arrows represent wind speed and direction

FLAG wind barbs represent wind speed and direction

(default)

WGMD= u and v wind profile from the NMC first guess wind MD file,

schema WGSS; use with CH=AFG for automatic cloud

tracking (default=VASTEXT)

WM= CC tracks clouds using cross-correlation

EN tracks clouds using Euclidian normal correlation

LP tracks clouds using correlation (default)

SP tracks clouds using a single pixel

#### Remarks

Use the minus sign to modify motion vector system keywords while command MW is running.

<u>DO NOT</u> use command WS to change keywords! The keywords are those listed by WS.

### **Examples**

This entry lists the current status of the motion vector system. Command MW must be running; otherwise use command WS. If entering this command in McIDAS-OS2, use Alt -. In McIDAS-X, type the minus sign (-) and press Enter.

#### - CH=M TH=300 TC=285 PW=850

This entry changes the cloud tracking to manual height assignments, the thickness to 300 ms, the temperature to 285°K and the pressure level to 850 mb.

### - WM=SP TH=800 PCT=850

This entry changes the cloud tracking mode to single pixel, the thickness to 800 mb and the cloud top pressure to 850 mb.

# ; (Semicolon)

Lists motion vector numbers.

### Remarks

When you set up the motion vector system with command MW, press the semicolon (;) key to list the row and column number of the current wind measurement. ; (Semicolon)

Issued 4/93

# **Chapter 12. Command Schedulers**

ESKE	Enters an event in the event scheduler	1
ESKL	Lists the event scheduler entries	4
ESKU	Event scheduler utility functions	6
LRAD	Lists Kavouras radar sites	7
RSKL	Lists the Kavouras radar schedule entries	8
SETF	Modifies event scheduler flags	9
SKE	Enters a command in the system time scheduler	10
SKL	Lists time scheduler entries	12
SKU	Time scheduler utility	14

Revised 6/95

Revised 6/95

## **ESKE**

Enters an event in the event scheduler.

F	O	r	n	n	a	t

ESKE [keywords] "expression "command

#### **Parameters**

"expression a

an event expression consisting of operators, event flag numbers, integer constants, and hexadecimal constants from those listed below.

Boolean: ~ (NOT), & (AND), V (OR), | (XOR)

Relational: >, <, =,  $\geq$ ,  $\leq$ , <>

Arithmetic: +, -

Flag numbers are preceded by F, hexadecimal constants by Z. When the expression takes the value of one (i.e., when it is true) the "command is run.

Expressions may be parenthesized. Otherwise, relational operators get highest priority, arithmetic second highest, Boolean lowest.

Example: "F22=1&(F23=5VF23=10)&F813=1

"command

the McIDAS command to run when the expression takes

the value 1

### Keywords

END=

day time ending day (YYDDD) and time (HH:MM:SS)

to run the entry (default=99365 23:59:59)

ID=

4-digit number to identify the command in the event scheduler (default=system assigned 3-digit number)

PROJ=

project number charged to run the command

(default=current)

START=

day time starting day (YYDDD) and time (HH:MM:SS)

the schedule entry is activated (default=current day, 0 UTC)

TERM=

terminal number to run the command on

(default=current)

#### Remarks

ESKE allows you to schedule commands based on the occurrence of events that you define. Defining an event consists of creating an expression of event flags, values of the flags and operators. When the expression is evaluated as true (i.e., 1) the associated command is run.

Event flags are flags with values indicating the current status of an event. For example, all satellite image data on McIDAS is input via ingestors which reformat real-time or recorded data so the system can access it readily. Each ingestor accepts input from one source at a time (e.g., GOES). Associated with each ingestor is an image spool that contains messages regarding the current state of the image being ingested. Most of the event flags set by the system are for the ingestor image spools. They contain information such as the satellite ID, current scan line and image nominal time and date.

There are 6999 event flags available for use on McIDAS. Flags 1 through 799 have integer values; flags 800 through 6999 have Boolean values.

Event flags currently in use are listed in edit member DNEFLAGS. This list includes flags set by system software and known user set flags. Contact the operators to determine which flag numbers are available.

Event flags can also be included in the command. Parameter substitution is done when the command is run. Any string of the form Fn in the command field is replaced by the current value of flag number n. This makes it possible to pass parameters whose values cannot be known in advance.

#### Caution!

Do not use SETF with other commands (separated by semicolons) in the "command parameter.

#### See Also

See the online text files DNESKED, DNEFLAGS and DNIMASPL for more information about the event scheduler.

#### **Examples**

## TE EXP "F22=1&(F27>550VF23=5)&(F40≥140000&F40≤232900) &F5000=0

This entry defines the values for the string EXP.

#### ESKE #EXP "EG 1;SF 1;DF \$F29 1 EC 36 90;MAP

This entry loads a visible image every time a new image reaches scan line 550 or a frame end code is received on ingestor spool 1 during daylight hours (between 1400 UTC and 2329 UTC).

#### ESKE #EXP "SETF F5000 1

This entry sets flag 5000 to 1 at the same time the DF command is run to prevent the command from repeatedly running.

#### ESKE "F22=1&F23=1 "SETF F5000 0

This entry sets flag 5000 back to 0 every time a new frame starts.

Revised 6/95 12-3

## **ESKL**

Lists the event scheduler entries.

Format	ESKL bio	d eid [keywo	ords]
Parameters	bid	0 0	event scheduler entry ID number to list; is 1 to 9999 (default=lists all entries)
	eid	ending ID	number to list (default=bid)
Keywords	PROJ=	min max	project number or range of numbers in the scheduler to list (default=1000 to 9999)
	SORT=	TERM	lists entries by ascending terminal numbers (default)
		TIME	lists entries by ascending start times
	TERM=	min max	terminal number or range of terminal numbers to list the schedule of (default=current)

#### Remarks

The output format is defined below.

Field	Definition
T#	terminal number
ID	command identification number
XS	S suspends the scheduled command;
	X disables your terminal's schedule
START	day (YYDDD) and time (HHMMSS) to
	start the schedule entry
END	day and time to end the schedule entry
NAME	user who created the entry
PROJ	project number
EXPRESSION TEXT	expression to evaluate
COMMAND TEXT	command to run

#### **Examples**

#### **ESKL**

This entry lists the current terminal's event scheduler entries.

#### ESKL 2000 2020 SORT=TIME

This entry lists the event scheduler entries between 2000 and 2020 on the current terminal in the order of ascending times.

#### ESKL TERM=66

This entry lists all event scheduler entries for terminal 66.

## **ESKU**

#### Event scheduler utility functions.

Formats ESKU CHA bid eid [keywords]

ESKU DEL bid eid [keywords]

ESKU REL bid eid [keywords]

ESKU SUS bid eid [keywords]

Parameters CHA changes the keyword TERM, PROJ or NAME field

DEL deletes an entry

REL releases an entry

SUS suspends an entry

bid beginning event scheduler entry ID number

eid ending ID number (default=bid)

Keywords NAME= old new changes the old user name to the new user

name (default=current)

**PROJ**= old new replaces the old project number with the new

project number

**TERM**= terminal number on which to run the entry

(default=current)

Examples ESKU SUS 1001 1009 TERM=0

This entry suspends schedule entries with IDs 1001 through 1009 at the

operator's terminal.

ESKU CHA 1001 1009 PROJ=7000 5630

This entry changes the schedule entries with IDs 1001 through 1009 that run at the user's terminal and under project 7000 to run under project

5630.

ESKU REL 1001 1009

This entry releases scheduled entries 1001 through 1009.

## **LRAD**

#### Lists Kavouras radar sites.

Formats LRAD station1...stationn [keywords]

LRAD state

LRAD [keywords]

Parameters station 3- or 4-letter radar station IDs

state 2-letter state Post Office abbreviation

Keywords LAT= min max minimum and maximum latitude range

LON= min max minimum and maximum longitude range

Example LRAD FL

This entry lists the Kavouras radar sites for Florida.

## **RSKL**

Lists the Kavouras radar schedule entries.

Format RSK

RSKL bentry eentry [keywords]

**Parameters** 

beginning entry number (default=lists the entire schedule

directory)

eentry

bentry

ending entry number (default=bentry)

Keywords

DAY=

day of the entry, YYDDD

FORM=

ALL generates an expanded listing

ID=

station ID to list

TIME=

time of the entry, HH:MM:SS

**Examples** 

RSKL

This entry lists all scheduled Kavouras entries.

RSKL 2 6

This entry lists the Kavouras entries from numbers 2 through 6.

## **SETF**

Modifies event scheduler flags.

**Format** 

SETF flag value

**Parameters** 

flag event flag number preceded by the letter F

value event flag value; can be an integer or a flag number preceded

by the letter F

Remarks

SETF is often used to synchronize a command. By setting the value of user event flags, you can control when commands run in the event scheduler. See the example for command ESKE.

If a SETF command appears as the *command* in an ESKE command, it is handled specially by the scheduler; the scheduler sets the flag itself without starting a SETF command. Because of this special handling do NOT include other commands (separated by semicolons) with a SETF command in an ESKE *command* field.

To display the current value of a flag, use the command below, replacing n with the flag number.

Type: GETF Fn

**Examples** 

**SETF F10 123** 

This entry assigns the value 123 to event flag number 10.

SETF F10 F12

This entry assigns the current value of event flag 12 to flag 10.

## SKE

#### Enters a command in the system time scheduler.

**Format** 

SKE day time repeat interval [keywords] "command

**Parameters** 

day to start the command, YYDDD

time to start the command, HH:MM:SS; colons are

mandatory (default=0 UTC)

repeat number of times to run the command; if you enter 999999,

the word MANY replaces it in the header (default=1)

interval time interval between commands, DDDHH:MM:SS;

colons are mandatory; for 1 day, enter 24:00:00 or

100:00:00 (default=1 hour)

"command command to run; it can be up to 160 characters

(including spaces) minus the preceding positional

parameters; the double quote is mandatory

**Keywords** 

ID= 4-digit number to identify the command in the scheduler

(default=system assigned, 3-digit number)

PROJ= project number charged to run the command

(default=logged on project number)

TERM= number of the terminal on which to run the command

(default=current)

TOL= late tolerance, HH:MM:SS; if McIDAS-MVS is down or

too busy for the command to run, the late tolerance

determines how much time can pass before the

command is skipped; if 10 to 24 hours are specified, the word BIG is entered in the header; three seconds

is the minimum acceptable time (default=1 hour)

Remarks

The keyword ID must be a 4-digit number (or omitted). Use it to refer

to a schedule entry for listing, suspension and deletion.

To enter a #command from the string table, enter: "####command.

If you schedule TV loads for a McIDAS-OS2 or McIDAS-X workstation, use the workstation auto logon option to ensure the workstation is logged on.

The maximum number of McIDAS-MVS scheduler entries that can be scheduled is 800.

The maximum number of local scheduler entries that can be scheduled per workstation is 100.

See Also

List DNSKED for further information.

Type: SHOWME DNSKED ALL DEV=P

**Examples** 

SKE 94340 13:30: 2 24:00: ID=3003 TERM=10 "SS This entry runs command SS at 1330 UTC on each of two consecutive days (94340, 94341) on terminal 10. The assigned ID for reference is 3003.

SKE 90100 00:00:01 999999 PROJ=7777 "DF 101 1 EC MSN This entry runs the DF command every day once an hour (999999 is listed as MANY by SKL), beginning with day 90100 at one second after 0 UTC. Project 7777 is charged for the computer time.

SKE 93071 "DF 101 1 EC MSN

This entry runs the DF command on day 93071 starting at 0 UTC with a 1-hour interval.

## SKL

### Lists time scheduler entries.

Format	SKL bid eid	[keywords]	"matchstring
Parameters	bid		ID number to list; the range is 1 to 9999 ists all entries)
	eid	ending ID	number to list (default=bid)
	"matchstring		the entries containing this string; ters maximum (default=no match performed)
Keywords	FORM=	ALL	uses as many lines of output as needed to list the entire command
	PROJ=	min max	project number or range of numbers in the scheduler to list (default=1000 9999)
	SORT=	ID PROJ RAW	sorts entries by ID number sorts entries by project number lists in the order of occurrence in the schedule (unsorted)
		TERM	lists entries by ascending terminal numbers (default)
		TIME	lists entries by ascending start times
	TERM=	min max	terminal number or range of numbers of the schedule to list (default=current)
Remarks	The maximum	number of	McIDAS-MVS scheduler entries that can be

scheduled is 800.

The maximum number of local scheduler entries that can be scheduled per workstation is 100.

The output format is defined in the table below.

Field	Definition
T#	terminal number
ID	command identification number
XS	S suspends the scheduled command;
	X disables your terminal's schedule
NEXT EXECUTN	next day (YYDDD) and time (HHMMSS)
	to run the command
#REM	number of remaining commands; if SKE
	repetitions is a 6-digit number, this will say
	MANY
INTERVAL	day and time interval between commands;
	the format is DDHH:MM:SS, entered by
	SKE interval where interval is 1 hour;
	if interval is 24, this output is listed as
	1000000 (1 day)
TOL	late tolerance time, HH:MM:SS; any entry
	over 9 hours is listed as BIG
NAME	user who created the entry
PROJ	project number
COMMAND TEXT	command to run

#### **Examples**

#### SKL

This entry lists all time scheduler entries for the current terminal.

#### SKL 420 430 PROJ=7000

This entry lists the scheduled commands on the current terminal for project 7000 between 420 and 430.

#### SKL TERM=70

This entry lists all schedule entries for terminal 70.

## SKU

option

Time scheduler utility.

**Formats** 

SKU option bid eid [keywords]

SKU CHA bid eid [keywords] "command

SKU DOIT bid eid

**Parameters** 

DEL deletes an entry from the schedule

REL releases an entry so the command runs at the

next scheduled time

SUS suspends an entry so the command will not run;

this does not delete the entry from the scheduler

CHA changes an entry; depends on the keyword used

**DOIT** runs a schedule entry without decrementing the counters

bid beginning time scheduler entry ID number

eid ending ID number (default=bid)

"command new command or text to replace the current command

**Keywords** 

NAME= old new changes the old user ID to the new user ID

**PROJ**= old new replaces the old project number with the

new project number

TERM= terminal number containing the schedule

(default=current)

Remarks

To change a schedule entry, you must be logged on to the project number listed in the entry.

Use the DOIT option to test schedule entries.

The maximum number of McIDAS-MVS scheduler entries that can be scheduled is 800.

The maximum number of local scheduler entries that can be scheduled per workstation is 100.

#### **Examples**

#### SKU SUS 1001 1009 TERM=10

This entry suspends schedule entries with IDs 1001 to 1009 at terminal number 10.

#### SKU CHA 1001 1009 PROJ=7000 5630

This entry changes schedule entries with IDs 1001 to 1009, running at your terminal under project 7000, to run under project 5630.

#### SKU DOIT 239

This entry runs the command scheduled in ID number 239. It neither changes the run time nor decreases the counter.

Revised 6/95

12-16

## **Chapter 13. System Navigation**

ND	Deletes data from a navigation file 1	<b>13-1</b>
NK	Creates a navigation codicil from the system navigation file 1	13-2
NKAREA	Assigns a navigation codicil to areas 1	13-4
NL	Lists the data in a navigation file	13-5
NLC	Lists navigation parameters from a navigation codicil	13-6
NT	Calculates a navigation transformation from navigation files 1	13-7
NTC	Calculates a transformation from a navigation codicil	
NVU	Navigation file utility	
NXCOPY	Copies a codicil from one type to another	

Issued 4/93

## ND

Deletes data from a navigation file.

#### **Format**

ND option ssyyddd time code [keyword]

#### **Parameters**

option	ALL	deletes all day and image dependent data
		(default)
	BLEG	deletes all B, L, E and G data
	В	deletes betas
	$\mathbf{E}$	deletes earth edge
	$\mathbf{G}$	deletes gamma
	Lieantra	deletes landmark

ssyyddd

sensor source, year and Julian day of the navigation, SSYYDDD or SSYY/MM/DD (default=ALL)

time

time of the data (default=ALL)

code

landmark code for deleting landmarks (default=ALL)

- 1 deletes the first beta
- 2 deletes the second beta

#### Keyword

NAVF=

navigation file to delete data from (default=current)

#### Remarks

You cannot specify NAVF=1, as file 1 is the system navigation file and

cannot be altered.

Use this command with GOES and POES data only.

#### See Also

Use NVU SET to point to a different navigation file.

#### **Examples**

#### ND ALL

This entry deletes all data from the current navigation file.

#### ND B 2892265 12:30 1 NAVF=4

This entry deletes the first beta for sensor source 28, day 92265 at 1230 UTC from navigation file 4.

#### ND ALL 1892100

This entry deletes all navigation from the current navigation file for sensor source 18, day 92100.

## NK

Creates a navigation codicil from the system navigation file.

**Format** 

NK ssyyddd time type [keywords]

**Parameters** 

ssyyddd sensor source, year and Julian day, SSYYDDD

time

image time, HH:MM:SS; do not specify with keyword

SENS

type

T creates a ticketed navigation codicil (default)

M creates a master navigation codicil

**Keywords** 

AREA=

area number to assign to the codicil; you must specify

this number when using keyword SENS

NAVF=

navigation file number

SENS=

AVHRR POES AVHRR sensor data (default)

ERB POES ERB sensor data
HIRS POES HIRS sensor data
MSU POES MSU sensor data

**UPDATE**=

bday btime eday etime tinc

creates master navigation codicils only; do not specify

with keyword SENS

bday beginning day, SSYYDDD (default=original SSYYDDD)

btime beginning time, HH:MM:SS (no default)

eday ending day, SSYYDDD

etime ending time, HH:MM:SS (no default)

tinc time increment (default=:30)

Remarks

The current system navigation file, set by command NVU, is the source file. If type T is specified, the string NAVNUM is filled with the ticket value assigned to the navigation codicil and placed in your string table. POES navigation parameters are also read from the current system navigation file. Keyword AREA is mandatory for POES, but the image time and keyword UPDATE are not used.

Use this command with GOES and POES data only.

#### **Examples**

#### NK 3092255 11:30

This entry generates a ticketed navigation codicil for sensor source 30, day 92255 at 11:30 UTC. The data is from the current system navigation file.

#### NK 6090030 AREA=2500 SENS=MSU

This entry generates a ticketed navigation codicil for area 2500 containing MSU data, sensor source 60, day 90030. The data is from the current system navigation file.

Revised 11/93 13-3

## **NKAREA**

Assigns a navigation codicil to areas.

Format NKAREA barea earea [keyword]

Parameters barea beginning area number (no default)

earea ending area number (default=barea)

Keyword MAX= maximum number of areas (default=16)

Remarks You cannot specify the navigation file. Use NVU SET to point to the

file. Areas that do not exist in sequence are skipped.

Keyword MAX is a safety feature to prevent unintentional overwriting of

navigation codicils.

Use this command with GOES and POES data only.

Examples NKAREA 5000

This entry files a navigation codicil for area 5000.

NKAREA 6530 6540

This entry files navigation codicils for areas 6530 through 6540.

### NL

#### Lists the data in a navigation file.

#### **Format**

NL option ssyyddd eptime [keywords]

#### **Parameters**

option ALL lists day and image dependent data (default)

B lists betas

DAY lists orbital information

E lists earth edgeG lists gammas

G lists gammas
L lists landmarks

ssyyddd

sensor source number, year and Julian day to list,

SSYYDDD

eptime

epoch time to list, HH:MM:SS (default=0)

#### **Keywords**

NAVF= navigation file number (default=current)

TIME= beg end range of times to list, HH:MM:SS (default=0)

#### Remarks

Use this command with GOES and POES data only.

#### **Examples**

#### NL ALL

This entry lists all the data in the current navigation file.

#### NL DAY 3290200

This entry lists the orbital information in the current navigation file for sensor source 32, day 90200.

#### NL B 3290200 TIME=12 15

This entry lists the betas in the current navigation file from 12 UTC to 15 UTC for sensor source 32, day 90200.

## **NLC**

Lists navigation parameters from a navigation codicil.

**Formats** 

NLC ssyyddd time CHEB

NLC ticket 0

**Parameters** 

ssyyddd sensor source, year and Julian day, SSYYDDD

time

time, HH:MM:SS

**CHEB** 

lists Chebyshev codicils

ticket 0

ticket number of the codicil parameters to list; the zero is

mandatory

Remarks

Use this command with GOES and POES data only.

To list codicil ticket numbers, enter: LA area FORM=ALL. The

number is listed after PRIMARY=.

**Examples** 

NLC 2892365 12:01

This entry lists the navigation parameters for sensor source 28, day

92365 at 1201 UTC.

NLC 62543 0

This entry lists the navigation parameters for ticketed codicil number

62543.

## NT

Calculates a navigation transformation from the system navigation files.

**Formats** 

NT ANG ssyyddd time lat lon [keywords]

NT ES ssyyddd time lat lon [keywords]

NT ROT ssyyddd time

NT SE ssyyddd time line ele [keywords]

NT SP ssyyddd time

**Parameters** 

ANG zenith angle transformation

ES earth to satellite transformation

ROT satellite rotation transformation

SE satellite to earth transformation

SP sub-satellite position transformation

ssyyddd sensor source, year and Julian day, SSYYDDD

time time, HH:MM:SS

lat latitude

lon longitude

line coordinate

ele element coordinate

Keywords

N= n1 n2 n1 is number of calculations between lines or

latitudes; n2 is the number of calculations

between elements or longitudes

THRU= elat elon calculates the conversion through this ending

latitude and longitude; use with parameters

ANG and ES

eline eele calculates the conversion through this ending line

and element; use with parameter SE

#### Remarks

Command NT uses the system navigation file. The keywords allow you to make transformations over a whole grid of points rather than just one.

The beginning points of the range are given by positional parameters *lat*, *lon*, *line* and *ele*. The ending points of the range are specified with keyword THRU. The number of calculations is specified with keyword N.

Use this command with GOES data only.

#### Example

#### NT ES 3093006 0 45 -89 THRU=50 99 N=6 3

This entry calculates earth to satellite transformations using the system navigation file data from sensor source 30 for day 93006 at 0 UTC. It makes  $18 (3 \times 6)$  transformations: 6 between latitudes 45 and 50 (every degree) and 3 between longitudes 89 and 99 (every 5 degrees).

## **NTC**

Calculates a transformation from a navigation codicil.

#### **Formats**

NTC ES primary secondary lat lon NTC SE primary secondary line ele

#### **Parameters**

ES earth to satellite transformation

SE satellite to earth transformation

primary sensor source, year and Julian day, SSYYDDD, or the

codicil ticket number; see the Remarks

secondary time of the data, HH:MM:SS

0 for a ticketed codicil

lat latitude

lon longitude

line coordinate

ele element coordinate

#### Remarks

This command can be used on any projection, e.g., SAT, PS, Mercator, etc.

To list codicil ticket numbers, enter: LA area FORM=ALL. The number is listed after PRIMARY=.

Commands NTC and NT calculate navigation transformations. NTC calculates transformations from a navigation codicil; NT calculates them from the system navigation file.

#### **Examples**

#### NTC ES 2893100 12 36 90

This entry calculates an earth to satellite transformation using codicil data from sensor source 28 for day 93100, 12 UTC at 36°N and 90°W.

#### NTC SE 74769 0 10010 20000

This entry calculates a satellite to earth transformation using codicil ticket number 74769 data at line 10010 and element 20000.

## NVU

Navigation file utility.

**Formats** 

NVU LIST [keywords]

NVU SET file

**Parameters** 

LIST

lists the navigation file entries (default)

SET

sets the navigation file pointer

file

navigation file number to set

Keywords

SS=

sensor source number

YY=

year of the navigation contained in the file

Remarks

Users cannot generate or delete navigation files on McIDAS-MVS.

**Examples** 

NVU

This entry lists the navigation file entries in the current navigation file.

NVU LIST SS=20

This entry lists the navigation entries in the current navigation file for sensor source 20.

## NXCOPY

Copies a codicil from one type to another.

	_				
1		-	 -	-	•
	_	_		-	т

NXCOPY intype inkey1 inkey2 outtype outkey1 outkey2

#### **Parameters**

intype	AREA input area codicil
	GRAF input graphics codicil
	GRAV input virtual graphics codicil
	NAV input navigation codicil
inkey1	primary key for the input codicil; see the Remarks for the formats
inkey2	secondary key for the input codicil; see the Remarks for the formats
outtype	output navigation codicil type; same options as intype
outkey1	primary key for the output codicil
	T ticketed codicil; do not enter outkey2
outkey2	secondary key for the output codicil; not used for ticketed codicils

#### Remarks

The formats for inkey1 and inkey2 are shown below.

Codicil Type	Primary Key	Secondary Key
AREA	area number	CALB (calibration type)
AREA	area number	CDnn (card image) nn=1 to 99, allowing for 99 card codicils
GRAF	ttffff (terminal and frame number)	scene
GRAV	ttffff (terminal and frame number)	scene
NAV	SSYYDDD	HHMMSS
NAV	ticket number	0

For ticketed navigation codicils, the ticket number is a number from 1 to 99999 that guarantees uniqueness.

#### See Also

Use command NXU to list and modify codicils. Use command NK to create navigation codicils.

#### **Examples**

#### NXCOPY NAV 3292300 120100 NAV T

This entry creates a ticketed navigation codicil from a master navigation codicil for sensor source 32, day 92300 at 12:01 UTC.

Use the series of examples below to copy a graphics codicil to a ticketed navigation codicil for use with an area.

#### EG

This entry erases the graphics.

#### MAP MID

This entry draws a map of the midwestern USA.

#### LG

This entry finds the graphics codicil keys.

#### NXCOPY GRAF ttffff 1 NAV T

This entry copies a graphics codicil as a ticketed navigation codicil, so the navigation can be assigned to an area. The *inkey1* value, entered in the format *ttffff* is taken from the LG output display in the previous command.

#### CA 5728 NAV=#NAVNUM

This entry changes the area 5728 parameters in the directory to the copied parameters of the ticketed navigation codicil. The ticket number is filed in the string NAVNUM.

## Chapter 14. Appendices

Appendix A.	Data Storage and File Allocation	1
Appendix B.	Sensor Source Numbers	5
Appendix C.	Meteorological Parameters	7
Appendix D.	Stability Indices	9
Appendix E.	Julian Day Numbers	11
Appendix F.	SSEC McIDAS Configuration	13
Appendix G.	WSI Radar	15
Appendix H.	McBASI Editor and Interpreter for McIDAS-MVS 14-1	17

Revised 11/93

# Appendix A Data Storage and File Allocation

SSEC's McIDAS-MVS can have 32,000 areas and 32,000 grid files and MD files. The actual maximum allowed is a site tailored option; contact your operators to request your system's maximum permitted area, MD file and grid file numbers. Typically, a block of 16 numbers is assigned to a project number or user for data storage. Do not attempt to store data in numbers other than your own, as you may ruin another user's data. The computer operators can assign protection for your numbers.

Numbers 1 to 1999 are reserved for system operations. The location of real-time area, MD file and grid file numbers on SSEC's McIDAS-MVS changes periodically. SSEC operations maintains a set of LW files that describe the data and its location. The set of LW files is listed in the daily logon message. To see the daily logon message, enter: .SEE LOGON.

#### **Bands for Satellite Areas**

The bands for real-time satellite areas are described below. Resolution refers to the maximum resolution of the instrument, which is not always the same as the resolution of the ingested data in the area. Definitions for the terms and acronyms follow.

#### GOES Variable Image

Satellites GOES-8 and GOES-9
Area Types VIS and IR
Instrument Imager

Resolution 1 km VIS, 4 km IR, 8 km Water Vapor

Band	Central Wavelength (µm)	Primary Uses
1000 1000	0.65 (VIS)	Cloud cover
2	3.9 (IR)	Nighttime clouds; shortwave window
3	6.8 (IR)	Upper level water vapor
4	10.7 (IR)	Surface temperatures; longwave window
5	12.0 (IR)	Sea surface temperature and water vapor

GOES Variable Sounder

Satellites GOES-8 and GOES-9
Area Type Sounding
Instrument Sounder
Resolution 8 km

OKER SI	Band	Central Wavelength (µm)	Absorbing Gases	Wave Number (cm <sup>-1</sup> )	Sounding Level (mb)	Primary Uses
	1	14.7	CO <sub>2</sub>	680	90	Stratosphere temperature
	2	14.4	CO <sub>2</sub>	696	300	Sounding; tropopause temperature
	3	14.1	CO <sub>2</sub>	711	550	Sounding; upper-level temperature
	4	13.6	CO <sub>2</sub> ; H <sub>2</sub> O	733	850	Sounding; mid-level temperature
	5	13.4	CO <sub>2</sub> ; H <sub>2</sub> O	748	900	Sounding; low-level temperature
	6	12.7	H <sub>2</sub> O	790	Surface	Sounding; total precipitable water
	7	12.0	H <sub>2</sub> O	832	Surface	Surface temperature and moisture
	8	11.0	H <sub>2</sub> O	907	Surface	Surface temperature
	9	9.7	O <sub>3</sub>	1030	25	Total ozone
	10	7.4	H <sub>2</sub> O	1345	725	Low-level moisture
	11	7.0	H <sub>2</sub> O	1425	550	Sounding; mid-level moisture
	12	6.5	H <sub>2</sub> O	1535	350	Sounding; upper-level moisture
	13	4.6	N <sub>2</sub> O	2188	1000	Temperature; low-level temperature
	14	4.5	N <sub>2</sub> O	2210	950	Sounding; mid-level temperature
	15	4.4	CO2; N2O	2248	650	Sounding; upper-level temperature
	16	4.1	CO <sub>2</sub>	2420	Surface	Sounding; boundary layer temperature
	17	4.0	Window	2513	Surface	Temperature
	18	3.7	Window	2671	Surface	Temperature
	19	0.70	Window	14367	Surface	Clouds
	20	disa medimum	un der anner	Elatic III ela	THE LOCAL TRANSPORT OF	Star Scan

**GOES AAA** 

Satellites

GOES-6 and GOES-7

Area Types

VIS, IR, MSI, Dwell Sounding

Instrument VAS

Resolution

1 km VIS, 4/8 km IR

Band	Central Wavelength (µm)	Major Absorbing Gases	Sounding Level (mb)	Primary Uses
1	14.7 (IR)	CO <sub>2</sub>	70	Temperature sounding
2	14.5 (IR)	CO <sub>2</sub>	125	Temperature sounding
3	14.3 (IR)	CO <sub>2</sub>	200	Temperature sounding
4	14.0 (IR)	CO <sub>2</sub>	500	Temperature sounding, cloud heights
5	13.3 (IR)	CO <sub>2</sub>	920	Temperature sounding, cloud heights
6	4.5 (IR)	CO <sub>2</sub> , N <sub>2</sub> O	850	Temperature sounding
7	12.7 (IR)	H <sub>2</sub> O	1000	Water vapor detection
8	11.2 (IR)	Window	Surface	Nighttime cloud detection, surface temp
9	7.3 (IR)	H <sub>2</sub> O	600	Water vapor detection
A(10)	6.7 (IR)	H <sub>2</sub> O	400	Water vapor detection
B(11)	4.4 (IR)	CO <sub>2</sub> , N <sub>2</sub> O	300	Temperature sounding
C(12)	3.9 (IR)	Window	Surface	Surface skin temperature, cloud detection
D*				
NA	0.65 (VIS)	Window	Surface	Daytime cloud detection

<sup>\*</sup> Band D(13) in a McIDAS area is the same as band 8 but at lower resolution.

POES	
------	--

Satellites NOAA-6 through 14 (currently NOAA-12 and 14)
Area Types HRPT and GAC
Instrument AVHRR
Resolution 1 km (VIS and IR)

Band	Central Wavelength (µm)	Primary Uses
1. Personal	0.63 (VIS)	Daytime cloud detection
2	0.91 (NIR)	Delineation of surface water, vegetation analyses
3	3.7 (IR)	Sea surface temperatures, hot spot detection
4	11.0 (IR)	Cloud detection, surface temperature
5	12.0 (IR)	Sea surface temperatures, soil moisture; band 5 on NOAA-10 is not available.

Satellites NOAA-6 through 14 (currently NOAA-12 and 14)
Area Types TIP
Instrument HIRS
Resolution 20 km

Band	Central Wavelength (µm)	Major Absorbing Gases	Sounding Level (mb)	Primary Uses
1	15.0 (IR)	CO <sub>2</sub>	30	Temperature sounding
2	14.7 (IR)	CO <sub>2</sub>	60	Temperature sounding
3	14.5 (IR)	CO <sub>2</sub>	100	Temperature sounding
4	14.2 (IR)	CO <sub>2</sub>	400	Temperature sounding
5	14.0 (IR)	CO <sub>2</sub>	600	Temperature sounding
6	13.7 (IR)	CO <sub>2</sub> , H <sub>2</sub> O	800	Temperature sounding
7	13.3 (IR)	CO <sub>2</sub> , H <sub>2</sub> O	900	Temperature sounding
8	11.1 (IR)	Window	Surface	Surface temperature
9	9.7 (IR)	O <sub>3</sub>	25	Ozone measurement
10	8.2 (IR)	H <sub>2</sub> O	900	Water vapor detection; NOAA-6 through 10 and 12
	12.5 (IR)	H <sub>2</sub> O	Surface	Water vapor detection; NOAA-11 and 14
11	7.3 (IR)	H <sub>2</sub> O	700	Water vapor detection
12	6.8 (IR)	H <sub>2</sub> O	500	Water vapor detection
13	4.57 (IR)	N <sub>2</sub> O	1000	Temperature sounding
14	4.52 (IR)	N <sub>2</sub> O	950	Temperature sounding
15	4.47 (IR)	CO <sub>2</sub> , N <sub>2</sub> O	700	Temperature sounding
16	4.4 (IR)	CO <sub>2</sub> , N <sub>2</sub> O	400	Temperature sounding
17	4.2 (IR)	CO <sub>2</sub>	Surface	Temperature sounding
18	4.0 (IR)	Window	Surface	Surface temperature
19	3.8 (IR)	Window	Surface	Surface temperature
20	0.70 (VIS)	Window	Cloud	Daytime cloud detection

Revised 5/96 14-3

Satellites

NOAA-6 through 14 (currently NOAA-12 and 14)

Area Types Instrument

Resolution

SSU 62 km

Band	Central Wavelength (µm)	Major Absorbing Gases	Sounding Level (mb)	Primary Uses		
1	15.0	CO <sub>2</sub>	100	Temperature sounding		
2	15.0	CO <sub>2</sub>	35	Temperature sounding		
3	15.0	CO <sub>2</sub>	10	Temperature sounding		

Satellites

NOAA-6 through 14 (currently NOAA-12 and 14)

Area Types Instrument TIP MSU

Resolution

115 km

Band	Frequency (GHz)	Major Absorbing Gases	Primary Uses	
1	50.3	O <sub>2</sub>	Temperature sounding	
2	53.8	02	Temperature sounding	
3	55.0	O <sub>2</sub>	Temperature sounding	
4	58.0	02	Temperature sounding	

#### **METEOSAT**

Satellites

M-1 through M-5 (currently M-3, M-4 and M-5)

**Area Types** 

VIS, IR, B-sector

Instrument

**METEOSAT** Radiometer

Resolution

2.5 km VIS, 5 km IR

Band	Central Wavelength (µm)	Primary Uses
1	0.75 (VIS)	Daytime cloud detection
8	11.5 (IR)	Nighttime cloud detection, surface
	AND STREET, SALE	temperature
10 (A)	6.9 (IR)	Water vapor detection

**GMS** 

Satellites GMS-4 with SS numbers 12 and 13

Area Types VIS, IR and DOC

Instrument VISSR

Resolution 1.25 km VIS, 5.0 km IR

Band	Central Wavelength (µm)	Primary Uses
1 4 14	11.5 (IR) Documentation 0.63 (VIS)	*** Raw Ingest Bands *** Nighttime cloud detection, surface temperatures Not displayed; ingest documentation Daytime cloud detection
1 8	0.63 (VIS) 11.5 (IR)	*** Converted Bands ***  Daytime cloud detection  Nighttime cloud detection, surface temperatures

Satellites GMS-4 through GMS-8 with SS numbers 82 through 86

Area Types VIS, IR and DOC

Instrument VISSR

Resolution 1.25 km VIS, 5.0 km IR

Band	Central Wavelength (µm)	Primary Uses
1	0.63 (VIS)	Daytime cloud detection
2	11.0 (IR)	Nighttime cloud detection, surface temperatures
3	12.0 (IR)	Sea surface temperatures, soil moisture
4	6.8 (IR)	Water vapor detection
5	Documentation	Not displayed; ingest documentation

Terms	Term	Definition
	absorbing gases	primary gases which absorb and emit radiation at the central wavelength
	band	number given to the wavelength channel of the satellite data
	B-sector	data covering Europe, northern Africa and the eastern Atlantic
	central wavelength	wavelength falling in the middle of the band over which the satellite collects data
	sounding level	average level where most of the radiant energy sensed by the satellite originates, assuming a cloud-free atmosphere
	uses	examples of how a band is used in physical applications
	window	channel that is transparent to atmospheric radiation

cronyms	Acronym	Definition
	AVHRR	Advanced Very High Resolution Radiometer
	GAC	Global Area Coverage
	GMS	Geostationary Meteorological Satellite
	GOES	Geostationary Operational Environmental Satellite
	HIRS	High resolution Infrared Radiation Sounder
	HRPT	High Resolution Picture Transmission
	IR	InfraRed
	NIR	Near InfraRed
	MSI	MultiSpectral Imagery (IR)
	MSU	Microwave Sounding Unit
	NOAA	National Oceanic and Atmospheric Administration
	POES	Polar Orbiting Environmental Satellite
	SSU	Stratospheric Sounding Unit
•	TIP	TIROS Information Processor
	VAS	VISSR Atmospheric Sounder
AR channels SA mother	VIS	VISible
	VISSR	Visible and InfraRed Spin Scan Radiometer
	WV	Water Vapor (IR)

14-4.2

# Appendix B Sensor Source Numbers

Number	Sensor Source	09
0	Derived data	19
1	Test netterns	
2	Graphics	
3	Miscellaneous	
4	PDUS METEOSAT Visible	
5	PDUS METEOSAT Infrared	
6	PDUS METEOSAT Water Vapor	
7	Radar	
8	Miscellaneous aircraft data	
9	Raw METEOSAT	
10	Composito imago	
12	GMS Vigible	
13	GMS Infrared	
14	ATS 6 Visible	
15	ATS 6 Infrared	
16	SMS 1 Visible	
17	CMC 1 Infrared	
18	CMC 2 Visible	
19	SMS-2 Infrared	
20	GOES-1 Visible	
21	COFS-1 Infrared	
22	COFC 9 Visible	
23	GOFS-2 Infrared	
24	GOES-3 Visible	
25	GOES-3 Visible GOES-3 Infrared	
26		
	GOES-4 Visible (VAS)	OTA CI
27	GOES 5 Winite GVAS	or (VAS)
28	GOES-5 Visible (VAS)	(TAC)
29	GOES 6 W. 11	or (VAS)
30	GOES-6 Visible	
31	GOES-6 Infrared	ne
32	GOES-7 Visible, Block 1 Auxiliary	Data
33	GOES-7 Infrared	
41	TIROS-N (POES)	
42	NOAA-6	*
43	NOAA-7	
44	NOAA-8	
45	NOAA-9	
46	Venus	
47	Voyager 1	
48	Voyager 2	

Revised 5/96

Number	Sensor Source	
49	Galileo	
50	Hubble ST	
54	METEOSAT 3	
55	METEOSAT 4	
56	METEOSAT 5	
60	NOAA-10	
61	NOAA-11	
62	NOAA-12	
63	NOAA-13	
64	NOAA-14	
70	GOES 8 (Imager)	
71	GOES 8 (Sounder)	
72	GOES 9 (Imager)	
73	GOES 9 (Sounder)	
74	GOES 10 (Imager)	
75	GOES 10 (Sounder)	
76	GOES 11 (Imager)	
77	GOES 11 (Sounder)	
78	GOES 12 (Imager)	
79	GOES 12 (Sounder)	
80	ERBE	
82	GMS 4	
83	GMS 5	
84	GMS 6	
85	GMS 7	
86	GMS 8	
87	DMSP F-8	
88	DMSP F-9	
89	DMSP F-10	
90	DMSP F-11	
91	DMSP F-12	
92	DMSP F-13	
93	DMSP F-14	
	DMSP F-14 DMSP F-15	
94	FY-1B	
95	FY-1C	
96	FY-1D	
97	CORE-7 Vendle Block 1	

# **Appendix C Meteorological Parameters**

The parameters below are primarily used in Chapter 9, Weather Analysis, and other applications.

Parameter	Definition	
ABV	absolute vorticity	
ADV	advection	
CLD	cloud cover	
DSH	deformation due to shear	
DST	deformation due to stretching	
DVG	divergence	
GEO	geostrophic wind	
GUS	wind gusts	
$\mathbf{ID}$	3-letter identification	
IDN	5-digit identification	
MIX	mixing ratio	
P	pressure	
PCP	precipitation total	
PLOT	plot station model	
PSL	surface pressure	
SND	snow cover	
SPD	wind speed	
STR	streamlines	
T	temperature	
TD	dew point	
THA	theta	
THAE	theta-E	
VIS	visibility	
VOR	vorticity	
WIN	wind	
WNF	wind flags	
WNV	wind vector	
WX	weather	
Z	height	
ZCH	high cloud height	
ZCL	low cloud height	
ZCM	middle cloud height	
ZS	station elevation	

Append ADV or DVG to any parameter for advection or divergence.

# Appendix D Stability Indices

Below are the indices calculated by commands STAB, STABIL, STUVE and SKEWT, which are documented in Chapter 9.

Indices	STAB and STABIL Schema Names	STUVE	SKEWT	UNITS
convective temperature	TCON	CONV-T	CVT	K x 100
equilibrium pressure level	PEQU	EQUIP	EQUIP	mb x 100
forecast maximum temperature	FMAX	FMAX	FMAX	K x 1000
K index	KINX	tanii. yd Laden	KINX	x100
lifted index	LI*	LI	LI	x100
parcel dew point	TDP	Kx100		
parcel equivalent potential temperature	THEP	dosu (L) obstano O favo (L)		K x 100
parcel mixing ratio parcel potential	MIXP	A MADE AME A MADE		K x 100
temperature	THAP	elleruris		K x 100
precipitable water	WV* 055 W/30 065 4	PW	PW	mm
sweat index	SWET*	q ar wq		x100
totals index	TOT*	TOTALS	TOTAL	x100

<sup>\*</sup> plotted by STABIL in a station model

#### **Stability Parameters**

#### TOTAL

TOTAL is the Total Totals Index. It is the sum of the Vertical Totals (VT) and Cross Totals (CT). TOTAL = Vertical Totals + Cross Totals = (850 mb TEMP + 850 mb DEW POINT) - 2 (500 mb TEMP).

#### **EQUIP**

EQUIP is the equilibrium pressure, in mb. It is synonymous with the Equilibrium Level (EL). EQUIP is the pressure at which the rising saturated parcel encounters negative buoyancy. Above that pressure, the parcel is cooler than its surroundings.

#### **FMAX**

FMAX is the forecast maximum temperature, computed only at 12 UTC, in degrees Celsius. It is found by displacing the parcel at the top of the boundary layer to the surface pressure dry adiabatically.

#### **CVT**

CVT is the convective temperature, in degrees Celsius. It is found by first computing the parcel's equivalent potential temperature (theta-E). This is followed by a "march" up the sounding to the point where the parcel theta-E equals the sounding theta-E. This point is the Convective Condensation Level (CCL). From the CCL, the parcel is brought down to the surface pressure dry adiabatically. The temperature at the surface pressure is the CVT.

#### LI

LI is the lifted index, in degrees Celsius. The point at which the parcel is cooled dry adiabatically until saturated is called the Lifted Condensation Level (LCL). From the LCL, the moist parcel is cooled moist adiabatically until reaching the 500 mb level. The temperature difference between the parcel and the 500 mb temperature is the LI.

#### KINX

KINX is the K-Index, in degrees Celsius. It provides a measure of thunderstorm potential based on lapse rate and the vertical extent of the moisture content in the lower atmosphere. KINX= (850 TEMP - 500 TEMP) + 850 DEW POINT - 700 DEW POINT DEPRESSION.

#### PW

PW is precipitable water, in mm. It is the sum of average mixing ratios across pressure layers up to and including 500 mb, i.e., w(ave) \* DP, where w(ave) represents the average mixing ratio across the pressure layer (DP). The data used is from the interpolated sounding seen with UL LIST station OPT=7.


## Appendix E Julian Day Numbers

The chart below shows the day numbers corresponding to the numbered Greenwich days.

Day	1											
of		Feb	March	April	May	June	July	August	Sept	October	Nov	Dec
Month 1	Jan 001	032	060 061	091 092	121 122	152 153	182 183	213 214	244 245	274 275	305 306	335 336
2	002	032	061 062	092 093	122 123	153 154	183 184	214 215	245 246	275 276	306 307	336 337
3	003	033	062 063	093 094	123 124	154 155	184 185	215 216	246 247	276 277	307 308	337 338
4	003	035	063 064	094 095	124 125	155 156	185 186	216 217	247 248	277 278	308 309	338 339
5	005	036	064 065	095 096	125 126	156 157	186 187	217 218	248 249	278 279	309 310	339 340
6	006	037	065 066	096 097	126 127	157 158	187 188	218 219	249 250	279 280	310 311	340 341
7	007	038	066 067	097 098	127 128	158 159	188 189	219 220	250 251	280 281	311 312	341 342
8	008	039	067 068	098 099	128 129	159 160	189 190	220 221	251 252	281 282	312 313	342 343
9	009	040	068 069	099 100	129 130	160 161	190 191	221 222	252 253	282 283	313 314	343 344
	010	040	069 070	100 101	130 131	161 162	191 192	222 223	253 254	283 284	314 315	344 345
10	011	041	070 071	100 101	131 132	162 163	192 193	223 224	254 255	284 285	315 316	345 346
12	012	042	071 072	102 103	132 133	163 164	193 194	224 225	255 256	285 286	316 317	346 347
	013	043	071 072	102 103	133 134	164 165	194 195	225 226	256 257	286 287	317 318	347 348
13		044	072 073	103 104	134 135	165 166	195 196	226 227	257 258	287 288	318 319	348 349
14	014				134 135	166 167	196 197	227 228	258 259	288 289	319 320	349 350
15	015	046	074 075 075 076	105 106	136 137	167 168	197 198	228 229	259 260	289 290	320 321	350 351
16 17	017	047	076 077	107 108	137 138	168 169	198 199	229 230	260 261	290 291	321 322	351 352
18	018	049	077 078	108 109	138 139	169 170	199 200	230 231	261 262	291 292	322 323	352 353
	019	050	078 079	109 110	139 140	170 171	200 201	231 232	262 263	292 293	323 324	353 354
19	020	051	078 079	110 111	140 141	171 172	201 202	232 233	263 264	293 294	324 325	354 355
20	020	052	080 081	111 112	141 142	172 173	202 203	233 234	264 265	294 295	325 326	355 356
22	021	053	081 082	112 113	142 143	173 174	203 204	234 235	265 266	295 296	326 327	356 357
23	023	054	082 083	113 114	143 144	174 175	204 205	235 236	266 267	296 297	327 328	357 358
	023	055	083 084	114 115	144 145	175 176	205 206	236 237	267 268	297 298	328 329	358 359
24		056	084 085	115 116	145 146	176 177	206 207	237 238	268 269	298 299	329 330	359 360
25	025	057	085 086	116 117	146 147	177 178	207 208	238 239	269 270	299 300	330 331	360 361
26	026	058	086 087	117 118	146 147	178 179	208 209	239 240	270 271	300 301	331 332	361 362
27						179 180	209 210	240 241	270 271	301 302	332 333	362 363
28	028	059	087 088	118 119	148 149	A SOUTH OF STREET		240 241	271 272 273	302 303	333 334	363 364
29	029	060		119 120	149 150	180 181	210 211	The state of the s	The second second second second	302 303	Warner of The Local Division	364 365
30	030	-	089 090	120 121	150 151	181 182	211 212	242 243	273 274		334 335	365 366
31	031	1	090 091		151 152		212 213	243 244		304 305		302 300

14-12 Issued 4/93

## Appendix F SSEC McIDAS Configuration



### Appendix G WSI Radar

Weather Services International (WSI) provides radar data (NOWrad) for McIDAS. WSI collects data from National Weather Service radar sites and combines these data into a composite image.

#### Composite Radar Images Available

WSI produces the nine composite radar images described below. WSI takes 5 to 10 minutes after it collects the data to create a composite radar image.

- 4-bit data, which is available for operational use, is generated at 15-minute intervals (0, 15, 30 and 45 minutes past the hour). The image has a 4 km resolution and is 240 lines by 378 pixels.
- 8-bit data, which is also available for operational use, is generated at 5-minute intervals. The image has a 2 km resolution and is 480 lines by 756 pixels.
- <u>USA national precipitation summaries</u> are generated every 30 minutes. The image has a 16 km resolution and is 240 lines by 378 pixels.
- GOES IR satellite photos with superimposed radar echoes are generated 25 to 30 minutes past the time data is collected.
   They have an 8 km resolution and are 480 lines by 756 pixels.
- The precipitation summary for the <u>current day since 12Z</u> has a 16 km resolution and is 240 lines by 378 pixels.
- Yesterday's 12Z to 12Z precipitation summary includes the current day's precipitation since 12Z, has a 16 km resolution and is 240 lines by 378 pixels.
- The precipitation composite for the <u>last 7 complete days</u> (week) has a 16 km resolution and is 240 lines by 378 pixels.
- Month-to-date precipitation composite images have a 16 km resolution and are 240 lines by 378 pixels.
- Year-to-date precipitation composite images have a 16 km resolution and are 240 lines by 378 pixels.

#### **Image Display**

WSI data uses the 32 color levels defined below. They are listed in the output from command D under column RAW.

Color level	Definition
0	water
1	land
2	borders
3	special basemap borders
4	airport identifiers
5	warning boxes
6 and 7	reserved or not used
8	missing indicators and warning box borders
9	site present indicators and radar site identifiers
10 to 15	reserved or not used
16 to 31	precipitation levels 0 to 15, which correspond to scaled
	dBZ values from < 5 to 75

WSI calibration modules modify color levels 16 to 31 into the standard 7 precipitation levels (VIPs 0 through 6). The table below lists the VIP levels corresponding to the 0 to 75 dBZ precipitation ranges and the 0 to 255 McIDAS gray levels. WSI color levels 0 to 15 are assigned VIP level 0.

Feature/VIP level	dBZ values	McIDAS gray level (8-bit data)	
water	_a.a.mq & 15	0	
land	asu <del></del> or poor	16	
basemap borders		32	
interstate highways	4.8	48	
site missing		96	
radar IDs	e predictional e	112	
site present	notifulcom mal	112	
1 andredininess 331 o	1-29	136-168	
2	30-40	176-184	
3	41-45	192	
4	46-49	200	
5 sai tot attioquio	50-57	208	
6 pure menunceau an	> 57	213-255	
annotation line		~232	

Use commands DF, AA, AAMAP, etc., to display WSI data. If you specify maps and borders for the 4- and 8-bit regional composites in the scheduler program RADE, they become part of the image and are subject to shading and enhancing with commands such as EU and EB. You are encouraged to develop enhancement tables for WSI images to highlight map features and precipitation echoes.

# Appendix H McBASI Editor and Interpreter for McIDAS-MVS

Use the McBASI Editor to edit card-image format (80 characters/line) LW files and McBASI files from a McIDAS workstation.

Editor instructions begin with a backslash (\) to distinguish them from McIDAS commands. Assigned line numbers permit you to direct commands to a specific line.

McBASI also has an online BASIC language Interpreter. The Editor and Interpreter are easily accessible. You can switch between them without specifying a program. If the Editor can't execute a command, it sends it to the Interpreter.

#### This appendix contains:

- McBASI Interpreter commands and reserved words
- McBASI Editor commands
- McBASI sample programs
- a McBASI practice session

#### McBASI Interpreter Commands and Reserved Words

Use the following McBASI Interpreter commands and reserved words to create and run a McBASI program. They are listed alphabetically. Each description contains the command's function and syntax. Some have examples.

CLOSE

Frees the I/O table entry for the specified unit (LW file). A maximum of 10 files are active at once.

Syntax:

CLOSE unit

where unit is any valid numeric expression associated with an LW file by a previous OPEN command.

Example: CLOSE 10

where 10 is the unit number associated with an LW file by a

prior OPEN command.

**GOSUB** 

Changes the normal downward flow of control. This command is like GOTO, except control may be returned to the statement following the GOSUB by executing a RETURN statement.

Syntax:

GOSUB x

where x is any valid numeric expression.

Example: 100 GOSUB 1000

1000 PRINT B 1010 RETURN

In this example, control is returned to line 100.

**GOTO** 

Changes the downward, line-by-line flow of control.

Syntax:

GOTO x

where x is any valid numeric expression.

Examples: GOTO 300

GOTO 13+6\*X

IF

Compares expressions, using relational operators, to determine whether to execute a statement, e.g., IF X+13>Y-9 GOTO 310. If several statements are used, either all are done (if the relationship is true) or none are done (if the relationship is false). To compare character strings, use only the = and <> relational operators. If statement is a let statement, i.e., a replacement statement, use the command LET.

Syntax:

IF expr relop expr statement

where:

expr any valid expression

relop

any relational operator

= means equal

<> or >< means not equal

> means greater than

< means less than

>= or => means greater than or equal to

<= or =< means less than or equal to

statement step to be executed if the relationship is true

Example: IF X=8 LET Y=13:LET J=9:GOTO 890
In this example, if X=8 is true, both LET statements and the GOTO statement are executed.

**INPUT** 

Allows data to be gathered from either an LW file or RUN statement. The input statement for LW files is restricted; only one character variable may be designated and an entire 80-character record from the file will be read into this variable. The syntax of this LW file input is shown below.

Syntax:

INPUT @u(r), A\$

where:

- u numeric expression for the unit number; @ is required
- (r) numeric expression used to specify a record number;
   record numbers begin with zero
- A\$ variable into which the record is read

This form of INPUT is useful for reading output produced by commands that use the DEV=F (device=file) keyword to direct their output into an LW file. To set the LW file pointer to the top of the file, rather than continuing down the file, use: DEV=F file R.

The syntax of the INPUT statement used to obtain values from the RUN statement is shown below.

Syntax:

INPUT a,b,c

where a, b, c are the variables.

Values are taken from the RUN command line as positional parameters of a normal McIDAS command. If the named variable is numeric, it is picked up as a number. If the variable is a character string, the value is picked up as a character parameter (up to 12 characters, no blanks). Each INPUT statement of this form picks up the next positional parameter. Thus, these statements are equivalent to the single INPUT statement above:

INPUT a INPUT b

INPUT c

If the RUN command line contains a quoted string (for example, "THIS IS A QUOTED STRING...), it may be read by using a character variable. The first character in the variable is a double quote (") to indicate it was picked up from the quoted string.

An attempt to input a parameter which is not present results in either a numeric value of zero or a character string of length zero.

Example: INPUT @3, A\$

IF MID\$(A\$.1.4)=EOF\$ GOTO xxx

This example tests for an end-of-file, using the pseudovariable EOF\$.

KEYIN

Submits a McIDAS command to be executed. The syntax is the same as the PRINT statement.

Syntax:

KEYIN list

where list is zero or more expressions. Place a comma or semicolon between expressions. Commas tabulate to a print position (column) that is a multiple of 16. Semicolons allow no spaces to be inserted. Do not end the list with a semicolon or comma unless you don't want the statement to execute until you've entered another KEYIN statement.

Example: LET A\$="MSN"

mad redday will ad pa con ad a LET T= 12.0

KEYIN "SL A ";

KEYIN A\$;

KEYIN " ";T

This example submits the command: SL A MSN 12

#### LET

Creates a replacement statement in a McBASI program.

Syntax: LET var = expr

where: var variable for numeric quantities; is a single letter or a

single letter followed by a digit; numeric variables are REAL\*4 quantities; for character strings, A\$ through Z\$ are available and may contain up to 255 characters

each

expr any valid numeric or character expression; numeric

expressions may contain the operators +,-,\*,/,\*\*, with normal precedence rules; for character or string expressions, expr may be a string variable, a string constant enclosed in quotes ("ABC"), a concatenation of two strings with the + operator, or a string function, e.g., pseudovariable TIME\$

The hexadecimal constant \$nnnn is available, e.g., \$FE equals 254. A single array is also available; ten thousand words are reserved and referenced by following a numeric variable name with a parenthetical expression. The value of this expression is added to the value of the variable to obtain an index into this array space.

Example: LET A=0

LET B=A(13) references the 13th word

LET C=10

LET B=C(13) references the 23rd word (10 + 13)

Do not mix numeric and character expressions. The VAL function converts character to numeric; STR\$ converts numeric to character. In most cases, the LET may be omitted.

#### **OPEN**

Logically equates a *unit* number with the name of an LW file for INPUT and OUTPUT. When an OPEN statement is executed, the record pointers for input and output are set to point to the first record of the file (record zero). If these options are omitted from the INPUT or PRINT statements, the next record is used.

When using the OPEN statement to read the output from a command created with a DEV=F keyword, use the pseudovariable TFILE\$ in place of the *filename*.

Syntax: OPEN filename, unit

where: filename valid string expression, less than 13 characters

unit any valid numeric expression

Example: OPEN "YYEXPLE",10

#### **PRINT**

Displays command text on your workstation. When developing programs that generate commands, use the PRINT statement for testing. This allows you to see the would-be command text on your workstation. The PRINT statement is identical in structure to the KEYIN statement.

PRINT list Syntax:

> where list is zero or more expressions. Place a comma or semicolon between expressions. Commas tabulate to a print position (column) that is a multiple of 16. Semicolons allow no spaces to be inserted. Do not end the list with a semicolon or comma unless you don't want the statement to execute until a future PRINT or KEYIN statement is executed.

Output may be directed to an LW file in card image format (80 characters per record). If the print line is less then 80 characters, it is blank padded. If it is more than 80, it is truncated. This file directed form of the PRINT statement has the following syntax.

Syntax:

PRINT @u(r), list

where:

- numeric expression for the unit number; @ is required
- numeric expression used to specify the record number which begins with zero; parentheses are required; if the r clause is omitted, the next record is assumed (record following the last one written); the comma is required and followed by a list of variables, constants, etc.; if a PRINT statement ends with a semicolon or comma (for do not print this yet), the @u(r) clause is ignored

Example: LET X=123

LET A\$= "MSN"

LET T= 12.0

PRINT "this is a test ":X:

KEYIN "SL A ":

PRINT " of the ".

KEYIN AS:

PRINT "print statement"

KEYIN " ":T

This example produces the following print line:

this is a test 123 of the

print statement

It also submits the command: SL A MSN 12.

Example: PRINT @4,EOF\$

This is a final PRINT statement that outputs a logical end-of-file. Use it for a sequential file that will be read by another McIDAS program.

Example: LPRINT list

This entry sends output directly to the local printer

The question mark (?) may be used in place of the PRINT statement. For example, these two statements are equivalent:

? "A=";A

PRINT "A=":A

REM

Adds comments or inserts a help into your program. Remarks (REMs) do not affect the flow of the program.

Syntax:

REM comment

Examples: REM?

REM?

Use one of these examples to begin a help line, which can be listed using the standard McIDAS HELP command.

RETURN

Returns from a subroutine call; also see GOSUB.

Syntax: RETURN

RUN

Executes your McBASI program. Enter RUN without the backslash (\). RUN stands alone or can be used with a list of parameters. The RUN statement can be abbreviated; see the examples below.

Syntax:

RUN parameters FILE= CLEAR= VAR=

where:

parameters parameter values

FILE=

runs a BSAVEd program from a different file

CLEAR=

suppresses initialization of all variables

NO variables retain previous values

variable's source

VAR=

SHARE shares variables when one

McBASI program RUNs another

 $\boldsymbol{x}$ 

LW file to store the variables (different from the default assigned by terminal number)

Examples: RUN parameters FILE=xxxxxx

'xxxxxx parameters

where xxxxxx is the file name (limited to 6 characters). These two RUN statements are interchangeable.

**STOP** 

Stops your program; also stops by "falling off the end," completing the last line of a program.

Syntax: STOP

#### **Functions**

The following functions are available. x and y refer to numeric expressions; a\$ and b\$ refer to character expressions.

Function	Meaning
SIN(x), $COS(x)$	trigonometric functions; x is an angle in radians;
TAN(x), $ASIN(y)$	the arc functions return values in radians
ACOS(y), $ATAN(y)$	
EXP(x)	exponential
LN(x)	natural logarithm
LOG(x)	base ten logarithm
ABS(x)	absolute value of $x$
INT(x)	integer part (truncated value) of $x$
NINT(x)	nearest integer value to x
MOD(x,y)	the remainder resulting from $x/y$
LEN(a\$)	length of the string in a\$
INDEX(a\$,b\$)	location in $a$ \$ string of $b$ \$ substring; if $b$ \$ is not
	in a\$, zero is returned
VAL(a\$)	numeric value of string a\$
SQRT(x)	square root of $x$
STR\$(x)	locates the string corresponding to the number $x$
	using McIDAS function CFG for the conversion
MID\$(a\$,x,y)	extracts a string of length $y$ from $a$ \$, starting at
	character position $x$ (first position = 1)
TIME\$	a pseudostring variable of length 6 which has
partar rate acreq	the current time in the format HH:MM:SS
DATE\$	a pseudostring variable of length 5 which has
taxiladi ji assaorq uli	the current date in the format YYDDD
DAY\$	a pseudostring variable of length 6 which has
BOUTTON B, WICHTANA	the current date in the format YYMMDD
TFILE\$	a pseudostring variable of length 9; a temporary
	LW file named during execution of a BASIC
	program; it is deleted (via LWD) when the
TOTA.	program terminates
EOF\$	a pseudostring variable; contains the universal value Z80808080
PEEK(x)	returns a value from User Common (UC)
	location x

Function	Meaning
PEEK\$(x)	returns a character string; PEEK assumes the
	UC word is integer and converts it to REAL*4;
	use command SHOWME DNUC ALL to list
	McIDAS User Common values
BIN(string\$)	the real number equivalent of the binary integer
	value in string\$; assumes the first four bytes
	are an integer value (in binary)
CHR\$(x)	returns a string of length one which is equivalent
	to the EBCDIC code value $x$
KSYS(x)	returns the value from the System KeyTable
	location $x$ ; the value in SYSKEY is assumed to
	be an integer and is converted to REAL*4
KSYS\$(x)	returns the value from the System KeyTable
	location $x$ ; the value in SYSKEY is assumed to
	be a character string of length 4

#### **McBASI Editor Commands**

Use the following McBASI Editor commands to edit card-image LW files and BASIC files on a McIDAS workstation. They are listed alphabetically. The backslash preceding each command distinguishes McBASI Editor commands from McIDAS commands.

Each description contains the command's function and syntax. Some descriptions also provide examples.

**BLOAD** 

Copies the contents of BASIC file filename into the terminal buffer.

Syntax:

\BLOAD filename

**BSAVE** 

Saves a BASIC format program by copying the contents of your terminal buffer to a special file for BASIC programs. BASIC programs can be run directly from this file.

Syntax:

**\BSAVE** filename

If filename already exists, use the form: \BSAVE (D) filename.

#### *\DELETE*

Deletes a line or range of lines. \DELETE can be abbreviated to \DEL.; the period (.) is mandatory.

Syntax: \DELETE line

\DELETE bline,eline \DELETE ,eline \DELETE bline,

**\DELETE** 

Examples: \DEL. 25

This entry deletes line 25.

**\DEL. 10,45** 

This entry deletes lines 10 through 45.

**\DELETE** ,50

This entry deletes the current line through line 50.

**\DELETE 1000,** 

This entry deletes from line 1000 to the end of the file.

#### **EDIT**

Changes a string of characters into another string of characters. If you omit the line number specifications, the changes are made to every line in the file. EDIT is abbreviated as "\E."; see the examples.

Syntax: \EI

\EDIT line /oldstring/newstring/

\EDIT bline,eline /oldstring/newstring/ \EDIT ,eline /oldstring/newstring/ \EDIT bline, /oldstring/newstring/

Examples: \E. 10,100 /SA/FT/

This entry changes all occurrences of SA in lines 10 through

100 to FT.

**\E. 50,150/A/AAA/ALL** 

In this example, ALL changes all occurrences of oldstring in lines 50 through 150. If ALL is not specified, only the first occurrence is changed.

\E. 20 'HELLO'

This statement searches line 20 for occurrences of HELLO. If newstring is omitted, the command searches for oldstring.

\EC.

This entry edits only the current line.

\FILES

Lists your LW and BASIC program files. At SSEC, the LW file list is purged each month and may not reflect the presence of an LW file. BASIC programs currently on file are listed.

Syntax:

\FILES

HELP

Displays an on-screen summary of Editor commands. Use the McIDAS HELP command to display the online help message for a specific McBASI command.

Syntax:

\HELP

\KILL

Stops a BASIC language program running on your workstation. The variable table is saved so values may be displayed with direct commands.

Syntax:

\KILL

\LIST

Lists all or part of your terminal buffer; abbreviated as "\L.".

Syntax:

\LIST

\LIST line

\LIST bline,eline

\LIST ,eline

\LIST bline,

Examples: \LIST 30

This entry lists line 30.

\L. 10,150

This entry lists lines 10 through 150.

\L. 100,

This entry lists line 100 through the end of the file.

\LC.

This entry lists the current line.

**LISTP** 

Sends a list to the local printer; abbreviated as "LP.".

Syntax:

**\LISTP** (line specifications are the same as LIST)

LISTS

Sends a list to the system printer; abbreviated as "\LS.".

Syntax:

**\LISTS** (line specifications are the same as LIST)

\LW.

This variation of the LIST command sets a list window of n lines on each side of the current line anytime a line is entered or changed.

Syntax:  $\LW. n$ 

Example: \LW. 3

When you edit line 60, lines 30, 40, 50, 60, 70, 80, and 90 are displayed on the screen (if lines are numbered in

increments of 10).

\LOAD

Copies the contents of an LW file into your terminal buffer. If this file was not created by McBASI, line numbers are assigned in increments of 10; otherwise, the previously assigned line numbers are intact.

Syntax: \LOAD filename

**NEW** 

Clears your terminal buffer. Each terminal has a 500-line buffer assigned to it. Use the NEW command to begin a new BASIC program. Do not simply delete all the lines in an old program.

Syntax: \NEW

**\REMOVE** 

Deletes a BASIC program from the BSAVE area. All programs are protected by user initials only. LW files may be deleted using the LWU DEL command. After deletion, their names may continue to appear in the \FILES list.

Syntax: \REMOVE filename

**\RENUMBER** 

Renumbers the lines in the range specified, beginning with the line number specified. For an increment other than 10, use **BY** increment.

Syntax: \RENUMBER bline, eline, start BY increment

Example: \RENUMBER 10,100,5 BY 5

This command renumbers lines 10 through 100, starting with line number 5 and incrementing line numbers by 5.

#### \SAVE

Copies the contents of your terminal buffer to an LW file. You specify filename. If filename is already in use, McBASI does not permit you to overwrite it with \SAVE.

Syntax: \SAVE filename

To delete the file, use either the LWU DEL command or: \SAVE (D) filename, where (D) means first delete the file. You must include the parentheses.

#### \SIZE

Determines how many lines of text are in your terminal buffer area. The absolute limit is 500 lines.

Syntax: \SIZE

#### \linenumber

Inserts the specified text (or replaces it if linenumber already exists) into the terminal buffer file, sorted by increasing line number. If you don't enter any text following linenumber, one of two things will happen. If linenumber already exists, it is deleted. If it doesn't exist, a blank line is inserted.

Syntax:

\linenumber

\linenumber text

Example: \15 PRINT A

#### \\text

Inserts text after the last line referenced in the file, at line number 10 greater. If the line 10 greater exists, McBASI won't execute the command. The last line referenced is the last line entered, listed, or edited. After a LOAD, it is the last line in the file.

Syntax: \\text

#### \anything else

Submits a direct execution BASIC language statement.

Example: \?SQRT(13.45)

This command displays the square root of 13.45.

#### McBASI Sample Programs

 In this program, parameters are read from the RUN command until the list is exhausted. DEV=CNN suppresses the normal DONE message from YA. This sends the standard output to the workstation, but does not send the error or debug output. Use RUN MSN MKE CLE BOS DCA or RUN MEM ORD for this example. A step-by-step practice session with this example follows.

This program illustrates a method of looping. The NINT function ensures that B will at some time be exactly equal to 101. A step-by- step practice session with this example follows. No parameters are necessary in the RUN statement.

```
\10 LET A=0
\20 LET B=0
\30 LET A=A+B
\40 LET B=B+1
\50 IF NINT(B)=101 GOTO 30
\60 PRINT A
```

3. In this example, the two character variables are read from the RUN statement. If they are identical, line 20 causes EQUAL to be displayed on the workstation and the program stops at line 100. If they are not equal, line 30 causes NOT EQUAL to be displayed, and lines 40 and 50 use the INDEX function to find out if one is a subset of the other. The semicolons between PRINT list items are omitted, as they are only required to prevent syntax ambiguities. For example, RUN ABC ABC produces EQUAL on the workstation while RUN ABC DEFABCGHI produces NOT EQUAL plus BUT ABC IS WITHIN DEFABCGHI.

```
\10 INPUT A$,B$
\20 IF A$=B$ PRINT "EQUAL": GOTO 100
\30 IF A$< >B$ PRINT "NOT EQUAL"
\40 IF INDEX(A$,B$) < >0/ PRINT "BUT "B$" IS WITHIN "A$
\50 IF INDEX(B$,A$) < >0/ PRINT "BUT "A$" IS WITHIN "B$
\100 STOP
```

4. To illustrate file manipulation, the name of a city or state is taken from the RUN statement and used for an SL command. The output from this command is sent to the file FPWI, via the DEV=F (device = file) clause. After this command is done, line 20 opens the same file (FPWI). Lines are read (line 40), checked for an end-of-file (line 45), and then printed (line 50). This repeats until an end-of-file is detected. Try this RUN statement: RUN MSN

5. Here is an extended example which seeks only the current temperature at the city specified in the RUN statement. In addition, the pseudovariable file name TFILE\$ is used. Try the following RUN statement: RUN MSN

```
\5
     INPUT B$
17
     IF B$="HELP" GOTO 200
/8
     IF B$=" " GOTO 200
19
     IF MID$(B$,3,1)=" " GOTO 200:REM BE SURE IT IS A CITY
10
   KEYIN "SL A "; B$; " DEV=FNN "; TFILE$
\20
     OPEN TFILE$,3
\40 INPUT @3(1),A$
\45 IF MID$(A$,1,4)=EOF$ GOTO 100
\50 LET A=VAL(MID$(A$,18,3))
160
     PRINT "THE TEMPERATURE AT "; B$; " IS "; A
\100 STOP
\200 PRINT "RUN <STATION-ID>"
```

Issued 11/93 14-31

#### **McBASI Editor Practice Session**

The first two sample programs from the previous section are entered and edited here in a detailed, step-by-step description, demonstrating the use of many of the Editor and Interpreter commands.

- 1. Log on to a McIDAS terminal.
- 2. Enter the NEW command to clear your workstation's buffer.

Type: \NEW Press: Enter

The following lines appear on the screen:

\NEW MCBASI - - DONE...

3. To see an online summary of the Editor commands,

Type: \HELP
Press: Enter

4. Now enter your program (or macro) as text, using the McBASI Editor. You may enter your own line numbers, using \# (where # is a specific line number) for each line, incrementing them as you like. Or you can enter two backslashes (\\) before each line of text and the Editor will automatically assign line numbers in increments of ten.

This program reads parameters from the RUN statement until the list is exhausted. DEV=CNN, for device = CRT (C), error (N), and debug (N), suppresses the normal "done" message from the YA command which lists weather data and information text.

To correct an error before you enter a line, use the backspace key, then type the new text. Or, use Editor commands to correct errors. To create the following program, type it exactly as it is printed below.

Type: \10 INPUT A\$
\20 IF LEN(A\$) GOTO 1000
\30 KEYIN "YA SA ";A\$;"DEV=CNN"
\40 KEYIN "YA FT ";A\$;"DEV=CNN"
\50 GOTO 2
\1000 REM FINISHED...

where A\$ is the character variable string A, LEN is the length of the string, and REM is a remark.

5. LIST your program file to check for errors.

Type: \LIST Press: Enter

This command lists the contents of your program file, line by line. Check to be sure there are no typing errors.

6. In line 50, you entered "GOTO 20". Change this to "GOTO 10" using the EDIT command before running the program.

Type: \EDIT 50 /20/10/

Press: Enter

This sequence changes the characters in line 50 that read 20 (old string) to 10 (new string). Enter the old string first, followed by the delimiter, then the new string. This version of EDIT changes only the first occurrence of the old string. To change every occurrence of an old string in a line or group of lines, add "ALL" to the end of the statement. For example: \EDIT 50 /20/10/ALL.

List the program file again to verify the change was made.

 After making all necessary changes, use the RUN statement to execute the program file. Here is an example:

Type: RUN MSN MKE CLE BOS DCA

Press: Enter

The Interpreter runs the program, outputting, for example:

MSN SA 1751 20SCT 6H 132/21/8/2108/011

8. Return to editing the program file and make a few more changes. For example, exchange SA and FT (SA = surface observation, FT = terminal forecasts). "E." is an abbreviation for the EDIT command.

Type: \E. 30 /SA/FT/

Press: Enter

Type:  $\backslash E$ . 40 /FT/SA/

Press: Enter

Also insert a print statement by adding line 45.

Type: \45 PRINT A\$

Press: Enter

The A character variable string (cities) is displayed on your screen when you run the program. This prints the city (MKE, MSN...) before the data for that city. List your program file to be sure the changes were made correctly. The abbreviation of the LIST command is "L.".

Type: \L. Press: Enter

9. Check to see that you've entered the changes correctly, then save your BASIC program file in a special file set up for BASIC language programs. Your program file can be run directly from this storage area. Use the \BSAVE filename command. Assign any name to your program file, following the rules listed on pages 7-3 and 7-4 of the Editor document. The prefix "XX" indicates a temporary file. For example:

Type: \BSAVE XXQAZDOC

Press: Enter

10. List the BASIC program files.

Type: \FILES
Press: Enter

The list should include your LW and BASIC program files, including the BASIC program you just saved.

11. Use the BLOAD command to load your newly saved file.

Type: \BLOAD XXQAZDOC

Press: Enter

If, instead, you had logged off, you must log on and then enter the BLOAD command to regain access to your McBASI program file. The BLOAD command, with the McBASI file name, is all that's necessary to access the McBASI program. BLOAD copies the contents of your BASIC program file into your terminal buffer. Your line numbers should remain intact.

12. Now go back and reedit your program, returning it to its original state. Edit lines 30 and 40, switching SA and FT, and remove line 45.

Type: \E. 30 /FT/SA/

Press: Enter

Type: \E. 40 /SA/FT/

Press: Enter
Type: \DEL. 45
Press: Enter

Once again, list your program file to verify your changes.

Type: \L. Press: Enter

- 13. Use \BSAVE(D) filename again, to save the most recent version of your file.
- 14. Now practice with another example that demonstrates a method of looping.

Type: \NEW Press: Enter

This clears your terminal buffer. Use two backslash characters (\\) for automatic line numbering and enter the lines as follows:

Type: \\ LET A=0 \\ LET B=0 \\ LET A=A+B \\ LET B=B+1 \\ IF NINT(B)=101 GOTO 30 \\ PRINT A

15. Now run the program.

Type: RUN
Press: Enter

The following appears on your screen:

0

16. Make a few changes to improve the program. First, add a PRINT statement for B.

Type: \45 PRINT B

Press: Enter

Change the IF statement in line 5 from "=" to <=".

Type: \E. 50 /=/<=/

Press: Enter

17. List your program file to verify the changes. Then run the program.

Type: RUN
Press: Enter

The following appears on the screen:

0	national desiration of the second
1	
2	
Last two back	
400	automatic line numbering and ent
101	
102	
5151	

The result is a list of the "b" outputs, 0-102, and "a", 5151.

18. Turn to the sample program files and try a few more. If you have questions or problems with any of these commands or sample programs, contact McIDAS User Services.



## Index so III a standard burdens and modify 5-14 MSU 10-36, 10-37 multiply two 5-19 remap 5-1, 5-22 scale 4-33 send to a workstation 4-35, 4-40 statistical brightness values compute 6-1 generate outline 6-24 AA 4-1 initialize file and set options 6-2 AAMAP 5-1 Bright negative in list outline 6-37 AC 6-1 restore outline 6-48 Add subtract two 5-21 constant to an area 5-15 TIP 10-43, 10-57 path points from an LW file 6-41 tracks used 1-12 segment to a path for object tracking 6-41 translate images from one to another 5-26 Advection (ADV) 9-41, 9-44, 9-68, 14-7 values at cursor center 6-11 AFOS headers 9-1 Arithmetic ALSO= vi calculation, store in string table 3-5 Alt key v Altimeter settings 9-11 operations performed on grids 8-12 utility, integer 1-1 Ampersand (&) 1-45 Arrows, display on graphics 2-19 Annotations, display on graphics frame 2-19 Automatic Archive inventory (GOES/GVAR) 4-4 image loading 4-19 ARCLST 4-4 motion vector tracking 11-1 Area **AUTOWINDCO** analyze and store in a grid 8-22 data inputs 11-26 assign navigation codicil to 13-4 delete targets 11-6 average up to four 5-19 initialize status file 11-12 brightness values, modify 5-14 combine 5-18 list targets 11-13 plot targets 11-17 copy 4-1, 4-30, 4-35, 5-1 delete 4-37 position cursor 11-20 select targets automatically 11-1 directory select targets manually 11-23 list 4-25 wind calculations 11-2 modify 4-9 AUTTAR 11-1 disk space needed for 1-12 AUTWIN 11-2 display Averaging false stereo view 5-6 loop of images 4-26 areas 5-19 brightness values 5-18 multiple images 4-30 on graphics frame 4-17 grids 8-12 on image frame 4-11 to reduce image resolution 5-3 on multiple WWWs 4-15 to smooth VAS-derived image 10-50 AVGI 5-3 single images 4-1, 4-8, 4-11 Aviation forecasts 9-9 generate 4-21 AX 6-2 from a grid 8-11 from virtual graphics 4-52 navigation codicil for 6-29

HIRS 10-29

and victoria	temperature estimate 6-11, 6-38, 11-5
	tracking 11-8, 11-15
Bad lines, remove 5-15	CLOUDH 11-5
Bands for satellite areas 14-1	CM 8-9
Best fit line 10-41	CMMD 10-5
Bias values 10-1	CMVA 10-8
Blow up/down image resolution 4-1, 4-8, 4-11,	Codicil (see Navigation codicil)
4-29, 4-46, 5-3	Coefficients, generate 10-22
Brackets ({}) v	Collocated grid values 8-2, 8-5
Brightness temperatures 10-1	Color imagery (see Enhancements)
Brightness values	Color ratio 5-20
average 5-18	Column headers in MD file, change 7-6
modify 5-14	Combine areas 5-18
BSVA 10-1	Commands
BU 4-8	concatenating v
Buffer flakes, remove 5-15	conventions used in documenting v
Buoy data 7-4, 7-16	currently running 1-38, 1-39
	format viii
	helps 1-10
operations performed on grids 8-12	list last command 1-45
	output, sent to destination device vii
C HI'A soundary no salgada asia - A	repeat using a string table 3-1
pilench 1	synchronize 12-9
C 6-4	Compare
CA 4-9	grid and MD file brightness temperatures
CALC 1-1	10-1 and bring to the architecture
Calculate mandatory level data 9-30	grid values 8-2, 10-3
Calibrate POES images 4-53, 4-54	grids for overlapping values 8-12
Calibration reference parameter file 10-31	MD file values 8-5, 10-5, 10-8
CCODE 1-2	COMPGG 8-2
CF 6-5	COMPMG 8-5
CG 8-1	Composite radar images 14-15
CGVA 10-3	Concatenating commands v
Channels within the cursor, list 10-66	Configuration for SSEC's McIDAS 14-13
Charges for CPU cycles 1-40	Contouring
City, locate by name and state 6-21	cloud drift winds 7-16
Classify MD file data 7-3	FOUS14 data 9-7
CLDMAK 5-4	grid files 8-17
Clean up data 5-15	image data 6-7
CLOCK 2-1	IR temperature 6-38
Clock, display on graphics 2-1	isentropic data 9-15
CLOSE 14-18	MD file data 7-16
Cloud 05-01 egamt hevineb-SAV decome of	NMC products 9-35
area combinations 5-18	ship and surface data 9-44
brightness 5-18, 6-11, 6-26, 6-38	stereo 6-7
cover symbols 9-28	streamlines 11-25
heights 11-5	surface observations 7-16, 9-40
pressure estimate 11-5	upper air observations 7-16, 9-68

Contrast stretch	editing
areas 5-14, 5-18	cloud track winds 11-7
frame overlay 6-18	MD file data 7-7
infrared 4-23	surface report 10-14
Conventions for documenting commands v	erase or fill graphics within 2-2
Convert	grid values at center 10-26
dates 1-15	image blowup 4-8
temperatures 1-3	list data in 6-38
TOVS 1-B archive data to raw TIP area 10-63	locate
unito 1.4	cites C 91
Coordinate systems 6-15	1' 1 0 15
Сору	modify.
Copy areas 4-1, 4-30, 4-40	color, size or type 1-6
edit member into an LW file 1-8	lag size 11-22
grid files 8-20	outline image sector extents 4-39
grid files to a workstation or mainframe 8-25	output data 6-11, 6-38
mida 0 10	n saition
image to a workstation or remote host 4-42	at desired point on frame 6-45
LW files 1-24, 1-25, 1-35	at target location 11-20
	delete/list AUTOWINDCO targets 11-6
MD files 7-2, 7-14 navigation codicils 13-11	list satellite parallax at 6-47
	list ten stations closest to 1-21
path to an LW file 6-9 POES areas to a workstation 4-35	list twenty towns closest to 6-50
VASTEXT documentation 10-64	use to edit MD files 7-7
virtual graphics to a workstation 2-12	TV load 4-8, 4-11
COTV 6-7	use to add or delete path point 6-41
Country codes 1-2	CW 2-2
County outlines 6-10	
CPYPTH 6-9	
Create	
grid file 8-20	udago frame 6-4, 6-6, 6-25
LW file 1-25	MD 01 7.14
MD file 7-14	
navigation codicil 13-2	D 6-11
Cross section	Data Base and any Lumin a
meteorogram 9-28	file, plot scatter diagram of 10-41
vertical 5-76	fill 5-14
CSVA 10-11	list for area bound by cursor 6-38
CT 1-3	storage 14-1
C11 6-10	Date, convert Julian/Gregorian 1-15
CU 1-4	DATOLW 1-8
CUR 1-6	Day and time standards vi
Curly brackets ({ }) v	Define abayyan 24 M. Jaguer taum eda ta arah
Cursor	area statistics options 6-2
area values at center 6-11	frame bounds from loop parameters 4-51
contour data in and produce plot 6-7	graphics display parameters 2-7
coordinates at center 6-15	grid header description 8-1
define size, type and color 1-6	loop control parameters 4-28
drawing 2-2, 6-24, 6-28	password for logging on 1-32
	L

Delete	radar area on a graphics frame 4-17
areas 4-37	real-time images 4-26, 4-46
AUTOWINDCO targets 11-6	scatter plot 5-13, 7-12
event scheduler entry 12-6	stereo perspective cloud images 5-4
grid file 8-20	USA image from manually digitized radar
grids 8-12	9-24
LW files 1-25	version number of -MVS software 1-43
MD files 7-14	vertical cross section 9-78
navigation file data 13-1	virtual graphics 2-13, 2-14
path or path segment 6-41	your own graph 2-3
string from a string table 3-6	DIST 6-12
string table 3-11	Distance, measure on navigated frame 6-12
time scheduler entry 12-14	Divergence (DVG) 9-41, 9-44, 9-68, 14-7
wind vector from wind file 11-7	Divide grids 8-12
DELFG 10-13	DMAP 1-9
DELTAR 11-6	Dollar sign (\$) 2-19
Derived	Draw
	area statistics outline 6-48
product imagery 10-18	
satellite imagery 5-9	front through path points 6-22
Destination device, send output to vii	line plot of image box 6-28
DEV= vii, 8-17, 8-19	line plot of image line 6-26
DF 4-11	path for object tracking 6-41
ס-פ עפזע	watch boxes 6-42
Drasap 4-15	your own graph 2-3
DFC 4-17	DTERM= vii
DFLOOP 4-19	DUO 3-1
DFMUL 4-20	DV 11-7
Directory	DYOG 2-3
area (see Area directory)	
graphics frame 2-8	
grid 8-9, 8-12, 8-20	
image frame 6-4, 6-5, 6-25	C. diplot and
MD file 7-14	E 68-1 16 W.1
path 6-41	
string table 3-11	Е 6-15
virtual graphics 2-9	
Disk space for areas, MD files and grid files	Earth coordinates
1-12	area copying 4-1, 4-46
Display 86-0 mesure of hourd sees and mil	at cursor center 6-15
annotations on a graphics frame 2-19	locate 6-45
	TV loads 4-8, 4-11, 4-30, 4-46
area (see Area display)	Edit
clock on the graphics 2-1	MD files 7-4, 7-7
command previously entered 1-45	members, copy 1-8, 1-24
date of the most recent -MVS upgrade 1-43	path latitude, longitude or label 6-41
images for stereo perspective display 5-24	row/column headers in MD files 7-6
images in real time 4-19	string in a string table 3-7
LW file text on a graphics frame 2-16, 2-17	surface report 10-14
MSU area information 10-37	values in MD file 10-73
polar orbital tracks 2-10, 2-18	VASTEXT documentation file 10-54

EG 2-5	Fill surface MD file for VAS processing 10-11
End a McIDAS-MVS session 1-17	FIND 6-21
Energy analysis of vertical sounding 10-52	First guess wind 11-22
ENH 6-16 made and space mind-8 sole	Flags, event scheduler 12-9
Enhancements	Forecasts
automatic 5-14	aviation 9-9
black/white 4-23	TAF 9-5, 9-64
cloud height tinting 6-20	weather service terminal 9-10
color 6-18	Format, command viii
color enhancement for VAS imagery 10-34	FOUS14 data 9-6, 9-7
contrast stretching 4-23, 5-14	FOUS14 data 9-6, 9-7 FOUSL 9-6
deep convection 6-19	FOUSP 9-7
display curves 6-16	Frame (see Graphics, Image frame)
frame overlay 6-18	FRONT 6-22
tint 6-18	Front, drawing 6-22
Erase	FT 9-9
graphics frame 2-5	FTL 9-10
graphics within the cursor 2-2	
virtual graphics 2-6	12 stretch tables 4-23
Error codes for winds 11-21	
ESKE 12-1	G 88-01 revo idab soutras
ESKL 12-4 Sp. of the Tries of A morney	OLO OLO MARIE CONTO
ESKU 12-6	
ESVA 10-14	GA 4-21
ET 6-18	GAC TOVS retrievals, generate 10-19
Event scheduler	GACTOV 10-19
enter an event in 12-1	GARS inventory 4-4
flags 12-9	GD 2-7 0 III-k Ch-k atalogu cool outsmulus
list the entries in 12-4	Generate A Maria Sola
utility 12-6	3-D topographical map 5-25
EVG 2-6	areas 4-21, 4-52, 8-11
EXVA 10-16	coefficients for retrieval estimates 10-22
	color enhancement for VAS imagery 10-34
	contours and streamlines from grids 8-17
	derived satellite imagery products 5-9
smooth with wavelength filter 10-17	energy analysis of vertical sounding 10-52
Fireamans 5-17	enhancements for image frame overlays
surface parameters 10-18	6-18
False stereo view 5-6	GAC TOVS retrievals 10-19
Fast listing for weather text and observations	geostrophic winds for MD files 10-27
9-1 8-01 E-01 orangenco	GOES IR stretch tables 4-23
FASTXT 9-1	graphics movie 8-7
FC 9-5 Ol simbou sell CM fate shirt SAV	grid files 8-20
FGRID 10-18	grids of surface parameters 10-48
Files (also see Grid files, LW files, MD files)	limb corrected MSU areas 10-36
allocation 14-1	LW files 1-25
navigation codicils for areas 13-4	MD files 7-14
protection 1-13	navigation codicils 6-29
Fill graphics within the cursor 2-2	outline of area statistics 6-24

path for object tracking 6-41	write to workstation vi, vii
retrieval grids with recursive filter analysis	Graphs
10-44	brightness 6-1, 6-26, 6-38
RFVA grids from an MD file 10-18	draw your own 2-3
stability indices 9-58	plot 8-hour space time 9-60
stereo perspective cloud images 5-4	scatter plot 5-13, 7-12
TOVS sounding retrievals 10-61	skew T 9-48
VAS image products 10-72	Stuve 9-62
Geostrophic winds, generate for MD file 10-27	GRDDIR 8-9
GESWIN 11-8	GRDIMG 8-11
GFUN 10-22	Greater than (>) key 1-37, 1-46
Global keywords vi	Gregorian date, convert to Julian 1-15
Global strings 3-6, 3-7, 3-10, 3-12	Grid files
GMOVIE 8-7	disk space needed for 1-12
GMS, bands for areas 14-4.1	utility 8-20
GO 6-24	Grid image using lat/lon 6-31
GOES	Grids
bands for areas 14-1	change the headers 8-1, 8-9
list archive inventory 4-4	compare grid values to collocated grid
IR stretch tables 4-23	values 8-2
satellite image, plot VAS retrievals or	compare MD file values to collocated grid
surface data over 10-38	values 8-5
GOLOOP 4-22	contour 7-16, 8-17, 9-40, 9-68
GOSUB 14-18	convert to area 8-11
GOTO 14-18	copy to workstation or remote host 8-25
GPVA 10-24	generate from an MD file 10-44
Gradient operator 5-14	grid directory utility 8-9
Graphics And Water British and All Market Bri	grid file utility 8-20
automatic loop update 4-49, 4-51, 6-49	image data 8-22
clock drawn 2-1	isentropic data 9-15
coordinates 6-15	operations 8-12
county outlines 6-10	plot data 7-16
cursor drawing 2-2	reformat guess wind 11-24
display area on 4-17	retrieval, generate 10-44
erase 2-2, 2-5	RFVA 10-18
fill within the cursor 2-2	ship and surface data 9-44
front drawing 6-22	smooth with wavelength filter 10-47
graph drawing 2-3	streamline 8-17
lettering 2-19	surface parameters 10-48
line width 2-7 m alawardan awom bas	values and the value because the
map outlines 6-31	at cursor location 10-26
movie 8-7	compare 10-3, 10-8
path drawing 6-41	interpolate 10-13
physical graphics list 2-8	VAS grids and MD files, update 10-65
plot text on 2-16, 2-17	write current MDR data into 9-22
position cursor on 6-45	GSVA 11-9
scene 2-8	GU 1-6, 8-8
streamline graphics movie 8-7	Guess grids 11-9, 11-24
track object 6-41	GVAR satellite archive inventory 4-4

**GVVA 10-26** overlays, generate enhancements for **GWVA 10-27** 6-18 position cursor on 6-45 grid on image 6-31 map outlines 6-10, 6-31 modify 5-14, 5-18 Н multiplication 5-18 navigate POES images 4-54 remap projection 5-1, 5-22 Headers 7-6, 8-1 resolution 4-1, 4-8, 4-11, 4-30, 4-46, 5-3 HELP 1-10 - I restrict making the authorities of scatter plot 5-13 HGTSUR 9-11 sector extents, outline 4-39 HIRS area 10-29 smooth 10-50 HIRTBA 10-29 split screen 5-20 HODO 9-13 stereo and motion perspective 5-24 Hodograph, plot 9-13 subtraction 5-21 Horizontally split image 5-20 translate from one area to another 5-26 HOWBIG 1-12 Imagery products, derived 5-9 Hurricanes, track 6-42 IMGGRD 8-22 IMGPRO 5-9 IMSCAT 5-13 Increment command 3-1 Indices, stability 14-9 Initialize AUTOWINDCO status file 11-12 IDVA 10-30 motion vector status file 11-11 IF 14-19 VASTEXT documentation file 10-30 IGG 8-12 VRET MD file row header 10-30 IGTV 8-17 workstation 1-18 IGU 8-20 - Contract stellenes perturbe ealog INPUT 14-19 Image Integer arithmetic utility 1-1 blow up or down 4-8 International master weather station list 1-30 brightness 6-11, 6-38 Interpolate calibrate POES 4-53, 4-54 upper air sounding to standard altimeter contour data 6-7, 6-38 settings 9-11 convert grid to image 8-11 values between grids 10-13 convert TV image to grid file 8-22 IR to flux (or Kelvin) conversion 5-14 coordinates 6-15 IS 4-23 copy area 4-1, 4-30 ISC 9-15 copy to a workstation 4-42 ISENT 9-17 data line plot 6-26 Isentropic data 9-15, 9-17, 9-19 display 4-1, 4-8, 4-11, 4-19, 4-30, 4-46 ISP 9-19 draw line plot of box 6-28 IUMCRP 10-31 false stereo 5-6 IW 11-11 frame IWAUTO 11-12 contents 6-4 directory, list and change 6-4, 6-5, 6-25 display digital area on 4-11 loop, update 4-30, 4-46, 4-49

J roll amanasonaling our case, availabre	LISDAY 1-15
	List
Julian day	area directory 4-25
calendar 14-11	area statistics calculations 6-37
convert to Gregorian 1-15	area values at cursor center 6-11
modily 5-14, 6-18	AUTOWINDCO targets 11-6
died with white warming 5-15	aviation forecasts 9-9
navenn PCT manual 4-5-5	channels within the cursor 10-66
DO B T D MARIN TO PROPERTY	command formats 1-10
K	commands running 1-38, 1-39
and another state of	coordinates at cursor center 6-15
K 6-15	country codes 1-2
11 0 10	FOUS14 data 9-6
110.7011.00 1 1 1 1 1 1 1 1 1 1 1	GOES/GVAR satellite archive inventory 4-4
	graphics frame directory 2-8
-103 -115 (666 661111111110)	grid directory 8-20
Keywords vi, viii	grid value at cursor location 10-26
Training my arreduction distribution of the control	grids 8-12
	image frame's directory 6-4, 6-25
INCORNO 6-9.	international master weather stations 1-30
L STATEMENT	Kavouras sites or schedule entries 12-7, 12-8
I de la base con tracal	LW files 1-9, 1-25, 1-34
Induces stability 14-9	MD file schema, data and records 7-1, 7-8,
LA 4-25	7-10
Lag interpolation, cursor 11-22	navigation file data 13-5
Latitude/longitude	navigation parameters 13-6
area moving 4-1, 4-30	NMC products 9-33
at cursor 6-15	path contents 6-41
lines, display on graphics frame 6-31	pixel value and temperature 6-11, 6-38
locate 6-45	polar orbiting satellite position 1-16
standards for entering in commands vi	project numbers logged on 1-42
TV loads 4-11, 4-46	SA data 9-38
Less than (<) key 1-37, 1-47	satellite parallax at cursor position 6-47
LET 14-21	scheduler entries 12-4, 12-12
Lettering on graphics 2-19	source code lines, previous or next 20 1-46,
Level brightness discrimination 5-18	1-47
Levels, change cursor 1-6	strings in a string table 3-10
LF 6-25	sunrise/sunset for date and location 1-41
LG 2-8	TAF forecasts 9-5, 9-64
Limb correction, apply to MSU area 10-36	ten stations closest to the cursor 1-21
Line/element	terminals logged on 1-39, 1-40
area moving 4-1, 4-30	text files 1-37
cursor center coordinates 6-15	time an orbiting sensor source views a
locate 6-45	ground point 1-33
TV loads 4-11, 4-46	twenty towns closest to the cursor 6-50
Line plot, draw 6-26, 6-28	upper air data 9-71
Linear area combinations 5-18	users logged on 1-40
Linearize data 5-14	VAS retrieval 10-67
Linefeed, prompt with string table 3-3	VASTEXT documentation file 10-33

15-8

	ond: 7-11
virtual graphics directory entries 2-9	LWS 1-22
weather	LWTODA 1-24
aviation forecasts 9-9	LWU 1-25
hourly surface observation 9-51	
service terminal forecasts 9-10	
stations 1-30	
text and observations 9-1, 9-65	
watches 9-76	M PET durant Value
LIST4D 9-21	
LISTAR 11-13	MA 5-14
LISWIN 11-14	MA 5-14 MAIL 1-27
LOAD 4-26	
Load area into an image frame 4-11	Mail messages 1-27 MAKNAV 6-29
Load an RGCOMP file 10-56	
LOCATE 1-16	MAKVPE 10-34
Locate coordinates 6-45	Mandatory level data 9-30, 9-71
Locate towns 6 91	Manually digitized radar data 9-23, 9-22, 9-24
LOCOFF 1 17	MAP 6-31
LOCON 1 19 1 24	Map outline 6-10, 6-31
1 OOD 4 99	MAPORB 2-10
Loop	Master navigation codicil 13-2
activate 4-22	Master station list 1-30
check and display satellite images for 4-26	MC 5-18
control parameters 4-19, 4-28	McBASI 14-17
define 4-28	commands 1-10, 14-18, 14-25
frames 4-51	functions 14-24
graphics frame, update 4-49	practice session 14-32
image frame, update 4-30, 4-46, 4-49	reserved words 14-18
I OVA 10 22	sample programs 14-24
ID and	McIDAS-MVS
LPLOTS 6-28	configuration 14-13
LRAD 12-7	session, start and end 1-17, 1-18
LSCHE 7-1	software version number 1-43
LTEN 1-21	MD files
LVC 9-0	brightness temperatures 10-1
I W files	classify data in 7-3
add path points from 6-41	contour data from 7-16
append output to vii	copy 7-2, 7-14
copy edit member into or from 1-8, 1-24	create or delete 7-14
conveneth to 6.0	directory 7-14
display text on graphics frame 2-16, 2-17	disk space needed for 1-12
func anger 1 0	edit 7-4, 7-7
ligt 1 24	fill for VAS processing 10-11
names, list 1-9	generate geostrophic winds for 10-27
replace output in vii	generate RFVA grids from 10-18
send to remote host or workstation 1-35	grid data from 7-16
size 1-9, 1-25	initialize VRET row header 10-30
space usage 1-22	list data in 7-8
utility 1-25	list wind vectors in 11-14
dulity 1-20	modify row and column headers in 7-6

pack 7-11	Modify area directory 4-9
plot data from 7-16	Motion vector system
plot wind speed and direction from 11-18	acceleration errors 11-21
records 7-10	check status 11-30
reformat guess grids into 11-9, 11-24	cloud heights, temperatures, thickness 11-5
scatter plot 7-12	cloud tracking technique 11-15
schemas, list header and keys 7-1	compute winds 11-15
send to workstation 7-24	contour winds 11-25
set current 7-14	initialize 11-11
update 10-65	keywords, list or change 11-28, 11-33
utility 7-14	list wind file 7-14
values	quality control 11-21
compare 8-5, 10-5, 10-8	number of winds 11-35
edit at cursor location 10-73	wind file
write wind vectors into 11-8, 11-15	delete 7-14
MDC 7-2	edit 11-7
MDCLAS 7-3	generate 7-14
MDE 7-4	initialize 11-11
MDEX 7-6	list directory and header 7-14
MDFIX 7-7	list record 7-8
MDL 7-8	list and plot winds 11-18
MDOA 6-37	move 7-2
MDOX 7-10	set pointer 7-14
MDPACK 7-11	streamlines 11-25
MDR data	Movie, graphics 8-7
	MOVIT 4-30
create USA image 9-23	MR 9-31
plot 9-24	
write into a grid 9-22	MSI mode, generate VAS image products for
MDR 9-22	10-72
MDRIMG 9-23	MSL 1-30
MDRPLT 9-24	MSU
MDSCAT 7-12	areas 10-36, 10-37
MDU 7-14 Ed-1 rendamin anima vicina vidua	calibration reference parameter file 10-31
MDX 7-16	MSUL 10-36
Measure distance on navigated frame 6-12	MSUTBA 10-37
Mercator	MULMUL 4-20
map, draw polar orbital tracks on 2-10	Multiple
projection	
generate navigation codicil for 6-29	commands executed 3-1
remap an area into 5-1	1 v 10aus 4-46
Message, send to system operator 1-44	Withipiy
Meteorograms 9-28, 9-31	areas 0-19
Meteorological parameters 14-7	grius 0-12
METEOSAT, bands for areas 14-4	MW 11-15
MG 9-26	
MGXS 9-28	replace output in vii
Minus (-) command 11-33	
MKMAND 9-30	GS 1 4 1 MXIII
Modify area 5-14	

N	upper air duta 9-73 VAS remuvals in surface data over a COES
N key 5-4, 5-8, 6-19	P 6-46
Navigate POES images 4-54	PAA 4-33
Navigated frame, find distance on 6-12	Pack MD file data records 7-11
Navigation	Parallax calculated 6-47
codicil	Parameters
assign to areas 13-4	graphics 2-7
calculate transform from 13-9	meteorological 14-7
copy from one type to another 13-11	positional viii
generate 6-29, 13-2	real-time image display 4-19
delete data 13-1	real-time image display 4-13 real-time satellite image loop control 4-28
file utility 13-10	stability 14-10
list data 13-5	surface 10-48
	PASS 1-32
list parameters 13-6 ND 13-1	PASSBY 1-33
NK 13-2	Passwords 1-18, 1-32
NKAREA 13-4	PATH 6-41
	OD 2 male than at to
NL 13-5	Path
NLC 13-6	copy to LW file 6-9
NMC products 9-33, 9-35	display for object tracking 6-41
NMCL 9-33	points, draw a front through 6-22
NMCX 9-35	PC 6-45
NT 13-7	Physical graphics frame directory 2-8
NTC 13-9	Pictel (see Raster/pictel)
NVU 13-10	Pixel coordinates 6-15
NXCOPY 13-11	Pixel values 6-11, 6-38
	PLAX 6-47
saudline minges, display with loop numbers	Plot
	2- or 3-dimensional 6-7
Recall a previously entaned common 1 1-45	4-day upper air meteorogram 9-31
Recalling a projection, generate newgation	8-hour space/time graph 9-60
	24-hour SAO meteorogram 9-26
Object tracking, display path for 6-41	displacement of first guess wind vector
OD 6-38	11-22
Online helps 1-10	FOUS14 data 9-7
OPEN 14-21	isentropic data 9-19
Operator, send text message to 1-44	manually digitized radar data 9-24
Outline	MD file data 7-16
draw and restore 6-48	meteorogram cross section 9-28
image sector extents 4-39	NMC products 9-35
region for area statistics calculation 6-24	orbital tracks 2-10, 2-18
Output	path on graphics frame 6-41
data in the cursor 6-38	scatter diagram of a data file 10-41
device, stretch data to fit 4-33	skew T thermodynamic diagram 9-48
Repent a nominand 3-1	stability indices 9-59
	Stuve thermodynamic diagram 9-62
	surface and ship data 9-46, 9-55
	targets from current target file 11-17

text on graphics 2-17	
upper air data 9-73	
VAS retrievals or surface data over a GOES	04 405
satellite image 10-38	QA 4-37
weather watch boxes 9-77	QCWIND 11-21
wind sounding hodograph 9-13	Quality control statistics for winds 11-21
winds on graphics frame 11-18	Question mark (?) 1-38, 1-48, 1-49, 3-6, 3-7,
PLTTAR 11-17	3-10, 3-12
PI.TWIN 11-18	QUIKTI 10-43
Plus sign (+) 7-20	
PLVA 10-38	
PO 6-48	
POES	generate 6-29, 13-2
	R delete de La 13-1
areas, send to workstation 4-35	
bands for areas 14-3	R 11-22
calibration 4-53, 4-54	Radar 3-81 englamana dell
navigation 4-54	
rotate image 180° 4-38	area, display on graphics frame 4-17
POESAA 4-35	Kavouras 12-7, 12-8
Point to grid files 8-20	projection, generate navigation codicil for
Poke a value into an LW file 1-25	6-29
Polar	WSI 14-15
orbital tracks 2-10, 2-18	Raster/pictel
orbiting satellite, list position of 1-16	area moving 4-1, 4-46
stereographic projection	cursor center coordinates 6-15
generate a navigation codicil for 6-29	locating 6-45
remap area into 5-1	TV loads 4-11, 4-30
Position cursor	Real-time
at a target location 11-20	image display 4-19
on a frame 6-45	satellite image loop control parameters 4-28
POSTAR 11-20	satellite images, display with loop numbers
Pound sign (#) 8-17	4-25
Pressure	Recall a previously entered command 1-45
assign cloud pressure 11-22	Rectilinear projection, generate navigation
climatology calculations 11-22	codicil for 6-29
station observation 9-51	Recursive filter analysis, generate retrieval
surface 7-16 9-40	grids with 10-44
unner air 7-16 9-68	Reduce image resolution by averaging 5-3
PRINT 14-99	REM 14-23
Print grid files 8-20	REMAP 5-22
Printer, send output to vii	Remap
Project numbers, list logged on 1-42	area into a different projection 5-1, 5-22
PROMPT 3-3	image data 5-26
Prompt with linefeed 3-3	Remove bad lines and buffer flakes 5-15
Protection	Rename an LW file 1-25
	Renumber grids 8-12, 8-20
file 1-13	REPEAT 3-1
for area, MD file and grid file numbers 14-1	Repeat a command 3-1
value 1-25	Residual distribution of wind file 11-22
PTVA 10-41	residual distribution of willu file 11-22

Resolution	Send
change 4-1, 4-8, 4-11, 4-30, 4-46	areas to a workstation 4-40
image 5-3	fully calibrated POES areas to a workstation
list 4-25, 6-25	4-35
Restore	grid to a workstation 8-25
area statistics outline 6-48	LW file to remote host or workstation 1-35
string table 3-11	mail messages 1-27
Retrieval	MD file to a workstation 7-24
estimates 10-22	most recent image to workstation or remote
grids, generate 10-44	host 4-42
RETURN 15-13	string table to a workstation 3-4
RFVA 10-18, 10-44	text message to the system operator 1-44
RGCOMP file, load or save 10-56	virtual graphic to a workstation 2-12
Rotate POES image 180° 4-38	SENGRD 8-25
ROTIRO 4-38	SENLW 1-35
Row headers in MD file, change 7-6	SENMD2 7-24
RSKL 12-8	Sensor source
RUN 14-23	numbers 14-5
	standards for entering in commands vi
	time it views a ground point 1-33
and the second s	SENST 3-4
S 44-0.04-0 audino bas - 19	SENVG 2-12
list 9-51	SEP 4-42
	SEQ 4-46
SA data 9-38 page role agreement when the	SEQG 4-49
SAO 9-38	Sequential filing system 9-1, 9-65
Satellite	Set
imagery, derived 5-9	file pointer for VAS processing 10-69 grid file 8-20
parallax at cursor position 6-47	MD file number 7-14
Save Bason pava	real-time image display parameters 4-19, 4-21
RGCOMP file 10-56	SETF 12-9
stability indices 9-58	SETLUP 4-51
string table 3-11	SFVA 10-48
SC 9-40	SHEAR 9-43
Scale area 4-33	Shear, calculate vertical 9-43
Scatter plot 5-13, 7-12, 8-2, 8-5, 10-41	Ship data 9-44, 9-46
Scene 2-8, 2-9, 2-14	SHIPC 9-44
Scheduler (see Command Scheduler or Event	SHIPP 9-46
Scheduler)	
Schema, list header and keys 7-1	SHOWME 1-37
SCLG 10-47	Significant level observations 9-30, 9-71
Screen prompts vi	Sinusoidal equal area projection, generate
SECTOR 4-39	navigation codicil for 6-29
SEE 1-34	SKE 12-10
SEG 6-49	SKEWT 9-48
SELTAR 11-23	SKL 12-12
Semicolon (;) v, 11-35	SKU 12-14
SENAA 4-40	SL 9-51
	Slash (/) 1-49

SMOOTH 10-50	String tables
Smooth grids with wavelength filter 10-47	delete 3-11
Smooth image by averaging 10-50	list directories 3-11
SNDVA 10-52	prompt next linefeed 3-3
Software version number 1-43	repeat a command 3-1
Sounding	save and restore 3-11
mover 4-1	send to workstation 3-4
plot on skew T diagram 9-48	utility 3-11
retrievals, TOVS 10-61	Strings (also see Global strings)
upper air, interpolate 9-11	delete from string table 3-6
Source code files, list text from 1-37	edit or enter in a string table 3-7
Source code lines, list 1-46, 1-47	list 3-10
SP 9-55	STUVE 9-62
Space/time graph 9-60	Stuve thermodynamic diagram 9-62
Split screen images 5-20	Subtract
SPVA 10-54	areas 5-21
SS 1-38	grids 8-12
SST 1-39	SUNLIT 1-41
ST 1-40	Sunrise and sunset, list for date and location
STAB 9-58	1-41
STABIL 9-59	Surface
Stability indices 9-58, 9-59, 14-9	data
Stability parameters 14-10	grid and contour 9-40, 9-44
Standards, day and time vi	list 9-51
Start a McIDAS-MVS session 1-18	plot 9-46, 9-55, 10-38
Stations	hourly observations, plot 9-60
IDs 1-30, 7-7	parameters, generate grid of 10-48
list ten closest to cursor position 1-21	report, edit at cursor location 10-14
plot surface hourly observations for 9-60	SVG 2-13
Statistics (see Area statistical brightness values)	SVGA 4-52
Status report 1-38, 1-39	SVRG 10-56
Stereo perspective 5-4, 5-24	SVS 2-14
STG 9-60	Synchronize a command 12-9
STOP 14-24	System status 1-38, 1-39, 1-40
Store Store	Dystem status 1-60, 1-60, 1-40
area analyses in a grid 8-22	88-4 <sup>f</sup> g na *
arithmetic calculation in a string table 3-5	atter plot 5-18 * 12 8-2 8-5 (0-4)
data 14-1	rene 2 8 2 9, 2474
STRDF 5-24	The July Comment Selection After a America
Streamlines	
contour from MD file schema VWIN 11-25	man hat header and leve 7-1 and a man
generate from grids 8-17	TAF 9-64
graphics movie 8-7	TAF forecasts 9-5, 9-64
surface 9-40	Target
upper air 9-68	file, list targets in 11-13
Stretch	plot 11-17
data to fit output device 4-33	position the cursor at 11-20
tables, GOES IR 4-23	select for AUTOWINDCO 11-1, 11-23
tables, GOES III 4-23	TC 3-5
DV 1 (A) des[2	TD 3-6

TE 3-7	TOON 10-59
Temperatures	TOPO3D 5-25
brightness 6-11, 6-38, 10-1	TOVRET 10-61
climatology calculations of clouds 11-5	TOVS
contouring 9-40, 9-68	archive data, convert to raw TIP area 10-63
convert 1-3	processing 10-30, 10-57
cross sections	retrievals 10-61
infrared 6-11, 6-38	TOVS1B 10-63
station observation 9-51, 9-71	Tower workstations 4-18
mafarmat 11.0	TOWNS 6-50
mind skill 10	Towns (20) closest to the cursor center 6-50
Manager 1	TPREP 4-54
communication (mail) 1-27	Track areas used 1-12
log off and on 1-17, 1-18	Track weather systems 6-41
status 1-38, 1-39, 1-40	Translate images from one area to another 5-26
TEXT 9-65	TRNIMG 5-26
Text ANALY AGMIN	TU 3-4, 3-11
annotation 2-19	TXVA 10-64
files	
list 1-34, 1-37	
page backward/forward 1-46, 1-47	
message, send to system operator 1-44	Venically pair mage 0-20
on graphics 2-16, 2-17	VIRT= 11, 2,13
screen, send output to vii	
TC 9 16	U 1-42
TGW 2-17	
Theta surface levels, calculate 9-17	UC 9-68
Three-dimensional displays	UGVAS 10-65
contour TV data 6-7	UL 9-71
	Units of measurement, convert 1-4
display area on image frame 5-6	UP 9-73
motion perspectives 5-24	Update
topographical map 5-25	graphics frame loop 4-49, 6-49
trajectories 9-21, 9-75	image frame loop 4-30, 4-46, 4-49
Ticketed navigation codicil 13-2	VAS guess grids and MD files 10-65
Time and day standards vi	Upgrade, list date of most recent 1-43
Time, current 1-42	Upper air
Time scheduler	data
enter a command in 12-10	calculate theta surface levels for 9-17
list entries in 12-12	grid and contour 9-68
update frames in 6-49	list 9-71
utility 12-14	
TIP area	plot 9-73
convert TOVS 1-B archive data to 10-63	mandatory levels 9-30
examine 10-43	meteorogram, plot 9-31
prepare for TOVS processing 10-57	sounding 9-11
TIP data 4-53, 4-54	USAORB 2-18
TIPTI 10-57	Users, list logged on 1-40
TIRCAL 4-53 TI. 3-10	
11. 0-11.	

V	text and observations, list 9-1, 9-65
98-94 MOOT	watch boxes, plot 9-77
TOF OLD 6/28	watches, list 9-76
VAS	WGVA 11-24
data 9-75	WIDE WORD workstation 4-15
derived images 10-34, 10-50	WINC 11-25
guess grids, update 10-65	Wind
guess profiles 10-24	chill 1-3
image products 10-70, 10-72	contouring 9-40, 9-68, 11-25
processing 10-11, 10-30, 10-69	cross sections 9-78
radiance bias 10-59	
retrieval 10-16, 10-38, 10-67	first guess, plot 11-22
temperature/moisture profiles 10-70	measurement 11-15, 11-35
VAS4D 9-75	plot on graphics frame 11-18
VASTEXT file 10-30, 10-33, 10-54, 10-64	quality control statistics 11-21
VDVA 10-66	surface 9-26
VER 1-43	upper air 9-13, 9-31, 9-48, 9-62
Version number for -MVS software 1-43	vectors 11-2, 11-7, 11-8, 11-14, 11-15
Vertical	WINDS 11-26
cross section, display 9-78	WINO neaders 9-2, 9-65
shear 9-43	Workstation
sounding 10-52	copy a virtual graphic to 2-12
Vertically split image 5-20	initialize 1-18
VIRT= vii, 2-13	send
	areas to 4-35, 4-40
Virtual graphics	grid to 8-25
coordinates 6-15	mainframe MD file to 7-24
copy to a workstation 2-12	string table to 3-4
display 2-13, 2-14	write graphics to vi, vii
erase 2-6	WS 11-28
list 2-9	WSAUTO 11-30
modify 2-14	WSI radar 14-15
specify with VIRT= vii	WTOR 1-44
write to an area 4-52	WWLIST 9-76
VL 10-67	WWPLOT 9-77
VPVA 10-69	Fightated paydention codicil 13-8
VRVA 10-70	Pime and my standards vi
VRVF 10-72	Sime, current 1-42
	Time scheduler
	enter a command in 12-10
	M. El ar garrena tall
A V	XRVA 10-73
plot 9-78	XSECT 9-78
Watch have draw 6.49	
Watch boxes, draw 6-42	
Water vapor cloud tracking (see Motion vector	
system)	
Weather	71 caus 4-53, 4-64
service terminal forecasts 9-10	HECAL 4-63
symbols, display on graphics 2-19	ZA 2-19
	M. 4-10
P1PC111PD1	

15-16

